User Contributed Perl Documentation TAGNAMES(1) TAGNAMES (1)

#### NAME

Image::ExifTool::TagNames - ExifTool tag name documentation

#### DESCRIPTION

This document contains a complete list of ExifTool tag names, organized into tables based on information type. Tag names are used to reference specific meta information extracted from or written to a file.

#### TAG TABLES

The tables listed below give the names of all tags recognized by ExifTool. They contain a total of 28408 tags, with 17642 unique tag

Tag ID, Index# or Sequence is given in the first column of each table. A Tag ID is the computer-readable equivalent of a tag name, and is the identifier that is actually stored in the file. Index# refers to the offset of a value when found at a fixed position within a data block (# is the multiplier for calculating a byte offset: 1, 2, 4 or 8). These offsets may have a decimal part which is used only to differentiate tags with values stored at the same position. (Note that writable tags within binary data blocks are not individually deletable, and the usual alternative is to set them to a value of zero.) Sequence gives the order of values for a serial data stream.

A Tag Name is the handle by which the information is accessed in ExifTool. In some instances, more than one name may correspond to a single tag ID. In these cases, the actual name used depends on the context in which the information is found. Valid characters in a tag name are A-Z, a-z, 0-9, hyphen (-) and underline (). Case is not significant. A question mark ("?") after a tag name indicates that the information is either not understood, not verified, or not very useful -- these tags are not extracted by ExifTool unless the Unknown (-u) option is enabled. Be aware that some tag names are different than the descriptions printed out by default when extracting information with exiftool. To see the tag names instead of the descriptions, use "exiftool -s".

The Writable column indicates whether the tag is writable by ExifTool. Anything but a "no" in this column means the tag is writable. A "yes" indicates writable information that is either unformatted or written using the existing format. Other expressions give details about the format of the stored value, and vary depending on the general type of information. The format name may be followed by a number in square brackets to indicate the number of values written, or the number of characters in a fixed-length string (including a null terminator which is added if required).

A plus sign ("+") after an entry in the Writable column indicates a List tag which supports multiple values and allows individual values to be added and deleted. A slash ("/") indicates a tag that ExifTool will Avoid when writing. These will be edited but not created if another same-named tag may be created instead. To create these tags, the group should be specified. A tilde ("~") indicates a tag this is writable only when the print conversion is disabled (by setting PrintConv to 0, using the -n option, or suffixing the tag name with a "#" character). An exclamation point ("!") indicates a tag that is considered <u>Unsafe</u> to write under normal circumstances. These tags are not written unless specified explicitly (ie. not when wildcards or "all" are used), and care should be taken when editing them manually since they may affect the way an image is rendered. An asterisk ("\*") indicates a Protected tag which is not writable directly, but is written automatically by ExifTool (often when a corresponding Composite or Extra tag is written). A colon (":") indicates a Mandatory tag which may be added automatically when writing (use the API NoMandatory option to avoid creating mandatory EXIF tags). Normally MakerNotes tags may not be deleted individually, but a caret ("^") indicates a <u>Deletable</u>

MakerNotes tag.

The HTML version of these tables also lists possible Values for discrete-valued tags, as well as Notes for some tags. The Values are listed with the computer-readable values on the left of the equals sign ("="), and the human-readable values on the right. The human-readable values are used by default when reading and writing, but the computer-readable values may be accessed by disabling the value conversion with the -n option on the command line, by setting the PrintConv option to 0 in the API, or or on a per-tag basis by adding a hash ("#") after the tag name.

Note: If you are familiar with common meta-information tag names, you may find that some ExifTool tag names are different than expected. The usual reason for this is to make the tag names more consistent across different types of meta information. To determine a tag name, either consult this documentation or run "exiftool -s" on a file containing the information in question.

(This documentation is the result of decades of research, testing and reverse engineering, and is the most complete metadata tag list available anywhere on the internet. It is provided not only for ExifTool users, but more importantly as a public service to help augment the collective knowledge, and is often used as a primary source of information in the development of other metadata software. Please help keep this documentation as accurate and complete as possible, and feed any new discoveries back to ExifTool. A big thanks to everyone who has helped with this so far!)

#### JPEG Tags

This table lists information extracted by ExifTool from JPEG images. See <a href="https://www.w3.org/Graphics/JPEG/jfif3.pdf">https://www.w3.org/Graphics/JPEG/jfif3.pdf</a>> for the JPEG specification.

Tag ID	Tag Name	Writable
 'APP0'		
APPU	JFIF JFXX	JFIF JFIF Extension
	CIFF	CanonRaw
	AVI1	JPEG AVI1
	Ocad	JPEG AVII JPEG Ocad
170011		
'APP1'	EXIF ExtendedXMP	EXIF
		XMP
	XMP	XMP
	QVCI	Casio QVCI
	FLIR	FLIR FFF
	RawThermalImage	no
'APP2'	ICC_Profile	ICC_Profile
	FPXR	FlashPix
	MPF	MPF
	InfiRayVersion	InfiRay Version
	UniformResourceName	no
	PreviewImage	no
'APP3'	Meta	Kodak Meta
	Stim	Stim
	JPS	JPEG JPS
	ThermalData	no
	ImagingData	no
	PreviewImage	no
'APP4'	Scalado	Scalado
	FPXR	FlashPix
	QualcommDualCamera	Qualcomm DualCamera
	InfiRayFactory	InfiRay Factory
	ThermalParams	DJI ThermalParams
	ThermalParams2	DJI ThermalParams2
	ThermalParams3	DJI ThermalParams3
	PreviewImage	no
'APP5'	RMETA	Ricoh RMETA
	SamsungUniqueID	Samsung APP5
	InfiRayPicture	InfiRay Picture

	Thermal Calibration	70
	ThermalCalibration	no
130001	PreviewImage	no
'APP6'	EPPIM	JPEG EPPIM
	NITF	JPEG NITF
	HP_TDHD	HP TDHD
	GoPro	GoPro GPMF
	InfiRayMixMode	InfiRay MixMode
	DJI_DTAT	no
'APP7'	Pentax	Pentax
	Huawei	Unknown
	Qualcomm	Qualcomm
	InfiRayOpMode	InfiRay OpMode
	DJI-DBG	DJI Info
'APP8'	SPIFF	JPEG SPIFF
	InfiRayIsothermal	InfiRay Isothermal
	SEAL	XMP SEAL
'APP9'	MediaJukebox	JPEG MediaJukebox
	InfiRaySensor	InfiRay Sensor
	SEAL	XMP SEAL
'APP10'	Comment	no
	HDRGainCurve	no
'APP11'	JPEG-HDR	JPEG HDR
	JUMBF	Jpeg2000
'APP12'	PictureInfo	APP12 PictureInfo
	Ducky	APP12 Ducky
'APP13'	Photoshop	Photoshop
	Adobe_CM	JPEG AdobeCM
'APP14'	Adobe	JPEG Adobe
'APP15'	GraphicConverter	JPEG GraphConv
'COM'	Comment	yes
'DQT'	DefineQuantizationTable	no
'SOF'	StartOfFrame	JPEG SOF
'Trailer'	AFCP	AFCP
	CanonVRD	CanonVRD
	FotoStation	FotoStation
	PhotoMechanic	PhotoMechanic
	MIE	MIE
	Samsung	Samsung Trailer
	Vivo	Trailer Vivo
	OnePlus	Trailer OnePlus
	Google	Trailer Google
	EmbeddedVideo	no
	Insta360	no
	NikonApp	no
	SonyHiddenData	no
	PreviewImage	yes
	110110W11110030	100

# JPEG AVI1 Tags

This information may be found in APPO of JPEG image data from AVI videos.

Index1	Tag Name	Writable
0	InterleavedField	no

# JPEG Ocad Tags

Tags extracted from the JPEG APPO "Ocad" segment (found in Photobucket images).

Writable

Tag ID	Tag Name	Writable
'Rev'	OcadRevision	no

# JPEG JPS Tags

Tags found in JPEG Stereo (JPS) images.

Index1 Tag Name

10	JPSSeparation	no
11	JPSFlags	no
12	JPSLayout	no
13	JPSType	no
16	JPSComment	no

# JPEG EPPIM Tags

APP6 is used in by the Toshiba PDR-M700 to store a TIFF structure containing PrintIM information.

Tag ID	Tag Name	Writable
0xc4a5	PrintIM	PrintIM

# JPEG NITF Tags

Information in APP6 used by the National Imagery Transmission Format. See

<http://www.gwg.nga.mil/ntb/baseline/docs/n010697/bwcguide25aug98.pdf>
for the official specification.

Index1	Tag Name	Writable
0	NITFVersion	no
2	ImageFormat	no
3	BlocksPerRow	no
5	BlocksPerColumn	no
7	ImageColor	no
8	BitDepth	no
9	ImageClass	no
10	JPEGProcess	no
11	Quality	no
12	StreamColor	no
13	StreamBitDepth	no
14	Flags	no

### JPEG SPIFF Tags

This information is found in APP8 of SPIFF-style JPEG images (the "official" yet rarely used JPEG file format standard: Still Picture Interchange File Format). See <a href="http://www.jpeg.org/public/spiff.pdf">http://www.jpeg.org/public/spiff.pdf</a> for the official specification.

Index1	Tag Name	Writable
0	SPIFFVersion	no
2	ProfileID	no
3	ColorComponents	no
6	ImageHeight	no
10	ImageWidth	no
14	ColorSpace	no
15	BitsPerSample	no
16	Compression	no
17	ResolutionUnit	no
18	YResolution	no
22	XResolution	no

## JPEG MediaJukebox Tags

Tags found in the XML metadata of the APP9 "Media Jukebox" segment.

Tag Name	Writable
Album	no
Caption	no
Date	no
Keywords	no
Name	no

People	no
Places	no
Tool_Name	no
Tool_Version	no

### JPEG HDR Tags

Information extracted from APP11 of a JPEG-HDR image.

Tag Name	Writable
RatioImage	no
Alpha	no
Beta	no
CorrectionMethod	no
Ln0	no
Ln1	no
S2n	no
JPEG-HDRVersion	no
	RatioImage Alpha Beta CorrectionMethod Ln0 Ln1 S2n

### JPEG AdobeCM Tags

The APP13 "Adobe\_CM" segment presumably contains color management information, but the meaning of the data is currently unknown. If anyone has an idea about what this means, please let me know.

Index2	Tag Name	Writable
0	AdobeCMType	no

### JPEG Adobe Tags

The APP14 "Adobe" segment stores image encoding information for DCT filters. This segment may be copied or deleted as a block using the Extra "Adobe" tag, but note that it is not deleted by default when deleting all metadata because it may affect the appearance of the image.

Index2	Tag Name	Writable
0	DCTEncodeVersion	no
1	APP14Flags0	no
2	APP14Flags1	no
3	ColorTransform	no

# JPEG GraphConv Tags

APP15 is used by GraphicConverter to store JPEG quality.

Tag ID	Tag Name	Writable
' Q '	Quality	no

### JPEG SOF Tags

This information is extracted from the JPEG Start Of Frame segment.

Tag Name	Writable
BitsPerSample	no
ColorComponents	no
EncodingProcess	no
ImageHeight	no
ImageWidth	no
YCbCrSubSampling	no

# EXIF Tags

EXIF stands for "Exchangeable Image File Format". This type of information is formatted according to the TIFF specification, and may be found in JPG, TIFF, PNG, JP2, PGF, MIFF, HDP, PSP and XCF images, as

well as many TIFF-based RAW images, and even some AVI and MOV videos.

The EXIF meta information is organized into different Image File Directories (IFD's) within an image. The names of these IFD's correspond to the ExifTool family 1 group names. When writing EXIF information, the default Group listed below is used unless another group is specified.

Mandatory tags (indicated by a colon after the Writable type) may be added automatically with default values when creating a new IFD, and the IFD is removed automatically when deleting tags if only defaultvalued mandatory tags remain.

The table below lists all EXIF tags. Also listed are TIFF, DNG, HDP and other tags which are not part of the EXIF specification, but may co-exist with EXIF tags in some images. Tags which are part of the EXIF 2.32 specification have an underlined Tag Name in the HTML version of this documentation. See

<https://web.archive.org/web/20190624045241if\_/http://www.cipa.jp:80/std/documents</pre> /e/DC-008-Translation-2019-E.pdf>

for the official EXIF 2.32 specification.

Tag ID	Tag Name	Group	Writable
0x0001	InteropIndex	InteropIFD	string!
0x0002	InteropVersion	InteropIFD	
0x000b	ProcessingSoftware	IFD0	string
0x00fe	SubfileType	IFD0	int32u!
0x00ff	OldSubfileType	IFD0	int16u!
0x0100	ImageWidth	IFD0	int32u!
0x0101	ImageHeight	IFD0	int32u!
0x0102	BitsPerSample	IFD0	int16u[n]!
0x0103	Compression	IFD0	int16u!:
0x0106	PhotometricInterpretation	IFD0	int16u!
0x0107	Thresholding	IFD0	int16u!
0x0108	CellWidth	IFD0	int16u!
0x0109	CellLength	IFD0	int16u!
0x010a	FillOrder	IFD0	int16u!
0x010d	DocumentName	IFD0	string
0x010e	ImageDescription	IFD0	string
0x010f	Make	IFD0	string
$0 \times 0110$	Model	IFD0	string
$0 \times 0111$	StripOffsets	-	no
	OtherImageStart	_	no
	PreviewJXLStart	_	no
	StripOffsets	_	no
	PreviewImageStart	IFD0	int32u*
	PreviewImageStart	All	int32u*
	JpgFromRawStart	SubIFD2	int32u*
$0 \times 0112$	Orientation	IFD0	int16u
$0 \times 0115$	SamplesPerPixel	IFD0	int16u!
$0 \times 0116$	RowsPerStrip	IFD0	int32u!
$0 \times 0117$	StripByteCounts	_	no
	OtherImageLength	_	no
	PreviewJXLLength	_	no
	StripByteCounts	_	no
	PreviewImageLength	IFD0	int32u*
	PreviewImageLength	All	int32u*
	JpgFromRawLength	SubIFD2	int32u*
$0 \times 0118$	MinSampleValue	IFD0	int16u
0x0119	MaxSampleValue	IFD0	int16u
0x011a	XResolution	IFD0	rational64u:
0x011b	YResolution	IFD0	rational64u:
0x011c	PlanarConfiguration	IFD0	int16u!
0x011d	PageName	IFD0	string
0x011e	XPosition	IFD0	rational64u
0x011f	YPosition	IFD0	rational64u
$0 \times 0120$	FreeOffsets	_	no
$0 \times 0121$	FreeByteCounts	- TED 0	no
0x0122	GrayResponseUnit	IFD0	int16u

	ExifTool 1	L3.24	Tag	Names		-
0x0123	GrayResponseCurve		-			no
0x0124	T40ptions		-			no
0x0125	T60ptions		-			no
$0 \times 0128$	ResolutionUnit		IFI			int16u:
$0 \times 0129$	PageNumber		IFI -	00		int16u[2]
0x012c 0x012d	ColorResponseUnit TransferFunction		- IFI	20		no int16u[768]!
0x012d	Software		IFI	_		string
0x0132	ModifyDate		IFI			string
0x013b	Artist		IFI	00		string
0x013c	HostComputer		IFI	00		string
0x013d	Predictor		IFI			int16u!
0x013e	WhitePoint		IFI			rational64u[2]
0x013f 0x0140	PrimaryChromaticitie ColorMap	28	IFI -	00		rational64u[6]
0x0141	HalftoneHints		IFI	00		int16u[2]
0x0142	TileWidth		IFI			int32u!
0x0143	TileLength		IFI	00		int32u!
$0 \times 0144$	TileOffsets		-			no
$0 \times 0145$	TileByteCounts		-			no
$0 \times 0146$ $0 \times 0147$	BadFaxLines CleanFaxData		_			no
0x0147 $0x0148$	ConsecutiveBadFaxLir	nes	_			no no
0x014a	SubIFD	100	_			EXIF
	A100DataOffset		IFI	00		no
0x014c	InkSet		IFI	00		int16u
0x014d	InkNames		-			no
$0 \times 014e$ $0 \times 0150$	NumberofInks		_			no
0x0150 $0x0151$	DotRange TargetPrinter		- IFI	00		no string
0x0151	ExtraSamples		_			no
0x0153	SampleFormat		Suk	OIFD		no
$0 \times 0154$	SMinSampleValue		-			no
0x0155	SMaxSampleValue		-			no
0x0156	TransferRange		-			no
$0 \times 0157$ $0 \times 0158$	ClipPath XClipPathUnits		_			no no
0x0150 $0x0159$	YClipPathUnits		_			no
0x015a	Indexed		-			no
0x015b	JPEGTables		-			no
0x015f	OPIProxy		-			no
0x0190	GlobalParametersIFD		-			EXIF
$0 \times 0191$ $0 \times 0192$	ProfileType FaxProfile		_			no no
0x0192	CodingMethods		_			no
0x0194	VersionYear		-			no
$0 \times 0195$	ModeNumber		-			no
0x01b1	Decode		-			no
0x01b2 0x01b3	DefaultImageColor T82Options		-			no
0x01b3	JPEGTables		_			no no
0x0200	JPEGProc		_			no
0x0201	ThumbnailOffset		IFI	01		int32u*
	ThumbnailOffset		IFI			int32u*
	ThumbnailOffset			oIFD		int32u*
	PreviewImageStart PreviewImageStart		Mak IFI		S	int32u* int32u*
	JpgFromRawStart			DIFD		int32u*
	JpgFromRawStart		IFI			int32u*
	OtherImageStart			oIFD1		int32u*
	OtherImageStart		Suk	oIFD2		int32u*
	OtherImageStart					no
$0 \times 0202$	ThumbnailLength		IFI			int32u*
	ThumbnailLength ThumbnailLength		IFI Sub	DU DIFD		int32u* int32u*
	PreviewImageLength				s	int32u*
	PreviewImageLength		IFI	00		int32u*
	JpgFromRawLength			OIFD		int32u*
	JpgFromRawLength		IFI			int32u*
	OtherImageLength		Sub	oIFD1		int32u*

	OtherImageLength	CubteD2	in+2011*
	OtherImageLength	SubIFD2	int32u*
00202	OtherImageLength JPEGRestartInterval	_	no
$0 \times 0203$		_	no
$0 \times 0205$ $0 \times 0206$	JPEGLosslessPredictors JPEGPointTransforms	_	no
0x0200		_	no
0x0207 0x0208	JPEGQTables JPEGDCTables	_	no
0x0208 $0x0209$	JPEGACTables	_	no
0x0209 $0x0211$	YCbCrCoefficients	IFD0	no rational64u[3]!
0x0211 0x0212	YCbCrSubSampling	IFD0	int16u[2]!
0x0212 0x0213	YCbCrPositioning	IFD0 IFD0	int16u!:
0x0213 $0x0214$	ReferenceBlackWhite	IFD0	rational64u[6]
0x0214	StripRowCounts	-	no
0x0221	ApplicationNotes	IFD0	XMP
0x02DC	RenderingIntent	-	no
0x03e7	USPTOMiscellaneous	_	no
0x1000	RelatedImageFileFormat	InteropIFD	
0x1001	RelatedImageWidth	InteropIFD	
0x1001	RelatedImageHeight	InteropIFD	
0x4746	Rating	IFD0	int16u/
0x4747	XP_DIP_XML	_	no
0x4748	StitchInfo	_	Microsoft Stitch
0x4749	RatingPercent	IFD0	int16u/
0x5001	ResolutionXUnit	_	no
0x5002	ResolutionYUnit	_	no
0x5003	ResolutionXLengthUnit	_	no
0x5004	ResolutionYLengthUnit	_	no
0x5005	PrintFlags	_	no
0x5006	PrintFlagsVersion	_	no
0x5007	PrintFlagsCrop	_	no
0x5008	PrintFlagsBleedWidth	_	no
0x5009	PrintFlagsBleedWidthScale	_	no
0x500a	HalftoneLPI	_	no
0x500b	HalftoneLPIUnit	_	no
0x500c	HalftoneDegree	_	no
0x500d	HalftoneShape	_	no
0x500e	HalftoneMisc	_	no
0x500f	HalftoneScreen	-	no
0x5010	JPEGQuality	-	no
0x5011	GridSize	-	no
0x5012	ThumbnailFormat	_	no
0x5013	ThumbnailWidth	_	no
0x5014	ThumbnailHeight	_	no
0x5015	ThumbnailColorDepth	-	no
0x5016	ThumbnailPlanes	-	no
0x5017	ThumbnailRawBytes	_	no
0x5018	ThumbnailLength	_	no
0x5019	ThumbnailCompressedSize	_	no
0x501a	ColorTransferFunction	_	no
0x501b	ThumbnailData	_	no
0x5020 0x5021	ThumbnailImageWidth	_	no
	ThumbnailImageHeight ThumbnailRitgRawSawnla	_	no
0x5022	ThumbnailBitsPerSample	_	no
0x5023 0x5024	ThumbnailCompression ThumbnailPhotometricInterp	_	no
0x5024 $0x5025$	ThumbnailDescription	) =	no
0x5025	ThumbnailEquipMake	_	no
0x5020 $0x5027$	ThumbnailEquipMake ThumbnailEquipModel		no no
0x5027	ThumbnailStripOffsets	_	no
0x5020	ThumbnailOrientation	_	no
0x5025	ThumbnailSamplesPerPixel	_	no
0x502b	ThumbnailRowsPerStrip	_	no
0x502c	ThumbnailStripByteCounts	_	no
0x502d	ThumbnailResolutionX	_	no
0x502e	ThumbnailResolutionY	_	no
0x502f	ThumbnailPlanarConfig	_	no
0x5030	ThumbnailResolutionUnit	_	no
0x5031	ThumbnailTransferFunction	_	no
0x5032	ThumbnailSoftware	_	no
0x5033	ThumbnailDateTime	_	no

0x5034	ThumbnailArtist	-	no
0x5035	ThumbnailWhitePoint	_	no
0x5036	ThumbnailPrimaryChromatic	ities -	no
0x5037	ThumbnailYCbCrCoefficients	s -	no
0x5038	ThumbnailYCbCrSubsampling	_	no
	<b>.</b>		
0x5039	ThumbnailYCbCrPositioning	-	no
0x503a	ThumbnailRefBlackWhite	_	no
0x503b	ThumbnailCopyright	_	no
0x5090	LuminanceTable	-	no
0x5091	ChrominanceTable	_	no
0x5100	FrameDelay	_	no
0x5101	LoopCount	-	no
0x5102	GlobalPalette	_	no
0x5103	IndexBackground	-	no
0x5104	IndexTransparent	_	no
0x5110	PixelUnits	_	no
0x5111	PixelsPerUnitX	-	no
0x5112	PixelsPerUnitY	_	no
0x5113	PaletteHistogram		
	2	_	no
0x7000	SonyRawFileType	-	no
0x7010	SonyToneCurve	_	no
	<del>-</del>	Cook TED	
0x7031	VignettingCorrection	SubIFD	int16s!
0x7032	VignettingCorrParams	SubIFD	int16s[17]!
0x7034	ChromaticAberrationCorrect	tion SubTED	int16gl
0x7035	ChromaticAberrationCorrPar	rams SublfD	int16s[33]!
0x7036	DistortionCorrection	SubIFD	int16s!
0x7037	DistortionCorrParams	SubIFD	int16s[17]!
0x7038	SonyRawImageSize	SubIFD	int32u[2]!
0x7310	BlackLevel	SubIFD	int16u[4]!
0x7313	WB RGGBLevels	SubIFD	int16s[4]!
	<del>_</del>		
0x74c7	SonyCropTopLeft	SubIFD	int32u[2]!
0x74c8	SonyCropSize	SubIFD	int32u[2]!
		Subilib	
0x800d	ImageID	_	no
0x80a3	WangTag1	-	no
0x80a4	WangAnnotation	_	no
0x80a5	WangTag3	_	no
0x80a6	WangTag4	_	no
0x80b9	ImageReferencePoints	_	
		_	no
0x80ba	RegionXformTackPoint	-	no
0x80bb	WarpOuadrilateral	_	no
0x80bc	AffineTransformMat		
		_	no
0x80e3	Matteing	-	no
0x80e4	DataType	_	no
0x80e5	ImageDepth	-	no
0х80еб	TileDepth	-	no
0x8214	ImageFullWidth	_	no
0x8215	ImageFullHeight	_	no
0x8216	TextureFormat	_	no
0x8217	WrapModes	_	no
	Widphodeb		110
0x8218	- C -		
	FovCot	-	no
0x8219	FovCot MatrixWorldToScreen		
	MatrixWorldToScreen	-	no
0x821a	MatrixWorldToScreen MatrixWorldToCamera	- - -	no no
	MatrixWorldToScreen	- - -	no
0x821a 0x827d	MatrixWorldToScreen MatrixWorldToCamera Model2	- - - SubIFD	no no no
0x821a 0x827d 0x828d	MatrixWorldToScreen MatrixWorldToCamera Model2 CFARepeatPatternDim	- - - - SubIFD	no no no int16u[2]!
0x821a 0x827d 0x828d 0x828e	MatrixWorldToScreen MatrixWorldToCamera Model2 CFARepeatPatternDim CFAPattern2	- - - - SubIFD SubIFD	no no no
0x821a 0x827d 0x828d	MatrixWorldToScreen MatrixWorldToCamera Model2 CFARepeatPatternDim		no no no int16u[2]!
0x821a 0x827d 0x828d 0x828e 0x828f	MatrixWorldToScreen MatrixWorldToCamera Model2 CFARepeatPatternDim CFAPattern2 BatteryLevel	SubIFD	no no no int16u[2]! int8u[n]! no
0x821a 0x827d 0x828d 0x828e 0x828f 0x8290	MatrixWorldToScreen MatrixWorldToCamera Model2 CFARepeatPatternDim CFAPattern2 BatteryLevel KodakIFD	SubIFD - -	no no no int16u[2]! int8u[n]! no Kodak IFD
0x821a 0x827d 0x828d 0x828e 0x828f 0x8290 0x8298	MatrixWorldToScreen MatrixWorldToCamera Model2 CFARepeatPatternDim CFAPattern2 BatteryLevel KodakIFD Copyright	SubIFD - - IFD0	no no int16u[2]! int8u[n]! no Kodak IFD string
0x821a 0x827d 0x828d 0x828e 0x828f 0x8290	MatrixWorldToScreen MatrixWorldToCamera Model2 CFARepeatPatternDim CFAPattern2 BatteryLevel KodakIFD	SubIFD - -	no no no int16u[2]! int8u[n]! no Kodak IFD
0x821a 0x827d 0x828d 0x828e 0x828f 0x8290 0x8298 0x829a	MatrixWorldToScreen MatrixWorldToCamera Model2 CFARepeatPatternDim CFAPattern2 BatteryLevel KodakIFD Copyright ExposureTime	SubIFD - - IFD0 ExifIFD	no no int16u[2]! int8u[n]! no Kodak IFD string rational64u
0x821a 0x827d 0x828d 0x828e 0x828f 0x8290 0x8298 0x829a 0x829d	MatrixWorldToScreen MatrixWorldToCamera Model2 CFARepeatPatternDim CFAPattern2 BatteryLevel KodakIFD Copyright ExposureTime FNumber	SubIFD - - IFD0	no no int16u[2]! int8u[n]! no Kodak IFD string rational64u rational64u
0x821a 0x827d 0x828d 0x828e 0x828f 0x8290 0x8298 0x829a 0x829d 0x82a5	MatrixWorldToScreen MatrixWorldToCamera Model2 CFARepeatPatternDim CFAPattern2 BatteryLevel KodakIFD Copyright ExposureTime FNumber MDFileTag	SubIFD - - IFD0 ExifIFD	no no int16u[2]! int8u[n]! no Kodak IFD string rational64u
0x821a 0x827d 0x828d 0x828e 0x828f 0x8290 0x8298 0x829a 0x829d	MatrixWorldToScreen MatrixWorldToCamera Model2 CFARepeatPatternDim CFAPattern2 BatteryLevel KodakIFD Copyright ExposureTime FNumber	SubIFD - - IFD0 ExifIFD	no no int16u[2]! int8u[n]! no Kodak IFD string rational64u rational64u
0x821a 0x827d 0x828d 0x828e 0x828f 0x8290 0x8298 0x829a 0x829d 0x82a5 0x82a6	MatrixWorldToScreen MatrixWorldToCamera Model2 CFARepeatPatternDim CFAPattern2 BatteryLevel KodakIFD Copyright ExposureTime FNumber MDFileTag MDScalePixel	SubIFD - - IFD0 ExifIFD	no no int16u[2]! int8u[n]! no Kodak IFD string rational64u rational64u no no
0x821a 0x827d 0x828d 0x828e 0x828f 0x8290 0x8298 0x829a 0x829d 0x82a5 0x82a6 0x82a7	MatrixWorldToScreen MatrixWorldToCamera Model2 CFARepeatPatternDim CFAPattern2 BatteryLevel KodakIFD Copyright ExposureTime FNumber MDFileTag MDScalePixel MDColorTable	SubIFD - - IFD0 ExifIFD	no no no int16u[2]! int8u[n]! no Kodak IFD string rational64u rational64u no no no
0x821a 0x827d 0x828d 0x828e 0x828f 0x8290 0x8298 0x829a 0x829d 0x82a5 0x82a6 0x82a7 0x82a8	MatrixWorldToScreen MatrixWorldToCamera Model2 CFARepeatPatternDim CFAPattern2 BatteryLevel KodakIFD Copyright ExposureTime FNumber MDFileTag MDScalePixel MDColorTable MDLabName	SubIFD - - IFD0 ExifIFD	no no int16u[2]! int8u[n]! no Kodak IFD string rational64u rational64u no no
0x821a 0x827d 0x828d 0x828e 0x828f 0x8290 0x8298 0x829a 0x829d 0x82a5 0x82a6 0x82a7	MatrixWorldToScreen MatrixWorldToCamera Model2 CFARepeatPatternDim CFAPattern2 BatteryLevel KodakIFD Copyright ExposureTime FNumber MDFileTag MDScalePixel MDColorTable	SubIFD - - IFD0 ExifIFD	no no no int16u[2]! int8u[n]! no Kodak IFD string rational64u rational64u no no no
0x821a 0x827d 0x828d 0x828e 0x828f 0x8290 0x8298 0x829a 0x829d 0x82a5 0x82a6 0x82a7 0x82a8 0x82a9	MatrixWorldToScreen MatrixWorldToCamera Model2 CFARepeatPatternDim CFAPattern2 BatteryLevel KodakIFD Copyright ExposureTime FNumber MDFileTag MDScalePixel MDColorTable MDLabName MDSampleInfo	SubIFD - - IFD0 ExifIFD	no no no int16u[2]! int8u[n]! no Kodak IFD string rational64u rational64u no no no no
0x821a 0x827d 0x828d 0x828e 0x828f 0x8290 0x8298 0x829a 0x829d 0x82a5 0x82a6 0x82a7 0x82a8 0x82a9 0x82a9	MatrixWorldToScreen MatrixWorldToCamera Model2 CFARepeatPatternDim CFAPattern2 BatteryLevel KodakIFD Copyright ExposureTime FNumber MDFileTag MDScalePixel MDColorTable MDLabName MDSampleInfo MDPrepDate	SubIFD - - IFD0 ExifIFD	no no no int16u[2]! int8u[n]! no Kodak IFD string rational64u rational64u no no no no no
0x821a 0x827d 0x828d 0x828e 0x828f 0x8290 0x8298 0x829a 0x829d 0x82a5 0x82a6 0x82a7 0x82a8 0x82a9 0x82a9	MatrixWorldToScreen MatrixWorldToCamera Model2 CFARepeatPatternDim CFAPattern2 BatteryLevel KodakIFD Copyright ExposureTime FNumber MDFileTag MDScalePixel MDColorTable MDLabName MDSampleInfo MDPrepDate MDPrepTime	SubIFD - - IFD0 ExifIFD	no no no int16u[2]! int8u[n]! no Kodak IFD string rational64u rational64u no no no no
0x821a 0x827d 0x828d 0x828e 0x828f 0x8290 0x8298 0x829a 0x829d 0x82a5 0x82a6 0x82a7 0x82a8 0x82a9 0x82a9	MatrixWorldToScreen MatrixWorldToCamera Model2 CFARepeatPatternDim CFAPattern2 BatteryLevel KodakIFD Copyright ExposureTime FNumber MDFileTag MDScalePixel MDColorTable MDLabName MDSampleInfo MDPrepDate	SubIFD - - IFD0 ExifIFD	no no no int16u[2]! int8u[n]! no Kodak IFD string rational64u rational64u no no no no no
0x821a 0x827d 0x828d 0x828e 0x828f 0x8290 0x8298 0x829a 0x829d 0x82a5 0x82a6 0x82a7 0x82a8 0x82a9 0x82a9 0x82ab 0x82ac	MatrixWorldToScreen MatrixWorldToCamera Model2 CFARepeatPatternDim CFAPattern2 BatteryLevel KodakIFD Copyright ExposureTime FNumber MDFileTag MDScalePixel MDColorTable MDLabName MDSampleInfo MDPrepDate MDPrepTime MDFileUnits	SubIFD - IFD0 ExifIFD ExifIFD	no no no int16u[2]! int8u[n]! no Kodak IFD string rational64u rational64u no no no no no no no
0x821a 0x827d 0x828d 0x828e 0x828f 0x8290 0x8298 0x829a 0x829d 0x82a5 0x82a6 0x82a7 0x82a8 0x82a9 0x82a2 0x82a0 0x82a2	MatrixWorldToScreen MatrixWorldToCamera Model2 CFARepeatPatternDim CFAPattern2 BatteryLevel KodakIFD Copyright ExposureTime FNumber MDFileTag MDScalePixel MDColorTable MDLabName MDSampleInfo MDPrepDate MDPrepTime MDFileUnits PixelScale	SubIFD IFD0 ExifIFD	no no no int16u[2]! int8u[n]! no Kodak IFD string rational64u rational64u no
0x821a 0x827d 0x828d 0x828e 0x828f 0x8290 0x8298 0x829a 0x829d 0x82a5 0x82a6 0x82a7 0x82a8 0x82a9 0x82a9 0x82ab 0x82ac	MatrixWorldToScreen MatrixWorldToCamera Model2 CFARepeatPatternDim CFAPattern2 BatteryLevel KodakIFD Copyright ExposureTime FNumber MDFileTag MDScalePixel MDColorTable MDLabName MDSampleInfo MDPrepDate MDPrepTime MDFileUnits	SubIFD - IFD0 ExifIFD ExifIFD	no no no int16u[2]! int8u[n]! no Kodak IFD string rational64u rational64u no no no no no no no

0x8336	AdventRevision	_	no
0x835c	UIC1Tag	_	no
0x835d	UIC2Tag	_	no
0x835e	UIC3Tag	_	no
0x835f	UIC4Tag	_	no
0x83bb	IPTC-NAA	IFD0	IPTC
0x847e	IntergraphPacketData	-	no
0x847f	IntergraphFlagRegisters	_	no
0x8480	IntergraphMatrix	IFD0	double[n]
		IFDU	
0x8481	INGRReserved	-	no
0x8482	ModelTiePoint	IFD0	double[n]
0x84e0	Site	_	no
0x84e1	ColorSequence	_	no
0x84e2	IT8Header	-	no
0x84e3	RasterPadding	_	no
0x84e4	BitsPerRunLength	-	no
0x84e5	BitsPerExtendedRunLength	_	no
0x84e6	ColorTable	_	no
0x84e7	ImageColorIndicator	_	no
0x84e8	BackgroundColorIndicator	_	no
0x84e9	ImageColorValue	_	no
0x84ea	BackgroundColorValue	_	no
0x84eb	PixelIntensityRange	_	no
0x84ec	TransparencyIndicator	_	no
0x84ed	ColorCharacterization		
	HCUsage	_	no
0x84ee		_	no
0x84ef	TrapIndicator	_	no
0x84f0	CMYKEquivalent	_	no
0x8546	SEMInfo	IFD0	string
0x8568	AFCP_IPTC	-	IPTC
0x85b8	PixelMagicJBIGOptions	-	no
0x85d7	JPLCartoIFD	-	no
0x85d8	ModelTransform	IFD0	double[16]
0x8602	WB_GRGBLevels	_	no
0x8606	LeafData	_	Leaf
0x8649	PhotoshopSettings	IFD0	Photoshop
0x8769	ExifOffset	IFD0	EXIF
0x8773	ICC_Profile	IFD0	ICC Profile
0x877f	TIFF_FXExtensions	_	no
0x8780	MultiProfiles	_	no
0x8781	SharedData	_	no
0x8782	T88Options	_	no
0x8762	ImageLayer	_	
			no
0x87af	GeoTiffDirectory	IFD0	int16u[0.5]
0x87b0	GeoTiffDoubleParams	IFD0	double[0.125]
0x87b1	GeoTiffAsciiParams	IFD0	string
0x87be	JBIGOptions	-	no
0x8822	ExposureProgram	ExifIFD	int16u
0x8824	SpectralSensitivity	ExifIFD	string
0x8825	GPSInfo	IFD0	GPS
0x8827	ISO	ExifIFD	int16u[n]
0x8828	Opto-ElectricConvFactor	-	no
0x8829	Interlace	_	no
0x882a	TimeZoneOffset	ExifIFD	int16s[n]
0x882b	SelfTimerMode	ExifIFD	int16u
0x8830	SensitivityType	ExifIFD	int16u
0x8831	StandardOutputSensitivity		int32u
0x8832	RecommendedExposureIndex	ExifIFD	int32u
0x8833	ISOSpeed	ExifIFD	int32u
0x8834	ISOSpeedLatitudeyyy	ExifIFD	int32u
0x8835	ISOSpeedLatitudeyyy ISOSpeedLatitudezzz	ExifIFD	int32u
	FaxRecvParams	TATTILD	
0x885c		_	no
0x885d	FaxSubAddress	_	no
0x885e	FaxRecvTime	-	no
0x8871		-	no
	FedexEDR		
0x888a	LeafSubIFD	-	Leaf SubIFD
0x9000	LeafSubIFD ExifVersion	- ExifIFD	undef:
0x9000 0x9003	LeafSubIFD ExifVersion DateTimeOriginal	ExifIFD	undef: string
0x9000 0x9003 0x9004	LeafSubIFD ExifVersion DateTimeOriginal CreateDate	ExifIFD ExifIFD	undef: string string
0x9000 0x9003	LeafSubIFD ExifVersion DateTimeOriginal	ExifIFD	undef: string

	ExifTool 1	13.24	Tag Na	mes	•
0x9010	OffsetTime		ExifI	FD	string
0x9011	OffsetTimeOriginal		ExifI	FD	string
0x9012	OffsetTimeDigitized		ExifI	FD	string
0x9101	ComponentsConfigurat		ExifI		undef[4]!:
0x9102	CompressedBitsPerPi	xel	ExifI		rational64u!
0x9201	ShutterSpeedValue		ExifI		rational64s
0x9202	ApertureValue		ExifI ExifI		rational64u
0x9203 0x9204	BrightnessValue ExposureCompensation	n	Exifi		rational64s
0x9204	MaxApertureValue	LI	ExifI		rational64u
0x9206	SubjectDistance		ExifI		rational64u
0x9207	MeteringMode		ExifI	FD	int16u
0x9208	LightSource		ExifI	FD	int16u
0x9209	Flash		ExifI		int16u
0x920a	FocalLength		ExifI	FD	rational64u
0x920b	FlashEnergy		-		no
0x920c 0x920d	SpatialFrequencyResp Noise	ponse	_		no no
0x920d	FocalPlaneXResolution	on	_		no
0x920f	FocalPlaneYResolution		_		no
0x9210	FocalPlaneResolution	-	_		no
0x9211	ImageNumber		ExifI	FD	int32u
0x9212	SecurityClassificat	ion	ExifI		string
0x9213	ImageHistory		ExifI		string
0x9214	SubjectArea		ExifI	FD	int16u[n]
0x9215	ExposureIndex		-		no
0x9216	TIFF-EPStandardID		_		no
0x9217 0x923a	SensingMethod CIP3DataFile		_		no no
0x923b	CIP3Sheet		_		no
0x923c	CIP3Side		_		no
0x923f	StoNits		_		no
0x927c	MakerNoteApple		ExifI	FD	Apple
	MakerNoteNikon		ExifI		Nikon
	MakerNoteCanon		ExifI		Canon
	MakerNoteCasio		ExifI		Casio
	MakerNoteCasio2 MakerNoteDJIInfo		ExifI ExifI		Casio Type2 DJI Info
	MakerNoteDJI		ExifI		DJI
	MakerNoteFLIR		ExifI		FLIR
	MakerNoteFujiFilm		ExifI		FujiFilm
	MakerNoteGE		ExifI	FD	GE
	MakerNoteGE2		ExifI		FujiFilm
	MakerNoteHasselblad		ExifI		Unknown
	MakerNoteHP		ExifI		HP
	MakerNoteHP2 MakerNoteHP4		ExifI ExifI		HP Type2 HP Type4
	MakerNoteHP6		ExifI		HP Type6
	MakerNoteISL		ExifI		Unknown
	MakerNoteJVC		ExifI		JVC
	MakerNoteJVCText		ExifI	FD	JVC Text
	MakerNoteKodak1a		ExifI		Kodak
	MakerNoteKodak1b		ExifI		Kodak
	MakerNoteKodak2		ExifI		Kodak Type2
	MakerNoteKodak3 MakerNoteKodak4		ExifI ExifI		Kodak Type3 Kodak Type4
	MakerNoteKodak5		ExifI		Kodak Types
	MakerNoteKodak6a		ExifI		Kodak Type6
	MakerNoteKodak6b		ExifI		Kodak Type6
	MakerNoteKodak7		ExifI		Kodak Type7
	MakerNoteKodak8a		ExifI		Kodak Type8
	MakerNoteKodak8b		ExifI		Kodak Type8
	MakerNoteKodak8c		ExifI		Kodak Type8
	MakerNoteKodak9 MakerNoteKodak10		ExifI ExifI		Kodak Type9 Kodak Type10
	MakerNoteKodak10 MakerNoteKodak11		Exifi		Kodak Typell Kodak Typell
	MakerNoteKodak12		ExifI		Kodak Typell
	MakerNoteKodakUnknov	wn	ExifI		Kodak Unknown
	MakerNoteKyocera		ExifI	FD	Unknown
	MakerNoteMinolta		ExifI	FD	Minolta

	EXILIOOI 13.24	rag Names -	· <del>-</del>
	MakerNoteMinolta2	ExifIFD	Olympus
	MakerNoteMinolta3	ExifIFD	undef
	MakerNoteMotorola	ExifIFD	Motorola
	MakerNoteNikon2	ExifIFD	Nikon Type2
	MakerNoteNikon3	ExifIFD	Nikon
	MakerNoteNintendo	ExifIFD	Nintendo
	MakerNoteOlympus	ExifIFD	Olympus
	MakerNoteOlympus2	ExifIFD	Olympus
	MakerNoteOlympus3	ExifIFD	Olympus
	MakerNoteLeica	ExifIFD	Panasonic
	MakerNoteLeica2	ExifIFD	Panasonic Leica2
	MakerNoteLeica3	ExifIFD	Panasonic Leica3
	MakerNoteLeica4	ExifIFD	Panasonic Leica4
	MakerNoteLeica5	ExifIFD	Panasonic Leica5
	MakerNoteLeica6	ExifIFD	Panasonic Leica6
	MakerNoteLeica7	ExifIFD	Panasonic Leica6
	MakerNoteLeica8	ExifIFD	Panasonic Leica5
	MakerNoteLeica9	ExifIFD	Panasonic Leica9
	MakerNoteLeica10	ExifIFD	Panasonic
	MakerNotePanasonic	ExifIFD	Panasonic
	MakerNotePanasonic2	ExifIFD	Panasonic Type2
	MakerNotePanasonic3	ExifIFD	Panasonic
	MakerNotePentax	ExifIFD	Pentax
	MakerNotePentax2	ExifIFD	Pentax Type2
	MakerNotePentax3	ExifIFD	Casio Type2
	MakerNotePentax4	ExifIFD	Pentax Type4
	MakerNotePentax5	ExifIFD	Pentax
	MakerNotePentax6	ExifIFD	Pentax S1
	MakerNotePhaseOne	ExifIFD	PhaseOne
	MakerNoteReconyx	ExifIFD	Reconyx
	MakerNoteReconyx2	ExifIFD	Reconyx Type2
	<b>-</b>	ExifIFD	
	MakerNoteReconyx3		Reconyx Type3
	MakerNoteRicohPentax	ExifIFD	Pentax
	MakerNoteRicoh	ExifIFD	Ricoh
	MakerNoteRicoh2	ExifIFD	Ricoh Type2
	MakerNoteRicohText	ExifIFD	Ricoh Text
	MakerNoteSamsung1a	ExifIFD	undef
	MakerNoteSamsung1b	ExifIFD	Samsung
	MakerNoteSamsung2	ExifIFD	Samsung Type2
	MakerNoteSanyo	ExifIFD	Sanyo
	MakerNoteSanyoC4	ExifIFD	Sanyo
	MakerNoteSanyoPatch	ExifIFD	Sanyo
	MakerNoteSigma	ExifIFD	Sigma
	MakerNoteSony	ExifIFD	Sony
	MakerNoteSony2	ExifIFD	Olympus
	MakerNoteSony3	ExifIFD	Olympus
	MakerNoteSony4	ExifIFD	Sony PIC
	MakerNoteSony5	ExifIFD	Sony
	MakerNoteSonyEricsson	ExifIFD	Sony Ericsson
	MakerNoteSonySRF	ExifIFD	Sony SRF
	MakerNoteUnknownText	ExifIFD	undef
	MakerNoteUnknownBinary	ExifIFD	undef
	MakerNoteUnknown	ExifIFD	Unknown
0x9286	UserComment	ExifIFD	undef
0x9290	SubSecTime	ExifIFD	string
0x9291	SubSecTimeOriginal	ExifIFD	string
0x9291 0x9292	SubSecTimeOfigitized	ExifIFD	string
0x932f	MSDocumentText	EXILIED	no
0x9321 $0x9330$	MSPropertySetStorage		
		_	no
0x9331	MSDocumentTextPosition	_ _	no Photoghop DogumentData
0x935c	ImageSourceData	IFD0	Photoshop DocumentData
0x9400	AmbientTemperature	ExifIFD	rational64s
0x9401	Humidity	ExifIFD	rational64u
0x9402	Pressure	ExifIFD	rational64u
0x9403	WaterDepth	ExifIFD	rational64s
0x9404	Acceleration	ExifIFD	rational64u
0x9405	CameraElevationAngle	ExifIFD	rational64s
0x9999	XiaomiSettings	ExifIFD	JSON
0x9a00	XiaomiModel	ExifIFD	string!
0x9c9b	XPTitle	IFD0	int8u

0x9c9c	XPComment	IFD0	int8u
0x9c9d	XPAuthor	IFD0	int8u
0x9c9e	XPKeywords	IFD0	int8u
0x9c9f	XPSubject	IFD0	int8u
0xa000	FlashpixVersion	ExifIFD	undef:
0xa001	ColorSpace	ExifIFD	int16u:
0xa002	ExifImageWidth	ExifIFD	int16u:
0xa003	ExifImageHeight	ExifIFD	int16u:
0xa004	RelatedSoundFile	ExifIFD	string
		EXILIED	
0xa005	InteropOffset	_	EXIF
0xa010	SamsungRawPointersOffset	_	no
0xa011	SamsungRawPointersLength	-	no
0xa101	SamsungRawByteOrder	_	no
0xa102	SamsungRawUnknown?	_	no
0xa20b	FlashEnergy	ExifIFD	rational64u
0xa20c	SpatialFrequencyResponse	_	no
0xa20d	Noise	_	no
0xa20e	FocalPlaneXResolution	ExifIFD	rational64u
0xa20f	FocalPlaneYResolution	ExifIFD	rational64u
0xa210	FocalPlaneResolutionUnit	ExifIFD	int16u
0xa211	ImageNumber		no
0xa212	SecurityClassification	_	no
0xa213	ImageHistory	-	no
0xa214	SubjectLocation	ExifIFD	int16u[2]
0xa215	ExposureIndex	ExifIFD	rational64u
0xa216	TIFF-EPStandardID	_	no
0xa217	SensingMethod	ExifIFD	int16u
	_	ExifIFD	
0xa300	FileSource		undef
0xa301	SceneType	ExifIFD	undef
0xa302	CFAPattern	ExifIFD	undef
0xa401	CustomRendered	ExifIFD	int16u
0xa402	ExposureMode	ExifIFD	int16u
0xa403	WhiteBalance	ExifIFD	int16u
0xa404	DigitalZoomRatio	ExifIFD	rational64u
0xa405	FocalLengthIn35mmFormat	ExifIFD	int16u
0xa406	SceneCaptureType	ExifIFD	int16u
0xa407	GainControl	ExifIFD	int16u
0xa408	Contrast	ExifIFD	int16u
0xa409	Saturation	ExifIFD	int16u
		ExifIFD	int16u
0xa40a	Sharpness		
0xa40b	DeviceSettingDescription	_	no
0xa40c	SubjectDistanceRange	ExifIFD	int16u
0xa420	ImageUniqueID	ExifIFD	string
0xa430	OwnerName	ExifIFD	string
0xa431	SerialNumber	ExifIFD	string
			-
0xa432	LensInfo	ExifIFD	rational64u[4]
0xa433	LensMake	ExifIFD	string
0xa434	LensModel	ExifIFD	string
0xa435	LensSerialNumber	ExifIFD	string
0xa436	ImageTitle	ExifIFD	string
0xa437	Photographer	ExifIFD	string
			_
0xa438	ImageEditor	ExifIFD	string
0xa439	CameraFirmware	ExifIFD	string
0xa43a	RAWDevelopingSoftware	ExifIFD	string
0xa43b	ImageEditingSoftware	ExifIFD	string
0xa43c	MetadataEditingSoftware	ExifIFD	string
0xa460	CompositeImage	ExifIFD	int16u
	_		
0xa461	CompositeImageCount	ExifIFD	int16u[2]
0xa462	CompositeImageExposureTim	es ExifIFD	undef
0xa480	GDALMetadata	IFD0	string
0xa481	GDALNoData	IFD0	string
0xa500	Gamma	ExifIFD	rational64u
0xa500	ExpandSoftware		
	_	_	no
0xafc1	ExpandLens	_	no
0xafc2	ExpandFilm	_	no
0xafc3			no
	ExpandFilterLens	_	110
0xafc4	ExpandFilterLens ExpandScanner	-	no
	ExpandScanner	- -	no
0xafc5	ExpandScanner ExpandFlashLamp	- -	no no
0xafc5 0xb4c3	ExpandScanner ExpandFlashLamp HasselbladRawImage	- - -	no no no
0xafc5	ExpandScanner ExpandFlashLamp	- - - -	no no

0 1 00	m		
0xbc02	Transformation	_	no
0xbc03	Uncompressed	_	no
0xbc04	ImageType	_	no
0xbc80	ImageWidth	_	no
0xbc81	ImageHeight	-	no
0xbc82	WidthResolution	-	no
0xbc83	HeightResolution	-	no
0xbcc0	ImageOffset	_	no
0xbcc1	ImageByteCount	_	no
0xbcc2	AlphaOffset	_	no
0xbcc3	AlphaByteCount	_	no
0xbcc4	ImageDataDiscard	_	no
0xbcc5	AlphaDataDiscard	_	no
0xc427	OceScanjobDesc		
		_	no
0xc428	OceApplicationSelector	_	no
0xc429	OceIDNumber	_	no
0xc42a	OceImageLogic	_	no
0xc44f	Annotations	-	no
0xc4a5	PrintIM	IFD0	PrintIM
0xc519	HasselbladXML	-	PLIST
0xc51b	HasselbladExif	-	EXIF
0xc573	OriginalFileName	_	no
0xc580	USPT00riginalContentType	_	no
0xc5e0	CR2CFAPattern	_	no
0xc612	DNGVersion	IFD0	int8u[4]!
0xc613	DNGBackwardVersion	IFD0	int8u[4]!
0xc614	UniqueCameraModel	IFD0	string
0xc615	LocalizedCameraModel	IFD0	string
0xc616	CFAPlaneColor	SubIFD	no
			_
0xc617	CFALayout	SubIFD	no
0xc618	LinearizationTable	SubIFD	int16u[n]!
0xc619	BlackLevelRepeatDim	SubIFD	int16u[2]!
0xc61a	BlackLevel	SubIFD	rational64u[n]!
0xc61b	BlackLevelDeltaH	SubIFD	rational64s[n]!
0xc61c	BlackLevelDeltaV	SubIFD	rational64s[n]!
0xc61d	WhiteLevel	SubIFD	int32u[n]!
0xc61e	DefaultScale	SubIFD	rational64u[2]!
0xc61f	DefaultCropOrigin	SubIFD	int32u[2]!
0xc620	DefaultCropSize	SubIFD	int32u[2]!
0xc621	ColorMatrix1	IFD0	rational64s[n]!
0xc622	ColorMatrix2	IFD0	rational64s[n]!
0xc623	CameraCalibration1	IFD0	rational64s[n]!
0xc624	CameraCalibration2	IFD0	rational64s[n]!
0xc625	ReductionMatrix1	IFD0	rational64s[n]!
0xc626	ReductionMatrix2		rational64s[n]!
0xc620		IFD0	
	AnalogBalance	IFD0	rational64u[n]!
0xc628	AsShotNeutral	IFD0	rational64u[n]!
0xc629	AsShotWhiteXY	IFD0	rational64u[2]!
0xc62a	BaselineExposure	IFD0	rational64s!
0xc62b	BaselineNoise	IFD0	rational64u!
0xc62c	BaselineSharpness	IFD0	rational64u!
0xc62d	BayerGreenSplit	SubIFD	int32u!
0xc62e	LinearResponseLimit	IFD0	rational64u!
0xc62f	CameraSerialNumber	IFD0	string
0xc630	DNGLensInfo	IFD0	rational64u[4]
0xc631	ChromaBlurRadius	SubIFD	rational64u!
0xc632	AntiAliasStrength	SubIFD	rational64u!
0xc633	ShadowScale	IFD0	rational64u!
0xc634	SR2Private	IFD0	Sony SR2Private
0110001	DNGAdobeData	IFD0	DNG AdobeData
	MakerNotePentax	IFD0	Pentax
	MakerNotePentax5	IFD0	Pentax
	MakerNotePentaxs  MakerNoteRicohPentax	IFD0	
			Pentax
	MakerNoteDJIInfo	IFD0	DJI Info
0 625	DNGPrivateData	IFD0	int8u!
0xc635	MakerNoteSafety	IFD0	int16u
0xc640	RawImageSegmentation	-	no
0xc65a	CalibrationIlluminant1	IFD0	int16u!
0xc65b	CalibrationIlluminant2	IFD0	int16u!
0xc65c	BestQualityScale	SubIFD	rational64u!

0xc65d			
UNCUJU	RawDataUniqueID	IFD0	int8u[16]!
0xc660	AliasLayerMetadata	_	no
0xc68b	OriginalRawFileName	IFD0	string!
0xc68c	OriginalRawFileData	IFD0	DNG OriginalRaw
0xc68d	ActiveArea	SubIFD	int32u[4]!
0xc68e	MaskedAreas	SubIFD	int32u[4]:
0xc68f	AsShotICCProfile	IFD0	ICC_Profile
0xc690	AsShotPreProfileMatrix	IFD0	rational64s[n]!
0xc691	CurrentICCProfile	IFD0	ICC_Profile
0xc692	CurrentPreProfileMatrix	IFD0	rational64s[n]!
0xc6bf	ColorimetricReference	IFD0	int16u!
0xc6c5	SRawType	IFD0	no
0xc6d2	PanasonicTitle	IFD0	undef
0xc6d3	PanasonicTitle2	IFD0	undef
0xc6f3	CameraCalibrationSig	IFD0	string!
0xc6f4	ProfileCalibrationSig	IFD0	string!
0xc6f5	ProfileIFD	IFD0	EXIF
0xc6f6	AsShotProfileName	IFD0	string!
0xc6f7	NoiseReductionApplied	SubIFD	rational64u!
0xc6f8	ProfileName	IFD0	string!
0xc6f9	ProfileHueSatMapDims	IFD0	int32u[3]!
0xc6fa	ProfileHueSatMapData1	IFD0	float[n]!
0xc6fb	ProfileHueSatMapData2	IFD0	float[n]!
0xc6fc	ProfileToneCurve	IFD0	float[n]!
0xc6fd	ProfileEmbedPolicy	IFD0	int32u!
	-		
0xc6fe	ProfileCopyright	IFD0	string!
0xc714	ForwardMatrix1	IFD0	rational64s[n]!
0xc715	ForwardMatrix2	IFD0	rational64s[n]!
0xc716	PreviewApplicationName	IFD0	string!
0xc717	PreviewApplicationVersion	IFD0	string!
0xc718	PreviewSettingsName	IFD0	string!
0xc719	PreviewSettingsDigest	IFD0	int8u!
0xc71a	PreviewColorSpace	IFD0	int32u!
0xc71b	PreviewDateTime	IFD0	string!
0xc71c	RawImageDigest	IFD0	int8u[16]!
0xc71d	OriginalRawFileDigest	IFD0	int8u[16]!
0xc71e	SubTileBlockSize	_	no
0xc71f	RowInterleaveFactor	_	no
0xc725	ProfileLookTableDims	IFD0	int32u[3]!
0xc725	ProfileLookTableData		float[n]!
0.8.0 / 2.0		IFD0	
0740	O 1		
0xc740	OpcodeList1	SubIFD	undef~!
0xc741	OpcodeList2	SubIFD	undef~!
0xc741 0xc74e	OpcodeList2 OpcodeList3	SubIFD SubIFD	undef~! undef~!
0xc741 0xc74e 0xc761	OpcodeList2 OpcodeList3 NoiseProfile	SubIFD SubIFD SubIFD	<pre>undef~! undef~! double[n]!</pre>
0xc741 0xc74e 0xc761 0xc763	OpcodeList2 OpcodeList3	SubIFD SubIFD	<pre>undef~! undef~! double[n]! int8u[n]</pre>
0xc741 0xc74e 0xc761	OpcodeList2 OpcodeList3 NoiseProfile	SubIFD SubIFD SubIFD	<pre>undef~! undef~! double[n]!</pre>
0xc741 0xc74e 0xc761 0xc763	OpcodeList2 OpcodeList3 NoiseProfile TimeCodes	SubIFD SubIFD SubIFD IFD0	<pre>undef~! undef~! double[n]! int8u[n]</pre>
0xc741 0xc74e 0xc761 0xc763 0xc764	OpcodeList2 OpcodeList3 NoiseProfile TimeCodes FrameRate	SubIFD SubIFD SubIFD IFD0 IFD0	<pre>undef~! undef~! double[n]! int8u[n] rational64s</pre>
0xc741 0xc74e 0xc761 0xc763 0xc764 0xc772	OpcodeList2 OpcodeList3 NoiseProfile TimeCodes FrameRate TStop ReelName	SubIFD SubIFD SubIFD IFD0 IFD0 IFD0	<pre>undef~! undef~! double[n]! int8u[n] rational64s rational64u[n] string</pre>
0xc741 0xc74e 0xc761 0xc763 0xc764 0xc772 0xc789 0xc791	OpcodeList2 OpcodeList3 NoiseProfile TimeCodes FrameRate TStop ReelName OriginalDefaultFinalSize	SubIFD SubIFD SubIFD IFD0 IFD0 IFD0 IFD0	<pre>undef~! undef~! double[n]! int8u[n] rational64s rational64u[n] string int32u[2]!</pre>
0xc741 0xc74e 0xc761 0xc763 0xc764 0xc772 0xc789 0xc791	OpcodeList2 OpcodeList3 NoiseProfile TimeCodes FrameRate TStop ReelName OriginalDefaultFinalSize OriginalBestQualitySize	SubIFD SubIFD SubIFD IFD0 IFD0 IFD0 IFD0 IFD0 IFD0	<pre>undef~! undef~! double[n]! int8u[n] rational64s rational64u[n] string int32u[2]! int32u[2]!</pre>
0xc741 0xc74e 0xc761 0xc763 0xc764 0xc772 0xc789 0xc791 0xc792 0xc793	OpcodeList2 OpcodeList3 NoiseProfile TimeCodes FrameRate TStop ReelName OriginalDefaultFinalSize OriginalBestQualitySize OriginalDefaultCropSize	SubIFD SubIFD SubIFD IFD0 IFD0 IFD0 IFD0 IFD0 IFD0 IFD0	<pre>undef~! undef~! double[n]! int8u[n] rational64s rational64u[n] string int32u[2]! int32u[2]! rational64u[2]!</pre>
0xc741 0xc74e 0xc761 0xc763 0xc764 0xc772 0xc789 0xc791 0xc792 0xc793	OpcodeList2 OpcodeList3 NoiseProfile TimeCodes FrameRate TStop ReelName OriginalDefaultFinalSize OriginalBestQualitySize OriginalDefaultCropSize CameraLabel	SubIFD SubIFD SubIFD IFD0 IFD0 IFD0 IFD0 IFD0 IFD0 IFD0 I	<pre>undef~! undef~! double[n]! int8u[n] rational64s rational64u[n] string int32u[2]! int32u[2]! rational64u[2]! string</pre>
0xc741 0xc74e 0xc761 0xc763 0xc764 0xc772 0xc789 0xc791 0xc792 0xc793 0xc7a1	OpcodeList2 OpcodeList3 NoiseProfile TimeCodes FrameRate TStop ReelName OriginalDefaultFinalSize OriginalBestQualitySize OriginalDefaultCropSize CameraLabel ProfileHueSatMapEncoding	SubIFD SubIFD SubIFD IFD0 IFD0 IFD0 IFD0 IFD0 IFD0 IFD0 I	<pre>undef~! undef~! double[n]! int8u[n] rational64s rational64u[n] string int32u[2]! int32u[2]! rational64u[2]! string int32u!</pre>
0xc741 0xc74e 0xc761 0xc763 0xc764 0xc772 0xc789 0xc791 0xc792 0xc793 0xc7a1 0xc7a3	OpcodeList2 OpcodeList3 NoiseProfile TimeCodes FrameRate TStop ReelName OriginalDefaultFinalSize OriginalBestQualitySize OriginalDefaultCropSize CameraLabel ProfileHueSatMapEncoding ProfileLookTableEncoding	SubIFD SubIFD SubIFD IFD0 IFD0 IFD0 IFD0 IFD0 IFD0 IFD0 I	<pre>undef~! undef~! double[n]! int8u[n] rational64s rational64u[n] string int32u[2]! int32u[2]! rational64u[2]! string int32u! int32u!</pre>
0xc741 0xc74e 0xc761 0xc763 0xc764 0xc772 0xc789 0xc791 0xc792 0xc793 0xc7a1 0xc7a3 0xc7a4	OpcodeList2 OpcodeList3 NoiseProfile TimeCodes FrameRate TStop ReelName OriginalDefaultFinalSize OriginalBestQualitySize OriginalDefaultCropSize CameraLabel ProfileHueSatMapEncoding ProfileLookTableEncoding BaselineExposureOffset	SubIFD SubIFD SubIFD IFD0 IFD0 IFD0 IFD0 IFD0 IFD0 IFD0 I	<pre>undef~! undef~! double[n]! int8u[n] rational64s rational64u[n] string int32u[2]! int32u[2]! rational64u[2]! string int32u! int32u! rational64s!</pre>
0xc741 0xc74e 0xc761 0xc763 0xc764 0xc772 0xc789 0xc791 0xc792 0xc793 0xc7a1 0xc7a3 0xc7a4 0xc7a5	OpcodeList2 OpcodeList3 NoiseProfile TimeCodes FrameRate TStop ReelName OriginalDefaultFinalSize OriginalBestQualitySize OriginalDefaultCropSize CameraLabel ProfileHueSatMapEncoding ProfileLookTableEncoding BaselineExposureOffset DefaultBlackRender	SubIFD SubIFD SubIFD IFD0 IFD0 IFD0 IFD0 IFD0 IFD0 IFD0 I	<pre>undef~! undef~! double[n]! int8u[n] rational64s rational64u[n] string int32u[2]! int32u[2]! rational64u[2]! string int32u! int32u! int32u! rational64s! int32u!</pre>
0xc741 0xc74e 0xc761 0xc763 0xc764 0xc772 0xc789 0xc791 0xc792 0xc793 0xc7a1 0xc7a3 0xc7a4 0xc7a5 0xc7a6	OpcodeList2 OpcodeList3 NoiseProfile TimeCodes FrameRate TStop ReelName OriginalDefaultFinalSize OriginalBestQualitySize OriginalDefaultCropSize CameraLabel ProfileHueSatMapEncoding ProfileLookTableEncoding BaselineExposureOffset DefaultBlackRender NewRawImageDigest	SubIFD SubIFD SubIFD IFD0 IFD0 IFD0 IFD0 IFD0 IFD0 IFD0 I	<pre>undef~! undef~! double[n]! int8u[n] rational64s rational64u[n] string int32u[2]! int32u[2]! rational64u[2]! string int32u! int32u! int32u! rational64s! int32u! int32u! int32u! int32u!</pre>
0xc741 0xc74e 0xc761 0xc763 0xc764 0xc772 0xc789 0xc791 0xc792 0xc793 0xc7a1 0xc7a3 0xc7a4 0xc7a5 0xc7a6 0xc7a6	OpcodeList2 OpcodeList3 NoiseProfile TimeCodes FrameRate TStop ReelName OriginalDefaultFinalSize OriginalBestQualitySize OriginalDefaultCropSize CameraLabel ProfileHueSatMapEncoding ProfileLookTableEncoding BaselineExposureOffset DefaultBlackRender NewRawImageDigest RawToPreviewGain	SubIFD SubIFD SubIFD SubIFD IFD0 IFD0 IFD0 IFD0 IFD0 IFD0 IFD0 I	<pre>undef~! undef~! double[n]! int8u[n] rational64s rational64u[n] string int32u[2]! int32u[2]! rational64u[2]! string int32u! int32u! int32u! int32u! int32u! int32u! int32u! int32u! int8u[16]! double!</pre>
0xc741 0xc74e 0xc761 0xc763 0xc764 0xc772 0xc789 0xc791 0xc792 0xc793 0xc7a1 0xc7a3 0xc7a4 0xc7a5 0xc7a6 0xc7a6 0xc7a7	OpcodeList2 OpcodeList3 NoiseProfile TimeCodes FrameRate TStop ReelName OriginalDefaultFinalSize OriginalBestQualitySize OriginalDefaultCropSize CameraLabel ProfileHueSatMapEncoding ProfileLookTableEncoding BaselineExposureOffset DefaultBlackRender NewRawImageDigest RawToPreviewGain CacheVersion	Subifd Subifd Subifd IFD0 IFD0 IFD0 IFD0 IFD0 IFD0 IFD0 IFD0	<pre>undef~! undef~! double[n]! int8u[n] rational64s rational64u[n] string int32u[2]! int32u[2]! rational64u[2]! string int32u! int32u!</pre>
0xc741 0xc74e 0xc761 0xc763 0xc764 0xc772 0xc789 0xc791 0xc792 0xc793 0xc7a1 0xc7a3 0xc7a4 0xc7a5 0xc7a6 0xc7a7 0xc7a8 0xc7a8	OpcodeList2 OpcodeList3 NoiseProfile TimeCodes FrameRate TStop ReelName OriginalDefaultFinalSize OriginalBestQualitySize OriginalDefaultCropSize CameraLabel ProfileHueSatMapEncoding ProfileLookTableEncoding BaselineExposureOffset DefaultBlackRender NewRawImageDigest RawToPreviewGain CacheVersion DefaultUserCrop	SubIFD SubIFD SubIFD SubIFD IFD0 IFD0 IFD0 IFD0 IFD0 IFD0 IFD0 I	<pre>undef~! undef~! double[n]! int8u[n] rational64s rational64u[n] string int32u[2]! int32u[2]! rational64u[2]! string int32u! int32u! int32u! rational64s! int32u! int8u[16]! double! int32u! rational64u[4]!</pre>
0xc741 0xc74e 0xc761 0xc763 0xc764 0xc772 0xc789 0xc791 0xc792 0xc793 0xc7a1 0xc7a3 0xc7a4 0xc7a5 0xc7a6 0xc7a6 0xc7a7 0xc7a8 0xc7a8	OpcodeList2 OpcodeList3 NoiseProfile TimeCodes FrameRate TStop ReelName OriginalDefaultFinalSize OriginalBestQualitySize OriginalDefaultCropSize CameraLabel ProfileHueSatMapEncoding ProfileLookTableEncoding ProfileLookTableEncoding BaselineExposureOffset DefaultBlackRender NewRawImageDigest RawToPreviewGain CacheVersion DefaultUserCrop NikonNEFInfo	Subifd Subifd Subifd IFD0 IFD0 IFD0 IFD0 IFD0 IFD0 IFD0 IFD0	undef~! undef~! double[n]! int8u[n] rational64s rational64u[n] string int32u[2]! int32u[2]! rational64u[2]! string int32u! int32u! int32u! rational64s! int32u! rational64s! int32u! int8u[16]! double! int32u! rational64u[4]! Nikon NEFInfo
0xc741 0xc74e 0xc761 0xc763 0xc764 0xc772 0xc789 0xc791 0xc792 0xc793 0xc7a1 0xc7a3 0xc7a4 0xc7a5 0xc7a6 0xc7a7 0xc7a8 0xc7a8	OpcodeList2 OpcodeList3 NoiseProfile TimeCodes FrameRate TStop ReelName OriginalDefaultFinalSize OriginalBestQualitySize OriginalDefaultCropSize CameraLabel ProfileHueSatMapEncoding ProfileLookTableEncoding BaselineExposureOffset DefaultBlackRender NewRawImageDigest RawToPreviewGain CacheVersion DefaultUserCrop	Subifd Subifd Subifd IFD0 IFD0 IFD0 IFD0 IFD0 IFD0 IFD0 IFD0	<pre>undef~! undef~! double[n]! int8u[n] rational64s rational64u[n] string int32u[2]! int32u[2]! rational64u[2]! string int32u! int32u! int32u! rational64s! int32u! int8u[16]! double! int32u! rational64u[4]!</pre>
0xc741 0xc74e 0xc761 0xc763 0xc764 0xc772 0xc789 0xc791 0xc792 0xc793 0xc7a1 0xc7a3 0xc7a4 0xc7a5 0xc7a6 0xc7a6 0xc7a7 0xc7a8 0xc7a8	OpcodeList2 OpcodeList3 NoiseProfile TimeCodes FrameRate TStop ReelName OriginalDefaultFinalSize OriginalBestQualitySize OriginalDefaultCropSize CameraLabel ProfileHueSatMapEncoding ProfileLookTableEncoding ProfileLookTableEncoding BaselineExposureOffset DefaultBlackRender NewRawImageDigest RawToPreviewGain CacheVersion DefaultUserCrop NikonNEFInfo	Subifd Subifd Subifd IFD0 IFD0 IFD0 IFD0 IFD0 IFD0 IFD0 IFD0	undef~! undef~! double[n]! int8u[n] rational64s rational64u[n] string int32u[2]! int32u[2]! rational64u[2]! string int32u! int32u! int32u! rational64s! int32u! rational64s! int32u! int8u[16]! double! int32u! rational64u[4]! Nikon NEFInfo
0xc741 0xc74e 0xc761 0xc763 0xc764 0xc772 0xc789 0xc791 0xc792 0xc793 0xc7a1 0xc7a3 0xc7a4 0xc7a5 0xc7a6 0xc7a6 0xc7a7 0xc7a8 0xc7aa 0xc7aa 0xc7aa 0xc7ab	OpcodeList2 OpcodeList3 NoiseProfile TimeCodes FrameRate TStop ReelName OriginalDefaultFinalSize OriginalBestQualitySize OriginalDefaultCropSize CameraLabel ProfileHueSatMapEncoding ProfileLookTableEncoding BaselineExposureOffset DefaultBlackRender NewRawImageDigest RawToPreviewGain CacheVersion DefaultUserCrop NikonNEFInfo DepthFormat	SubIFD SubIFD SubIFD SubIFD IFD0 IFD0 IFD0 IFD0 IFD0 IFD0 IFD0 I	undef~! undef~! double[n]! int8u[n] rational64s rational64u[n] string int32u[2]! int32u[2]! rational64u[2]! string int32u! int32u! int32u! rational64s! int32u! rational64s! int32u! rational64u[4]! Nikon NEFInfo int16u!
0xc741 0xc74e 0xc761 0xc763 0xc764 0xc772 0xc789 0xc791 0xc792 0xc793 0xc7a1 0xc7a3 0xc7a4 0xc7a5 0xc7a6 0xc7a6 0xc7a6 0xc7a6 0xc7a6 0xc7a7 0xc7a8 0xc7a8 0xc7a8 0xc7a8	OpcodeList2 OpcodeList3 NoiseProfile TimeCodes FrameRate TStop ReelName OriginalDefaultFinalSize OriginalBestQualitySize OriginalDefaultCropSize CameraLabel ProfileHueSatMapEncoding ProfileLookTableEncoding BaselineExposureOffset DefaultBlackRender NewRawImageDigest RawToPreviewGain CacheVersion DefaultUserCrop NikonNEFInfo DepthFormat DepthNear DepthFar	SubIFD SubIFD SubIFD SubIFD IFD0 IFD0 IFD0 IFD0 IFD0 IFD0 IFD0 I	undef~! undef~! double[n]! int8u[n] rational64s rational64u[n] string int32u[2]! int32u[2]! rational64u[2]! string int32u! int32u! int32u! rational64s! int32u! rational64s! int32u! rational64u[4]! Nikon NEFInfo int16u! rational64u!
0xc741 0xc74e 0xc761 0xc763 0xc764 0xc772 0xc789 0xc791 0xc792 0xc793 0xc7a1 0xc7a3 0xc7a4 0xc7a5 0xc7a6 0xc7a6 0xc7a7 0xc7a8 0xc7a6 0xc7a7 0xc7a8 0xc7a8 0xc7a6 0xc7a7	OpcodeList2 OpcodeList3 NoiseProfile TimeCodes FrameRate TStop ReelName OriginalDefaultFinalSize OriginalBestQualitySize OriginalDefaultCropSize CameraLabel ProfileHueSatMapEncoding ProfileLookTableEncoding BaselineExposureOffset DefaultBlackRender NewRawImageDigest RawToPreviewGain CacheVersion DefaultUserCrop NikonNEFInfo DepthFormat DepthNear DepthFar DepthUnits	SubIFD SubIFD SubIFD SubIFD IFD0 IFD0 IFD0 IFD0 IFD0 IFD0 IFD0 I	undef~! undef~! double[n]! int8u[n] rational64s rational64u[n] string int32u[2]! int32u[2]! rational64u[2]! string int32u! int32u! rational64s! int32u! rational64s! int32u! rational64u[4]! Nikon NEFInfo int16u! rational64u!
0xc741 0xc74e 0xc761 0xc763 0xc764 0xc772 0xc789 0xc791 0xc792 0xc793 0xc7a1 0xc7a3 0xc7a4 0xc7a5 0xc7a6 0xc7a6 0xc7a7 0xc7a8 0xc7a6 0xc7a6 0xc7a6 0xc7a6 0xc7a6 0xc7a7	OpcodeList2 OpcodeList3 NoiseProfile TimeCodes FrameRate TStop ReelName OriginalDefaultFinalSize OriginalBestQualitySize OriginalDefaultCropSize CameraLabel ProfileHueSatMapEncoding ProfileLookTableEncoding BaselineExposureOffset DefaultBlackRender NewRawImageDigest RawToPreviewGain CacheVersion DefaultUserCrop NikonNEFInfo DepthFormat DepthNear DepthFar	Subifd Subifd Subifd IFD0 IFD0 IFD0 IFD0 IFD0 IFD0 IFD0 IFD0	undef~! undef~! double[n]! int8u[n] rational64s rational64u[n] string int32u[2]! int32u[2]! rational64u[2]! string int32u! int32u! rational64s! int32u! rational64s! int32u! rational64u[4]! Nikon NEFInfo int16u! rational64u! int16u! int16u!
0xc741 0xc74e 0xc761 0xc763 0xc764 0xc772 0xc789 0xc791 0xc792 0xc793 0xc7a1 0xc7a3 0xc7a4 0xc7a5 0xc7a6	OpcodeList2 OpcodeList3 NoiseProfile TimeCodes FrameRate TStop ReelName OriginalDefaultFinalSize OriginalBestQualitySize OriginalDefaultCropSize CameraLabel ProfileHueSatMapEncoding ProfileLookTableEncoding BaselineExposureOffset DefaultBlackRender NewRawImageDigest RawToPreviewGain CacheVersion DefaultUserCrop NikonNEFInfo DepthFormat DepthNear DepthMear DepthMeasureType EnhanceParams	Subifd Subifd Subifd IFD0 IFD0 IFD0 IFD0 IFD0 IFD0 IFD0 IFD0	undef~! undef~! double[n]! int8u[n] rational64s rational64u[n] string int32u[2]! int32u[2]! rational64u[2]! string int32u! int32u! rational64s! int32u! rational64s! int32u! rational64u[4]! Nikon NEFInfo int16u! rational64u! int16u!
0xc741 0xc74e 0xc761 0xc763 0xc764 0xc772 0xc789 0xc791 0xc792 0xc793 0xc7a1 0xc7a3 0xc7a4 0xc7a5 0xc7a6 0xc7e9 0xc7ee 0xc7ee 0xc7ee 0xc7ee 0xc7ee 0xc7ee	OpcodeList2 OpcodeList3 NoiseProfile TimeCodes FrameRate TStop ReelName OriginalDefaultFinalSize OriginalBestQualitySize OriginalDefaultCropSize CameraLabel ProfileHueSatMapEncoding ProfileLookTableEncoding BaselineExposureOffset DefaultBlackRender NewRawImageDigest RawToPreviewGain CacheVersion DefaultUserCrop NikonNEFInfo DepthFormat DepthFormat DepthMear DepthMeasureType EnhanceParams ProfileGainTableMap	Subifd Subifd Subifd IFD0 IFD0 IFD0 IFD0 IFD0 IFD0 IFD0 IFD0	undef~! undef~! double[n]! int8u[n] rational64s rational64u[n] string int32u[2]! int32u[2]! rational64u[2]! string int32u! int32u! rational64s! int32u! rational64s! int32u! rational64u[4]! Nikon NEFInfo int16u! rational64u! rational64u! int16u! string! undef!
0xc741 0xc74e 0xc761 0xc763 0xc764 0xc772 0xc789 0xc791 0xc792 0xc793 0xc7a1 0xc7a3 0xc7a4 0xc7a5 0xc7a6	OpcodeList2 OpcodeList3 NoiseProfile TimeCodes FrameRate TStop ReelName OriginalDefaultFinalSize OriginalBestQualitySize OriginalDefaultCropSize CameraLabel ProfileHueSatMapEncoding ProfileLookTableEncoding BaselineExposureOffset DefaultBlackRender NewRawImageDigest RawToPreviewGain CacheVersion DefaultUserCrop NikonNEFInfo DepthFormat DepthNear DepthMear DepthMeasureType EnhanceParams	Subifd Subifd Subifd IFD0 IFD0 IFD0 IFD0 IFD0 IFD0 IFD0 IFD0	undef~! undef~! double[n]! int8u[n] rational64s rational64u[n] string int32u[2]! rational64u[2]! string int32u! int32u! rational64s! int32u! rational64s! int32u! rational64u[4]! Nikon NEFInfo int16u! rational64u! int16u! int16u! string!

0xcd31	CalibrationIlluminant3	IFD0	int16u!
0xcd32	CameraCalibration3	IFD0	rational64s[n]!
0xcd33	ColorMatrix3	IFD0	rational64s[n]!
0xcd34	ForwardMatrix3	IFD0	rational64s[n]!
0xcd35	IlluminantDatal	IFD0	undef!
0xcd36	IlluminantData2	IFD0	undef!
0xcd37	IlluminantData3	IFD0	undef!
0xcd38	MaskSubArea	SubIFD	no
0xcd39	ProfileHueSatMapData3	IFD0	float[n]!
0xcd3a	ReductionMatrix3	IFD0	rational64s[n]!
0xcd3f	RGBTables	IFD0	undef!
0xcd40	ProfileGainTableMap2	IFD0	undef!
0xcd41	JUMBF	_	Jpeg2000
0xcd43	ColumnInterleaveFactor	SubIFD	int32u!
0xcd44	ImageSequenceInfo	IFD0	DNG ImageSeq
0xcd46	ImageStats	IFD0	undef!
0xcd47	ProfileDynamicRange	IFD0	DNG ProfileDynamicRange
0xcd48	ProfileGroupName	IFD0	string!
0xcd49	JXLDistance	IFD0	float
0xcd4a	JXLEffort	IFD0	int32u
0xcd4b	JXLDecodeSpeed	IFD0	int32u
0xcea1	SEAL	IFD0	XMP SEAL
0xea1c	Padding	ExifIFD	undef!
0xea1d	OffsetSchema	ExifIFD	int32s!
0xfde8	OwnerName	ExifIFD	string/
0xfde9	SerialNumber	ExifIFD	string/
0xfdea	Lens	ExifIFD	string/
0xfe00	KDC_IFD	_	Kodak KDC_IFD
0xfe4c	RawFile	ExifIFD	string/
0xfe4d	Converter	ExifIFD	string/
0xfe4e	WhiteBalance	ExifIFD	string/
0xfe51	Exposure	ExifIFD	string/
0xfe52	Shadows	ExifIFD	string/
0xfe53	Brightness	ExifIFD	string/
0xfe54	Contrast	ExifIFD	string/
0xfe55	Saturation	ExifIFD	string/
0xfe56	Sharpness	ExifIFD	string/
0xfe57	Smoothness	ExifIFD	string/
0xfe58	MoireFilter	ExifIFD	string/

# IPTC Tags

The tags listed below are part of the International Press Telecommunications Council (IPTC) and the Newspaper Association of America (NAA) Information Interchange Model (IIM). This is an older meta information format, slowly being phased out in favor of XMP -- the newer IPTCCore specification uses XMP format. IPTC information may be found in JPG, TIFF, PNG, MIFF, PS, PDF, PSD, XCF and DNG images.

IPTC information is separated into different records, each of which has its own set of tags. See <a href="http://www.iptc.org/std/IIM/4.1/specification/IIMV4.1.pdf">http://www.iptc.org/std/IIM/4.1/specification/IIMV4.1.pdf</a> for the official IPTC IIM specification.

This specification dictates a length for ASCII ("string" or "digits") and binary ("undef") values. These lengths are given in square brackets after the Writable format name. For tags where a range of lengths is allowed, the minimum and maximum lengths are separated by a comma within the brackets. When writing, ExifTool issues a minor warning and truncates the value if it is longer than allowed by the IPTC specification. Minor errors may be ignored with the IgnoreMinorErrors (-m) option, allowing longer values to be written, but beware that values like this may cause problems for some other IPTC readers. ExifTool will happily read IPTC values of any length.

Separate IPTC date and time tags may be written with a combined date/time value and ExifTool automagically takes the appropriate part of the date/time string depending on whether a date or time tag is being written. This is very useful when copying date/time values to IPTC from other metadata formats.

IPTC time values include a timezone offset. If written with a value which doesn't include a timezone then the current local timezone offset is used (unless written with a combined date/time, in which case the local timezone offset at the specified date/time is used, which may be different due to changes in daylight savings time).

Note that it is not uncommon for IPTC to be found in non-standard locations in JPEG and TIFF-based images. When reading, the family 1 group name has a number added for non-standard IPTC ("IPTC2", "IPTC3", etc), but when writing only "IPTC" may be specified as the group. To keep the IPTC consistent, ExifTool updates tags in all existing IPTC locations, but will create a new IPTC group only in the standard location.

Record	Tag Name	Writable
1	IPTCEnvelope	IPTC EnvelopeRecord
2	IPTCApplication	IPTC ApplicationRecord
3	IPTCNewsPhoto	IPTC NewsPhoto
7	IPTCPreObjectData	IPTC PreObjectData
8	IPTCObjectData	IPTC ObjectData
9	IPTCPostObjectData	IPTC PostObjectData
240	IPTCFotoStation	IPTC FotoStation

# IPTC EnvelopeRecord Tags

Tag ID	Tag Name	Writable
0	EnvelopeRecordVersion	int16u:
5	Destination	string[0,1024]+
20	FileFormat	int16u
22	FileVersion	int16u
30	ServiceIdentifier	string[0,10]
40	EnvelopeNumber	digits[8]
50	ProductID	string[0,32]+
60	EnvelopePriority	digits[1]
70	DateSent	digits[8]
80	TimeSent	string[11]
90	CodedCharacterSet	string[0,32]!
100	UniqueObjectName	string[14,80]
120	ARMIdentifier	int16u
122	ARMVersion	int16u

# IPTC ApplicationRecord Tags

Tag ID	Tag Name	Writable
0	ApplicationRecordVersion	int16u:
3	ObjectTypeReference	string[3,67]
4	ObjectAttributeReference	string[4,68]+
5	ObjectName	string[0,64]
7	EditStatus	string[0,64]
8	EditorialUpdate	digits[2]
10	Urgency	digits[1]
12	SubjectReference	string[13,236]+
15	Category	string[0,3]
20	SupplementalCategories	string[0,32]+
22	FixtureIdentifier	string[0,32]
25	Keywords	string[0,64]+
26	ContentLocationCode	string[3]+
27	ContentLocationName	string[0,64]+
30	ReleaseDate	digits[8]
35	ReleaseTime	string[11]
37	ExpirationDate	digits[8]
38	ExpirationTime	string[11]
40	SpecialInstructions	string[0,256]
42	ActionAdvised	digits[2]
45	ReferenceService	string[0,10]+
47		digits[8]+
50	ReferenceNumber	digits[8]+

55 60 62	DateCreated TimeCreated DigitalCreationDate	digits[8] string[11] digits[8]
63	DigitalCreationTime	string[11]
65	OriginatingProgram	string[0,32]
70	ProgramVersion	string[0,10]
75	ObjectCycle	string[1]
80	By-line	string[0,32]+
85	By-lineTitle	string[0,32]+
90	City	string[0,32]
92	Sub-location	string[0,32]
95 100	Province-State	string[0,32]
100	Country-PrimaryLocationCode Country-PrimaryLocationName	string[3] string[0,64]
103	OriginalTransmissionReference	string[0,32]
105	Headline	string[0,256]
110	Credit	string[0,32]
115	Source	string[0,32]
116	CopyrightNotice	string[0,128]
118	Contact	string[0,128]+
120	Caption-Abstract	string[0,2000]
121	LocalCaption	string[0,256]
122	Writer-Editor	string[0,32]+
125	RasterizedCaption	undef[7360]
130 131	<pre>ImageType ImageOrientation</pre>	string[2] string[1]
135	LanguageIdentifier	string[2,3]
150	AudioType	string[2]
151	AudioSamplingRate	digits[6]
152	AudioSamplingResolution	digits[2]
153	AudioDuration	digits[6]
154	AudioOutcue	string[0,64]
184	JobID	string[0,64]
185	MasterDocumentID	string[0,256]
186	ShortDocumentID	string[0,64]
187	UniqueDocumentID	string[0,128]
188 200	OwnerID ObjectPreviewFileFormat	string[0,128] int16u
200	ObjectPreviewFileVersion	int16u
201	ObjectPreviewData	undef[0,256000]
221	Prefs	string[0,64]
225	ClassifyState	string[0,64]
228	SimilarityIndex	string[0,32]
230	DocumentNotes	string[0,1024]
231	DocumentHistory	string[0,256]
232	ExifCameraInfo	string[0,4096]
255	CatalogSets	string[0,256]+

# IPTC NewsPhoto Tags

Tag ID	Tag Name	Writable
0	NewsPhotoVersion	int16u:
10	IPTCPictureNumber	string[16]
20	IPTCImageWidth	int16u
30	IPTCImageHeight	int16u
40	IPTCPixelWidth	int16u
50	IPTCPixelHeight	int16u
55	SupplementalType	int8u
60	ColorRepresentation	int16u
64	InterchangeColorSpace	int8u
65	ColorSequence	int8u
66	ICC_Profile	no
70	ColorCalibrationMatrix	no
80	LookupTable	no
84	NumIndexEntries	int16u
85	ColorPalette	no
86	IPTCBitsPerSample	int8u
90	SampleStructure	int8u
100	ScanningDirection	int8u

102	IPTCImageRotation	int8u
110	DataCompressionMethod	int32u
120	QuantizationMethod	int8u
125	EndPoints	no
130	ExcursionTolerance	int8u
135	BitsPerComponent	int8u
140	MaximumDensityRange	int16u
145	GammaCompensatedValue	int16u

### IPTC PreObjectData Tags

Tag ID	Tag Name	Writable
10	SizeMode	no
20	MaxSubfileSize	no
90	ObjectSizeAnnounced	no
95	MaximumObjectSize	no

## IPTC ObjectData Tags

Tag ID	Tag Name	Writable
10	SubFile	no+

#### IPTC PostObjectData Tags

Tag ID	Tag Name	Writable
10	ConfirmedObjectSize	no

#### IPTC FotoStation Tags

Tag ID	Tag Name	Writable
[no tags	known]	

#### XMP Tags

XMP stands for "Extensible Metadata Platform", an XML/RDF-based metadata format which is being pushed by Adobe. Information in this format can be embedded in many different image file types including JPG, JP2, TIFF, GIF, EPS, PDF, PSD, IND, INX, PNG, DJVU, SVG, PGF, MIFF, XCF, CRW, DNG and a variety of proprietary TIFF-based RAW images, as well as MOV, AVI, ASF, WMV, FLV, SWF and MP4 videos, and WMA and audio formats supporting ID3v2 information.

The XMP Tag ID's aren't listed because in most cases they are identical to the Tag Name (aside from differences in case). Tags with different ID's are mentioned in the Notes column of the HTML version of this document.

All XMP information is stored as character strings. The Writable column specifies the information format: "string" is an unformatted string, "integer" is a string of digits (possibly beginning with a '+' or '-'), "real" is a floating point number, "rational" is entered as a floating point number but stored as two "integer" strings separated by a '/' character, "date" is a date/time string entered in the format "YYYY:mm:dd HH:MM:SS[.ss][+/-HH:MM]" but some partial date/time formats are also accepted (see <https://exiftool.org/faq.html#Q5>), "boolean" is either "True" or "False" (but "true" and "false" may be written as a ValueConv value for compatibility with non-conforming applications), "struct" indicates a structured tag, and "lang-alt" is a tag that supports alternate languages.

When reading, "struct" tags are extracted only if the Struct (-struct) option is used. Otherwise the corresponding <u>Flattened</u> tags, indicated by an underline ("\_") after the <u>Writable</u> type, are extracted. When copying, by default both structured and flattened tags are available, but the flattened tags are considered "unsafe" so they aren't copied unless specified explicitly. The Struct option may be disabled by setting Struct to 0 via the API or with --struct on the command line to

copy only flattened tags, or enabled by setting Struct to 1 via the API or with -struct on the command line to copy only as structures. When writing, the Struct option has no effect, and both structured and flattened tags may be written. See <a href="https://exiftool.org/struct.html">https://exiftool.org/struct.html</a> for more details.

Individual languages for "lang-alt" tags are accessed by suffixing the tag name with a '-', followed by an RFC 3066 language code (eg. "XMP:Title-fr", or "Rights-en-US"). (See <a href="http://www.ietf.org/rfc/rfc3066.txt">http://www.ietf.org/rfc/rfc3066.txt</a> for the RFC 3066 specification.) A "lang-alt" tag with no language code accesses the "x-default" language, but causes other languages for this tag to be deleted when writing. The "x-default" language code may be specified when writing to preserve other existing languages (eg. "XMP-dc:Description-x-default"). When reading, "x-default" is not specified.

The XMP tags are organized according to schema Namespace in the following tables. The ExifTool family 1 group names are derived from the namespace prefixes by adding a leading "XMP-" (eg. "XMP-dc"). A few of the longer prefixes have been shortened (as mentioned in the documentation below) to avoid excessively long ExifTool group names. The tags of any namespace may be deleted as a group by specifying the family 1 group name (eg. "-XMP-dc:all=" on the command line). This includes namespaces which are not pre-defined by ExifTool.

In cases where a tag name exists in more than one namespace, less common namespaces are avoided when writing. However, a specific namespace may be written by providing a family 1 group name for the tag (eg. XMP-crs:Contrast or XMP-exif:Contrast). When deciding on which tags to add to an image, using standard schemas such as dc, xmp, iptcCore and iptcExt is recommended if possible.

For structures, the heading of the first column is Field Name. Field names are very similar to tag names, except they are used to identify fields inside structures instead of stand-alone tags. See <a href="https://exiftool.org/struct.html#Fields">https://exiftool.org/struct.html#Fields</a>> for more details.

ExifTool will extract XMP information even if it is not listed in these tables, but other tags are not writable unless added as user-defined tags in the ExifTool config file. For example, the "pdfx" namespace doesn't have a predefined set of tag names because it is used to store application-defined PDF information, so although this information will be extracted, it is only writable if the corresponding user-defined tags have been created.

The tables below list tags from the official XMP specification (with an underlined Namespace in the HTML version of this documentation), as well as extensions from various other sources. See <a href="http://www.adobe.com/devnet/xmp/">http://www.adobe.com/devnet/xmp/</a>> for the official XMP specification.

Namespace	Writable
aas	XMP aas
acdsee	XMP acdsee
acdsee-rs	XMP ACDSeeRegions
album	XMP Album
apdi	XMP apdi
apple-fi	XMP apple_fi
ast	Nikon ast
aux	XMP aux
CC	XMP cc
cell	XMP cell
crd	XMP crd
creatorAtom	XMP creatorAtom
crs	XMP crs
dc	XMP dc
Device	XMP Device
dex	XMP dex
DICOM	XMP DICOM

	DALLIOOL 13.21 149	Hames
digiKam		XMP digiKam
drone-dji		DJI XMP
dwc		DarwinCore
et		XMP ExifTool
exif		XMP exif
exifEX		XMP exifEX
expressionmedia		XMP ExpressionMedia
extensis		XMP extensis
fpv		XMP fpv
GAudio		XMP GAudio
GCamera		XMP GCamera
GContainer		XMP GContainer
GCreations		XMP GCreations
GDepth		XMP GDepth
getty		XMP GettyImages
GFocus		XMP GFocus
GImage		XMP GImage
GPano		XMP GPano
GSpherical		XMP GSpherical
hdr		XMP hdr
HDRGainMap		XMP HDRGainMap
hdrgm		XMP hdrgm
		<del>-</del>
ics		XMP ics
iptcCore		XMP iptcCore
iptcExt		XMP iptcExt
LImage		XMP LImage
lr		XMP Lightroom
mediapro		XMP MediaPro
microsoft		Microsoft XMP
MP		Microsoft MP
MP1		Microsoft MP1
mwg-coll		MWG Collections
mwg-kw		MWG Keywords
mwg-rs		MWG Regions
nine		Nikon nine
panorama		XMP panorama
pdf		XMP pdf
pdfx		XMP pdfx
photomech		PhotoMechanic XMP
photoshop		XMP photoshop
PixelLive		XMP PixelLive
plus		PLUS XMP
pmi		XMP pmi
prism		XMP prism
prl		XMP prl
prm		XMP prm
pur		XMP pur
rdf		XMP rdf
sdc		Nikon sdc
seal		XMP seal
swf		XMP swf
tiff		XMP tiff
X		XMP x
xmp		XMP xmp
xmpBJ		XMP xmpBJ
xmpDM		XMP xmpDM
xmpDSA		Panasonic DSA
MMqmx		MMqmx qMX
xmpNote		XMP xmpNote
xmpPLUS		XMP xmpPLUS
-		
xmpRights		XMP xmpRights
xmpTPg		XMP xmpTPg
-		
MP aas Tags		

# XMP aas Tags

Apple Adjustment Settings used by iPhone/iPad.

These tags belong to the ExifTool XMP-aas family 1 group.

Tag Name Writable

AffineA real AffineB real AffineC real AffineD real AffineX real AffineY real CropH integer/ CropW integer/ CropX integer/ CropY integer/ Curve0x real Curve0y real Curve1x real Curvely real Curve2x real Curve2y real Curve3x real Curve3y Curve4x real Curve4y real FaceBalanceOrigI real FaceBalanceOrigQ real FaceBalanceStrength real FaceBalanceWarmth real Highlights real/ Shadows real/ Vibrance real/

## XMP acdsee Tags

ACD Systems ACDSee namespace tags.

(A note to software developers: Re-inventing your own private tags instead of using the equivalent tags in standard XMP namespaces defeats one of the most valuable features of metadata: interoperability. Your applications mumble to themselves instead of speaking out for the rest of the world to hear.)

These tags belong to the ExifTool XMP-acdsee family 1 group.

Tag Name Writable Author string/ Caption string/ Categories string/ Collections string/ DateTime date/ DPP lang-alt/ EditStatus string/ FixtureIdentifier string/ string/+ Keywords Notes string/ ObjectCycle string/ OriginatingProgram string/ Rating real/ Rawrppused boolean/ ReleaseDate string/ ReleaseTime string/ RPP lang-alt/ string/+ Snapshots boolean/ Tagged

# XMP ACDSeeRegions Tags

These tags belong to the ExifTool XMP-acdsee-rs family 1 group.

Tag Name Writable -----RegionInfoACDSee ACDSeeRegionInfo Struct

ACDSeeRegionAppliedToDimensions ACDSeeDimensions Struct\_  ${\tt ACDSeeRegionAppliedToDimensionsH}$ real/\_ ACDSeeRegionAppliedToDimensionsUnit string/\_ ACDSeeRegionAppliedToDimensionsW real/\_ ACDSeeRegion Struct + ACDSeeRegion ACDSeeRegionALGArea ACDSeeArea Struct\_+ ACDSeeRegionALGAreaH real/\_+ ACDSeeRegionALGAreaW real/\_+ ACDSeeRegionALGAreaX real/\_+ ACDSeeRegionALGAreaY real/\_+ ACDSeeRegionDLYArea ACDSeeArea Struct\_+ ACDSeeRegionDLYAreaH real/\_+ real/\_+ ACDSeeRegionDLYAreaW real/\_+ ACDSeeRegionDLYAreaX ACDSeeRegionDLYAreaY real/\_+ ACDSeeRegionName string/\_+ ACDSeeRegionNameAssignType string/\_+ ACDSeeRegionType string/ + XMP ACDSeeRegionInfo Struct Field Name Writable \_\_\_\_\_\_ ACDSeeDimensions Struct AppliedToDimensions RegionList ACDSeeRegion Struct+ XMP ACDSeeDimensions Struct Field Name Writable Η real Unit string real XMP ACDSeeRegion Struct Field Name Writable \_\_\_\_\_ \_\_\_\_\_ ACDSeeArea Struct ALGArea DLYArea ACDSeeArea Struct Name string NameAssignType string string Type XMP ACDSeeArea Struct Field Name Writable \_\_\_\_\_ \_\_\_\_\_ Н real W real X real Y real XMP Album Tags Adobe Album namespace tags. These tags belong to the ExifTool XMP-album family 1 group. Tag Name Writable \_\_\_\_\_ Notes string XMP apdi Tags

These tags belong to the ExifTool XMP-apdi family 1 group.

Tag Name

Used in Apple HDR GainMap images.

Writable

AuxiliaryImageType string
NativeFormat string
StoredFormat string

#### XMP apple fi Tags

Face information tags written by the Apple iPhone 5 inside the mwg-rs RegionExtensions.

These tags belong to the ExifTool XMP-apple-fi family 1 group.

Tag Name Writable
-----AngleInfoRoll integer
AngleInfoYaw integer
ConfidenceLevel integer
FaceID integer
TimeStamp integer

#### XMP aux Tags

Adobe-defined auxiliary EXIF tags. This namespace existed in the XMP specification until it was dropped in 2012, presumably due to the introduction of the EXIF 2.3 for XMP specification and the exifEX namespace at this time. For this reason, tags below with equivalents in the exifEX namespace are avoided when writing.

These tags belong to the ExifTool XMP-aux family 1 group.

Tag Name \_\_\_\_\_ ApproximateFocusDistance rational DistortionCorrectionAlreadyApplied EnhanceDenoiseAlreadyApplied boolean EnhanceDenoiseLumaAmount string EnhanceDenoiseVersion string EnhanceDetailsAlreadyApplied boolean EnhanceDetailsVersion string EnhanceSuperResolutionAlreadyApplied boolean EnhanceSuperResolutionScale rational EnhanceSuperResolutionVersion string Firmware string FlashCompensation rational ImageNumber string IsMergedHDR boolean IsMergedPanorama boolean LateralChromaticAberrationCorrectionAlreadyApplied boolean Lens string LensDistortInfo string LensID string LensInfo string/ LensSerialNumber string/ NeutralDensityFactor string OwnerName string/ SerialNumber string/ VignetteCorrectionAlreadyApplied boolean

## XMP cc Tags

Creative Commons namespace tags. Note that the CC specification for XMP is non-existent, so ExifTool must make some assumptions about the format of the specific properties in XMP (see <a href="http://creativecommons.org/ns">http://creativecommons.org/ns</a>).

These tags belong to the ExifTool XMP-cc family 1 group.

Tag Name Writable
----AttributionName string

```
AttributionURL
                                                string
DeprecatedOn
                                                date
Jurisdiction
                                                string
LegalCode
                                                string
License
                                                string
MorePermissions
                                                string
Permits
                                                string+
Prohibits
                                                string+
Requires
                                                string+
UseGuidelines
                                                string
```

## XMP cell Tags

Location tags written by some Sony Ericsson phones.

These tags belong to the ExifTool XMP-cell family 1 group.

Tag Name	Writable
CellTowerID	string
CellGlobalID	string
LocationAreaCode	string
MobileCountryCode	string
MobileNetworkCode	string
CellR	string

## XMP crd Tags

Adobe Camera Raw Defaults tags.

CircGradBasedCorrMaskRangeDepthMin

These tags belong to the ExifTool XMP-crd family 1 group.

```
Tag Name
_____
                                              _____
AlreadyApplied
                                              boolean/
AutoBrightness
                                              boolean/
AutoContrast
                                              boolean/
AutoExposure
                                              boolean/
AutoLateralCA
                                              integer/
AutoShadows
                                              boolean/
AutoTone
                                              boolean/
AutoToneDigest
                                              string/
AutoToneDigestNoSat
                                              string/
AutoWhiteVersion
                                              integer/
Blacks2012
                                              integer/
BlueHue
                                              integer/
BlueSaturation
                                              integer/
Brightness
                                              integer/
CameraModelRestriction
                                              string/
CameraProfile
                                              string/
CameraProfileDigest
                                              string/
ChromaticAberrationB
                                              integer/
ChromaticAberrationR
                                             integer/
CircularGradientBasedCorrections
                                              Correction Struct+
CircGradBasedCorrActive
                                             boolean/_
CircGradBasedCorrAmount
                                              real/
CircGradBasedCorrMasks
                                              CorrectionMask Struct +
CircGradBasedCorrMaskAlpha
                                              real/_
CircGradBasedCorrMaskAngle
                                              real/_
                                              real/_
CircGradBasedCorrMaskBottom
CircGradBasedCorrMaskCenterValue
                                              real/_
CircGradBasedCorrMaskCenterWeight
                                              real/_
CircGradBasedCorrMaskRange
                                              CorrRangeMask Struct_+
CircGradBasedCorrMaskRangeAreaModels
                                              AreaModels Struct_+
CircGradBasedCorrMaskRangeAreaModelsComponents string/_+
CircGradBasedCorrMaskRangeAreaModelsColorSampleInfo string/_+
                                        real/_+
CircGradBasedCorrMaskRangeColorAmount
                                              real/_+
CircGradBasedCorrMaskRangeDepthFeather
CircGradBasedCorrMaskRangeDepthMax
                                              real/_+
```

real/\_+

```
CircGradBasedCorrMaskRangeInvert
                                               boolean/_+
CircGradBasedCorrMaskRangeLumFeather real/_+
CircGradBasedCorrMaskRangeLuminanceDepthSampleInfo string/_+
CircGradBasedCorrMaskRangeLumMax
                                      real/_+
CircGradBasedCorrMaskRangeLumMin
                                              real/_+
CircGradBasedCorrMaskRangeLumRange
                                              string/_+
                                             integer/_+
string/_+
CircGradBasedCorrMaskRangeSampleType
CircGradBasedCorrMaskRangeType
CircGradBasedCorrMaskRangeVersion
                                              string/_+
CircGradBasedCorrMaskDabs
                                              string/_
CircGradBasedCorrMaskFeather
                                              real/_
CircGradBasedCorrMaskFlipped
                                              boolean/_
CircGradBasedCorrMaskFlow
                                              real/_
CircGradBasedCorrMaskFullX
                                              real/_
CircGradBasedCorrMaskFullY
                                              real/_
CircGradBasedCorrMaskInputDigest
                                              string/_
CircGradBasedCorrMaskLeft
                                               real/_
                                              boolean/_
CircGradBasedCorrMaskMaskActive
CircGradBasedCorrMaskMaskBlendMode
                                               integer/_
CircGradBasedCorrMaskMaskDigest
                                               string/_
                                               boolean/_
CircGradBasedCorrMaskMaskInverted
CircGradBasedCorrMaskMaskName
                                               string/_
CircGradBasedCorrMaskMasks
                                               CorrectionMask Struct +
CircGradBasedCorrMaskMasksAlpha
CircGradBasedCorrMaskMasksAngle
                                              real/_
                                              real/_
                                              real/_
CircGradBasedCorrMaskMasksBottom
CircGradBasedCorrMaskMasksCenterValue
                                              real/_
                                              real/_
CircGradBasedCorrMaskMasksCenterWeight
CircGradBasedCorrMaskMasksDabs
                                              string/_+
CircGradBasedCorrMaskMasksFeather
                                              real/_
CircGradBasedCorrMaskMasksFlipped
                                              boolean/_
CircGradBasedCorrMaskMasksFlow
                                              real/
CircGradBasedCorrMaskMasksFullX
CircGradBasedCorrMaskMasksFullY
                                              real/
                                              real/_
CircGradBasedCorrMaskMasksInputDigest
                                              string/_
CircGradBasedCorrMaskMasksLeft
CircGradBasedCorrMaskMasksMaskActive
CircGradBasedCorrMaskMasksMaskBlendMode
                                              real/_
                                              boolean/_
                                              integer/_
CircGradBasedCorrMaskMasksMaskDigest
                                              string/_
                                              boolean/_
CircGradBasedCorrMaskMasksMaskInverted
CircGradBasedCorrMaskMasksMaskName
                                              string/_
                                            string/_
string/_
CircGradBasedCorrMaskMasksMaskSubType
CircGradBasedCorrMaskMasksMaskSyncID
                                             real/_
string/_
CircGradBasedCorrMaskMasksValue
CircGradBasedCorrMaskMasksMaskVersion
CircGradBasedCorrMaskMasksMidpoint real/_
CircGradBasedCorrMaskMasksOrigin string/_
CircGradBasedCorrMaskMasksPerimeterValue real/_
real/_
CircGradBasedCorrMaskMasksRadius
CircGradBasedCorrMaskMasksReferencePoint string/_
real/_
                                             real/_
CircGradBasedCorrMaskMasksRoundness
                                              real/_
CircGradBasedCorrMaskMasksSizeX
                                              real/_
CircGradBasedCorrMaskMasksSizeY
CircGradBasedCorrMaskMasksTop
                                              real/
CircGradBasedCorrMaskMaskSubType
                                              string/
CircGradBasedCorrMaskMasksVersion
                                              integer/_
                                              string/_
CircGradBasedCorrMaskMasksWhat
CircGradBasedCorrMaskMasksWholeImageArea
                                           string/_
CircGradBasedCorrMaskMasksX
                                              real/_
CircGradBasedCorrMaskMasksY
                                              real/_
CircGradBasedCorrMaskMaskSyncID
                                              string/_
CircGradBasedCorrMaskMasksZeroX
                                              real/_
CircGradBasedCorrMaskMasksZeroY
                                              real/_
CircGradBasedCorrMaskValue
                                              real/_
CircGradBasedCorrMaskMaskVersion
                                              string/_
CircGradBasedCorrMaskMidpoint
                                              real/_
                                               string/_
CircGradBasedCorrMaskOrigin
CircGradBasedCorrMaskPerimeterValue
                                               real/_
CircGradBasedCorrMaskRadius
                                               real/
```

```
CircGradBasedCorrMaskReferencePoint
                                            string/_
CircGradBasedCorrMaskRight
                                           real/_
CircGradBasedCorrMaskRoundness
                                           real/_
                                           real/_
CircGradBasedCorrMaskSizeX
CircGradBasedCorrMaskSizeY
                                           real/
CircGradBasedCorrMaskTop
                                           real/_
CircGradBasedCorrMaskVersion
                                           integer/_
CircGradBasedCorrMaskWhat
CircGradBasedCorrMaskWholeImageArea
                                           string/_
CircGradBasedCorrMaskX
                                           real/_
CircGradBasedCorrMaskY
                                            real/_
CircGradBasedCorrMaskZeroX
                                            real/_
CircGradBasedCorrMaskZeroY
                                            real/_
CircGradBasedCorrCorrectionName
                                            string/_+
CircGradBasedCorrRangeMask
                                           CorrRangeMask Struct_+
CircGradBasedCorrRangeMaskAreaModels
                                           AreaModels Struct_+
CircGradBasedCorrRangeMaskAreaModelsComponents string/_+
CircGradBasedCorrRangeMaskAreaModelsColorSampleInfo string/_+
CircGradBasedCorrRangeMaskColorAmount real/_+
CircGradBasedCorrRangeMaskDepthFeather
                                            real/_+
CircGradBasedCorrRangeMaskDepthMax
                                            real/ +
CircGradBasedCorrRangeMaskDepthMin
                                            real/_+
                                           boolean/_+
CircGradBasedCorrRangeMaskInvert
CircGradBasedCorrRangeMaskLumFeather
                                           real/_+
CircGradBasedCorrRangeMaskLuminanceDepthSampleInfo string/_+
CircGradBasedCorrRangeMaskLumMax real/_+
                                           real/_+
CircGradBasedCorrRangeMaskLumMin
CircGradBasedCorrRangeMaskLumRange
                                           string/_+
CircGradBasedCorrRangeMaskSampleType
                                           integer/ +
CircGradBasedCorrRangeMaskType
CircGradBasedCorrRangeMaskVersion
                                           string/ +
                                           string/ +
CircGradBasedCorrCorrectionSyncID
                                           string/ +
CircGradBasedCorrBlacks2012
                                           real/_
CircGradBasedCorrBrightness
                                           real/_
CircGradBasedCorrClarity
                                           real/_
CircGradBasedCorrClarity2012
                                           real/_
CircGradBasedCorrContrast
                                           real/_
CircGradBasedCorrContrast2012
                                           real/_
CircGradBasedCorrDefringe
                                            real/_
CircGradBasedCorrDehaze
                                            real/_
                                            real/_
CircGradBasedCorrExposure
CircGradBasedCorrExposure2012
                                            real/_
CircGradBasedCorrHighlights2012
                                            real/_
CircGradBasedCorrHue
                                            real/_
                                            real/_
CircGradBasedCorrLuminanceNoise
                                            real/_
CircGradBasedCorrMoire
CircGradBasedCorrSaturation
                                            real/
CircGradBasedCorrShadows2012
                                            real/_
CircGradBasedCorrSharpness
                                            real/_
CircGradBasedCorrTemperature
                                            real/
CircGradBasedCorrTexture
                                            real/
CircGradBasedCorrTint
                                            real/_
                                           real/_
CircGradBasedCorrToningHue
CircGradBasedCorrToningSaturation
                                           real/
CircGradBasedCorrWhites2012
                                           real/
CircGradBasedCorrWhat
                                            string/
Clarity
                                            integer/
Clarity2012
                                            integer/
ClipboardAspectRatio
                                            integer/
ClipboardOrientation
                                            integer/
Cluster
                                            string/
ColorGradeBlending
                                            integer/
ColorGradeGlobalHue
                                            integer/
ColorGradeGlobalLum
                                            integer/
ColorGradeGlobalSat
                                            integer/
ColorGradeHighlightLum
                                            integer/
ColorGradeMidtoneHue
                                            integer/
ColorGradeMidtoneLum
                                             integer/
ColorGradeMidtoneSat
                                             integer/
ColorGradeShadowLum
                                             integer/
```

```
ColorNoiseReduction
                                              integer/
ColorNoiseReductionDetail
                                              integer/
ColorNoiseReductionSmoothness
                                              integer/
CompatibleVersion
                                              string/
ContactInfo
                                              string/
Contrast
                                              integer/
Contrast2012
                                              integer/
Converter
                                              string/
ConvertToGrayscale
                                              boolean/
Copyright
                                              string/
                                              real/
CropAngle
CropBottom
                                              real/
CropConstrainToWarp
                                              integer/
CropHeight
                                              real/
CropLeft
                                              real/
CropRight
                                              real/
CropTop
                                              real/
CropUnit
                                              integer/
CropUnits
                                              integer/
CropWidth
                                              real/
DefaultAutoGray
                                              boolean/
DefaultAutoTone
                                              boolean/
DefaultsSpecificToISO
                                              boolean/
DefaultsSpecificToSerial
                                              boolean/
Defringe
                                              integer/
DefringeGreenAmount
                                              integer/
DefringeGreenHueHi
                                              integer/
DefringeGreenHueLo
                                              integer/
DefringePurpleAmount
                                              integer/
DefringePurpleHueHi
                                              integer/
DefringePurpleHueLo
                                              integer/
Dehaze
                                              real/
DepthBasedCorrections
                                              DepthBasedCorr Struct+
DepthBasedCorrCorrectionActive
                                             boolean/_+
DepthBasedCorrCorrectionAmount
                                              real/ +
DepthBasedCorrMask
                                              CorrectionMask Struct +
DepthBasedCorrMaskAlpha
                                              real/_
                                              real/_
DepthBasedCorrMaskAngle
DepthBasedCorrMaskBottom
                                              real/_
                                              real/_
DepthBasedCorrMaskCenterValue
                                              real/_
DepthBasedCorrMaskCenterWeight
DepthBasedCorrMaskRange
                                              CorrRangeMask Struct +
DepthBasedCorrMaskRangeAreaModels
                                              AreaModels Struct +
DepthBasedCorrMaskRangeAreaModelsComponents string/ +
DepthBasedCorrMaskRangeAreaModelsColorSampleInfo string/ +
DepthBasedCorrMaskRangeColorAmount
                                              real/_+
                                              real/ +
DepthBasedCorrMaskRangeDepthFeather
                                              real/ +
DepthBasedCorrMaskRangeDepthMax
DepthBasedCorrMaskRangeDepthMin
                                              real/_+
DepthBasedCorrMaskRangeInvert
                                              boolean/ +
DepthBasedCorrMaskRangeLumFeather
                                              real/ +
DepthBasedCorrMaskRangeLuminanceDepthSampleInfo string/_+
DepthBasedCorrMaskRangeLumMax
                                              real/ +
DepthBasedCorrMaskRangeLumMin
                                              real/ +
DepthBasedCorrMaskRangeLumRange
                                             string/ +
DepthBasedCorrMaskRangeSampleType
                                             integer/ +
DepthBasedCorrMaskRangeType
                                             string/ +
DepthBasedCorrMaskRangeVersion
                                              string/_+
                                              string/_+
DepthBasedCorrMaskDabs
DepthBasedCorrMaskFeather
                                              real/
DepthBasedCorrMaskFlipped
                                              boolean/_
DepthBasedCorrMaskFlow
                                              real/_
DepthBasedCorrMaskFullX
                                              real/_
DepthBasedCorrMaskFullY
                                              real/_
DepthBasedCorrMaskInputDigest
                                              string/_
                                              real/_
DepthBasedCorrMaskLeft
                                              boolean/_
DepthBasedCorrMaskMaskActive
                                              integer/_
DepthBasedCorrMaskMaskBlendMode
DepthBasedCorrMaskMaskDigest
                                              string/
DepthBasedCorrMaskMaskInverted
                                              boolean/_
```

```
DepthBasedCorrMaskMaskName
                                              string/_
DepthBasedCorrMaskMasks
                                             CorrectionMask Struct_+
DepthBasedCorrMaskMasksAlpha
                                             real/_
                                            real/_
DepthBasedCorrMaskMasksAngle
DepthBasedCorrMaskMasksBottom
                                            real/
DepthBasedCorrMaskMasksCenterValue
                                            real/_
DepthBasedCorrMaskMasksCenterWeight
                                           real/_
DepthBasedCorrMaskMasksDabs
                                            string/_+
DepthBasedCorrMaskMasksFeather
                                            real/_
DepthBasedCorrMaskMasksFlipped
                                            boolean/_
DepthBasedCorrMaskMasksFlow
                                            real/_
DepthBasedCorrMaskMasksFullX
                                            real/_
DepthBasedCorrMaskMasksFullY
                                            real/_
                                          string/_
DepthBasedCorrMaskMasksInputDigest
DepthBasedCorrMaskMasksLeft
                                            real/_
DepthBasedCorrMaskMasksMaskActive
                                            boolean/_
DepthBasedCorrMaskMasksMaskBlendMode
DepthBasedCorrMaskMasksMaskDigest
DepthBasedCorrMaskMasksMaskInverted
DepthBasedCorrMaskMasksMaskName
                                          integer/_
string/_
boolean/_
                                             string/_
DepthBasedCorrMaskMasksMaskName
DepthBasedCorrMaskMasksMaskSubType
                                           string/_
DepthBasedCorrMaskMasksMaskSyncID
                                             string/_
                                            real/_
DepthBasedCorrMaskMasksValue
DepthBasedCorrMaskMasksMaskVersion
                                            string/_
                                            real/_
DepthBasedCorrMaskMasksMidpoint
DepthBasedCorrMaskMasksOrigin
                                            string/_
                                            real/_
DepthBasedCorrMaskMasksPerimeterValue
DepthBasedCorrMaskMasksRadius
                                            real/
DepthBasedCorrMaskMasksReferencePoint
                                            string/_
DepthBasedCorrMaskMasksRight
                                            real/
DepthBasedCorrMaskMasksRoundness
                                            real/
DepthBasedCorrMaskMasksSizeX
                                            real/
DepthBasedCorrMaskMasksSizeY
                                            real/
DepthBasedCorrMaskMasksTop
                                            real/
DepthBasedCorrMaskMaskSubType
                                            string/_
DepthBasedCorrMaskMasksVersion
                                            integer/_
DepthBasedCorrMaskMasksWhat
                                            string/_
DepthBasedCorrMaskMasksWholeImageArea
                                            string/_
DepthBasedCorrMaskMasksX
                                             real/_
DepthBasedCorrMaskMasksY
                                            real/_
                                             string/_
DepthBasedCorrMaskMaskSyncID
DepthBasedCorrMaskMasksZeroX
                                            real/_
DepthBasedCorrMaskMasksZeroY
                                            real/_
DepthBasedCorrMaskValue
                                             real/
DepthBasedCorrMaskMaskVersion
                                             string/
DepthBasedCorrMaskMidpoint
                                             real/_
                                            string/_
DepthBasedCorrMaskOrigin
                                            real/_
DepthBasedCorrMaskPerimeterValue
                                            real/_
DepthBasedCorrMaskRadius
DepthBasedCorrMaskReferencePoint
                                            string/_
                                            real/_
DepthBasedCorrMaskRight
DepthBasedCorrMaskRoundness
                                            real/
                                            real/_
DepthBasedCorrMaskSizeX
                                            real/
DepthBasedCorrMaskSizeY
DepthBasedCorrMaskTop
                                            real/
DepthBasedCorrMaskVersion
                                            integer/_
DepthBasedCorrMaskWhat
                                            string/_
DepthBasedCorrMaskWholeImageArea
                                            string/_
                                            real/_
DepthBasedCorrMaskX
                                             real/_
DepthBasedCorrMaskY
DepthBasedCorrMaskZeroX
                                             real/_
DepthBasedCorrMaskZeroY
                                             real/_
DepthBasedCorrCorrectionSyncID
                                             string/_+
DepthBasedCorrLocalCorrectedDepth
                                            real/_+
DepthBasedCorrLocalCurveRefineSaturation
                                             real/_+
                                             string/_+
DepthBasedCorrWhat
DepthMapInfo
                                             DepthMapInfo Struct
DepthMapInfoBaseHighlightGuideInputDigest
                                            string/_
                                             string/_
DepthMapInfoBaseHighlightGuideTable
DepthMapInfoBaseHighlightGuideVersion
                                             string/_
```

```
DepthMapInfoBaseLayeredDepthInputDigest
                                            string/_
DepthMapInfoBaseLayeredDepthTable
                                            string/_
DepthMapInfoBaseLayeredDepthVersion
                                           string/_
                                           string/_
DepthMapInfoBaseRawDepthInputDigest
DepthMapInfoBaseRawDepthTable
                                           string/
DepthMapInfoBaseRawDepthVersion
                                           string/_
DepthMapInfoDepthSource
                                            string/_
Description
                                            lang-alt/
DNGIgnoreSidecars
                                            boolean/
Exposure
                                            real/
Exposure2012
                                            real/
                                            integer/
FillLight
GradientBasedCorrections
                                            Correction Struct+
GradientBasedCorrActive
                                            boolean/_
GradientBasedCorrAmount
                                            real/_
GradientBasedCorrMasks
                                            CorrectionMask Struct_+
GradientBasedCorrMaskAlpha
                                            real/_
GradientBasedCorrMaskAngle
                                            real/_
                                            real/_
GradientBasedCorrMaskBottom
GradientBasedCorrMaskCenterValue
                                            real/_
                                            real/_
GradientBasedCorrMaskCenterWeight
GradientBasedCorrMaskRange
                                            CorrRangeMask Struct_+
GradientBasedCorrMaskRangeAreaModels
                                            AreaModels Struct +
GradientBasedCorrMaskRangeAreaModelsComponents string/ +
GradientBasedCorrMaskRangeAreaModelsColorSampleInfo string/_+
GradientBasedCorrMaskRangeColorAmount
                                           real/ +
                                           real/_+
GradientBasedCorrMaskRangeDepthFeather
GradientBasedCorrMaskRangeDepthMax
                                           real/ +
GradientBasedCorrMaskRangeDepthMin
                                            real/ +
GradientBasedCorrMaskRangeInvert
                                           boolean/_+
GradientBasedCorrMaskRangeLumFeather
                                           real/ +
GradientBasedCorrMaskRangeLuminanceDepthSampleInfo string/ +
GradientBasedCorrMaskRangeLumMax
                                           real/ +
GradientBasedCorrMaskRangeLumMin
                                           real/_+
GradientBasedCorrMaskRangeLumRange
                                           string/ +
GradientBasedCorrMaskRangeSampleType
                                           integer/ +
GradientBasedCorrMaskRangeType
                                           string/_+
GradientBasedCorrMaskRangeVersion
                                           string/_+
GradientBasedCorrMaskDabs
                                            string/_
                                            real/_
GradientBasedCorrMaskFeather
GradientBasedCorrMaskFlipped
                                            boolean/
GradientBasedCorrMaskFlow
                                            real/_
GradientBasedCorrMaskFullX
                                            real/_
GradientBasedCorrMaskFullY
                                            real/
GradientBasedCorrMaskInputDigest
                                            string/
GradientBasedCorrMaskLeft
                                            real/_
                                           boolean/_
GradientBasedCorrMaskMaskActive
GradientBasedCorrMaskMaskBlendMode
                                            integer/_
GradientBasedCorrMaskMaskDigest
                                            string/_
GradientBasedCorrMaskMaskInverted
                                           boolean/_
GradientBasedCorrMaskMaskName
                                            string/
GradientBasedCorrMaskMasks
                                           CorrectionMask Struct_+
                                           real/_
GradientBasedCorrMaskMasksAlpha
                                           real/
GradientBasedCorrMaskMasksAngle
GradientBasedCorrMaskMasksBottom
                                           real/
GradientBasedCorrMaskMasksCenterValue
                                           real/
GradientBasedCorrMaskMasksCenterWeight
                                           real/
GradientBasedCorrMaskMasksDabs
                                           string/_+
                                           real/_
GradientBasedCorrMaskMasksFeather
GradientBasedCorrMaskMasksFlipped
                                           boolean/
GradientBasedCorrMaskMasksFlow
                                           real/_
GradientBasedCorrMaskMasksFullX
                                           real/_
GradientBasedCorrMaskMasksFullY
                                           real/_
GradientBasedCorrMaskMasksInputDigest
                                           string/_
GradientBasedCorrMaskMasksLeft
                                            real/_
GradientBasedCorrMaskMasksMaskActive
                                            boolean/_
GradientBasedCorrMaskMasksMaskBlendMode
                                            integer/_
                                            string/_
GradientBasedCorrMaskMasksMaskDigest
GradientBasedCorrMaskMasksMaskInverted
                                            boolean/_
GradientBasedCorrMaskMasksMaskName
                                            string/_
```

```
GradientBasedCorrMaskMasksMaskSubType
                                          string/_
GradientBasedCorrMaskMasksMaskSyncID
                                          string/_
GradientBasedCorrMaskMasksValue
                                          real/_
GradientBasedCorrMaskMasksMaskVersion
                                          string/_
GradientBasedCorrMaskMasksMidpoint
GradientBasedCorrMaskMasksOrigin
                                          real/
                                          string/_
                                       real/_
real/_
GradientBasedCorrMaskMasksPerimeterValue
GradientBasedCorrMaskMasksRadius
GradientBasedCorrMaskMasksReferencePoint string/_
GradientBasedCorrMaskMasksRight
                                          real/_
                                        real/_
GradientBasedCorrMaskMasksRoundness
GradientBasedCorrMaskMasksSizeX
                                          real/_
GradientBasedCorrMaskMasksSizeY
                                          real/_
GradientBasedCorrMaskMasksTop
                                          real/_
GradientBasedCorrMaskMaskSubType
                                          string/
GradientBasedCorrMaskMasksVersion
                                          integer/_
GradientBasedCorrMaskMasksWhat
                                          string/_
GradientBasedCorrMaskMasksWholeImageArea
                                          string/_
GradientBasedCorrMaskMasksX
                                           real/_
GradientBasedCorrMaskMasksY
                                           real/_
GradientBasedCorrMaskMaskSyncID
                                           string/_
GradientBasedCorrMaskMasksZeroX
                                           real/_
GradientBasedCorrMaskMasksZeroY
                                           real/
GradientBasedCorrMaskValue
                                           real/_
GradientBasedCorrMaskMaskVersion
                                           string/_
GradientBasedCorrMaskMidpoint
                                          real/_
GradientBasedCorrMaskOrigin
                                          string/
                                          real/_
GradientBasedCorrMaskPerimeterValue
GradientBasedCorrMaskRadius
                                          real/
GradientBasedCorrMaskReferencePoint
                                          string/
GradientBasedCorrMaskRight
                                          real/
GradientBasedCorrMaskRoundness
                                          real/
GradientBasedCorrMaskSizeX
                                          real/
GradientBasedCorrMaskSizeY
                                          real/_
GradientBasedCorrMaskTop
                                          real/
GradientBasedCorrMaskVersion
                                          integer/
GradientBasedCorrMaskWhat
                                          string/_
GradientBasedCorrMaskWholeImageArea
                                          string/
GradientBasedCorrMaskX
                                           real/_
                                           real/_
GradientBasedCorrMaskY
GradientBasedCorrMaskZeroX
                                           real/_
GradientBasedCorrMaskZeroY
                                           real/_
GradientBasedCorrCorrectionName
                                           string/ +
GradientBasedCorrRangeMask
                                           CorrRangeMask Struct +
GradientBasedCorrRangeMaskAreaModels
                                           AreaModels Struct +
GradientBasedCorrRangeMaskAreaModelsComponents string/_+
GradientBasedCorrRangeMaskAreaModelsColorSampleInfo string/ +
GradientBasedCorrRangeMaskColorAmount real/_+
                                          real/_+
real/_+
GradientBasedCorrRangeMaskDepthFeather
GradientBasedCorrRangeMaskDepthMax
                                          real/ +
GradientBasedCorrRangeMaskDepthMin
                                          boolean/_+
GradientBasedCorrRangeMaskInvert
GradientBasedCorrRangeMaskLumFeather
                                          real/ +
GradientBasedCorrRangeMaskLuminanceDepthSampleInfo string/ +
GradientBasedCorrRangeMaskLumMax
                                   real/ +
GradientBasedCorrRangeMaskLumMin
                                          real/ +
GradientBasedCorrRangeMaskLumRange
                                          string/ +
GradientBasedCorrRangeMaskSampleType
                                         integer/_+
GradientBasedCorrRangeMaskType
                                          string/_+
GradientBasedCorrRangeMaskVersion
                                          string/ +
GradientBasedCorrCorrectionSyncID
                                          string/_+
GradientBasedCorrBlacks2012
                                          real/_
GradientBasedCorrBrightness
                                          real/_
GradientBasedCorrClarity
                                          real/_
GradientBasedCorrClarity2012
                                          real/_
GradientBasedCorrContrast
                                           real/_
GradientBasedCorrContrast2012
                                           real/_
                                           real/_
GradientBasedCorrDefringe
                                           real/_
GradientBasedCorrDehaze
GradientBasedCorrExposure
                                           real/_
```

EXIITOOI 13.24	Tag	Names	
GradientBasedCorrExposure2012			real/_
GradientBasedCorrHighlights2012			real/
GradientBasedCorrHue			real/
GradientBasedCorrLuminanceNoise			real/_
GradientBasedCorrMoire			real/_
GradientBasedCorrSaturation			real/_
GradientBasedCorrShadows2012			real/_
GradientBasedCorrSharpness			real/_
GradientBasedCorrTemperature			real/_
GradientBasedCorrTexture			real/_
GradientBasedCorrTint			real/_
GradientBasedCorrToningHue			real/_
GradientBasedCorrToningSaturation			real/
GradientBasedCorrWhites2012			real/
			· <del>-</del>
GradientBasedCorrWhat			string/_
GrainAmount			integer/
GrainFrequency			integer/
GrainSeed			integer/
GrainSize			integer/
GrayMixerAqua			integer/
GrayMixerBlue			integer/
GrayMixerGreen			integer/
GrayMixerMagenta			integer/
= -			<b>5</b> ,
GrayMixerOrange			integer/
GrayMixerPurple			integer/
GrayMixerRed			integer/
GrayMixerYellow			integer/
GreenHue			integer/
GreenSaturation			integer/
Group			lang-alt/
HasCrop			boolean/
HasSettings			boolean/
HDREditMode			integer/
Highlight2012			integer/
HighlightRecovery			integer/
Highlights2012			integer/
HueAdjustmentAqua			integer/
HueAdjustmentBlue			integer/
HueAdjustmentGreen			integer/
HueAdjustmentMagenta			integer/
HueAdjustmentOrange			integer/
HueAdjustmentPurple			integer/
HueAdjustmentRed			integer/
HueAdjustmentYellow			integer/
IncrementalTemperature			integer/
IncrementalTint			integer/
JPEGHandling			string/
LensBlur			LensBlur Struct
LensBlurActive			boolean/_
LensBlurAmount			real/_
LensBlurBokehAspect			real/
LensBlurBokehRotation			real/_
LensBlurBokehShape			real/_
LensBlurBokehShapeDetail			real/_
LensBlurCatEyeAmount			real/_
LensBlurCatEyeScale			real/_
LensBlurFocalRange			string/_
LensBlurFocalRangeSource			real/_
LensBlurHighlightsBoost			real/_
LensBlurHighlightsThreshold			real/_
LensBlurSampledArea			string/_
LensBlurSampledRange			string/_
LensBlurSphericalAberration			real/_
LensBlurSubjectRange			string/_
LensBlurVersion			string/_
LensManualDistortionAmount			integer/
LensProfileChromaticAberrationScal	.e		integer/
LensProfileDigest			string/
LensProfileDistortionScale			integer/
LensProfileEnable			integer/

```
LensProfileFilename
                                             string/
LensProfileIsEmbedded
                                             boolean/
LensProfileMatchKeyCameraModelName
                                            string/
LensProfileMatchKeyExifMake
                                            string/
LensProfileMatchKeyExifModel
                                            string/
LensProfileMatchKeyIsRaw
                                            boolean/
LensProfileMatchKeyLensID
                                            string/
LensProfileMatchKeyLensInfo
                                            string/
LensProfileMatchKeyLensName
                                            string/
LensProfileMatchKeySensorFormatFactor
                                            real/
LensProfileName
                                             string/
LensProfileSetup
                                             string/
LensProfileVignettingScale
                                             integer/
                                             Look Struct
Look
LookAmount
                                             string/_
LookCluster
                                             string/_
LookCopyright
                                             string/_
LookGroup
                                             lang-alt/_
LookName
                                             string/
LookParameters
                                             LookParms Struct_
                                             string/_
LookParametersCameraProfile
                                             string/_
LookParametersClarity2012
                                             string/_
LookParametersConvertToGrayscale
LookParametersHighlights2012
                                             string/_
LookParametersLookTable
                                             string/_
LookParametersProcessVersion
                                             string/_
LookParametersShadows2012
                                             string/
LookParametersToneCurvePV2012
                                            string/ +
LookParametersToneCurvePV2012Blue
                                            string/ +
LookParametersToneCurvePV2012Green
                                            string/ +
LookParametersToneCurvePV2012Red
                                            string/ +
LookParametersVersion
                                             string/
LookSupportsAmount
                                             string/
LookSupportsMonochrome
                                             string/_
LookSupportsOutputReferred
                                             string/
LookUUID
                                            string/
LuminanceAdjustmentAqua
                                             integer/
LuminanceAdjustmentBlue
                                             integer/
LuminanceAdjustmentGreen
                                             integer/
LuminanceAdjustmentMagenta
                                             integer/
LuminanceAdjustmentOrange
                                             integer/
LuminanceAdiustmentPurple
                                             integer/
LuminanceAdjustmentRed
                                             integer/
LuminanceAdjustmentYellow
                                             integer/
LuminanceNoiseReductionContrast
                                             integer/
LuminanceNoiseReductionDetail
                                             integer/
                                             integer/
LuminanceSmoothing
MaskGroupBasedCorrections
                                             Correction Struct+
MaskGroupBasedCorrActive
                                            boolean/_
{\tt MaskGroupBasedCorrAmount}
                                            real/_
MaskGroupBasedCorrMask
                                            CorrectionMask Struct_+
MaskGroupBasedCorrMaskAlpha
                                            real/_
MaskGroupBasedCorrMaskAngle
                                            real/
                                            real/_
MaskGroupBasedCorrMaskBottom
MaskGroupBasedCorrMaskCenterValue
                                             real/
MaskGroupBasedCorrMaskCenterWeight
                                             real/
MaskGroupBasedCorrMaskRange
                                             CorrRangeMask Struct +
MaskGroupBasedCorrMaskRangeAreaModels
                                             AreaModels Struct_+
MaskGroupBasedCorrMaskRangeAreaModelsComponents string/_+
MaskGroupBasedCorrMaskRangeAreaModelsColorSampleInfo string/_+
MaskGroupBasedCorrMaskRangeColorAmount
                                         real/_+
                                           real/_+
MaskGroupBasedCorrMaskRangeDepthFeather
MaskGroupBasedCorrMaskRangeDepthMax
                                             real/_+
MaskGroupBasedCorrMaskRangeDepthMin
                                             real/_+
MaskGroupBasedCorrMaskRangeInvert
                                             boolean/_+
                                             real/_+
MaskGroupBasedCorrMaskRangeLumFeather
MaskGroupBasedCorrMaskRangeLuminanceDepthSampleInfo string/_+
                                  real/_+
MaskGroupBasedCorrMaskRangeLumMax
MaskGroupBasedCorrMaskRangeLumMin
                                             real/_+
MaskGroupBasedCorrMaskRangeLumRange
                                             string/_+
```

```
MaskGroupBasedCorrMaskRangeSampleType
                                          integer/_+
MaskGroupBasedCorrMaskRangeType
                                           string/_+
MaskGroupBasedCorrMaskRangeVersion
                                          string/_+
MaskGroupBasedCorrMaskDabs
                                           string/_+
MaskGroupBasedCorrMaskFeather
                                           real/
MaskGroupBasedCorrMaskFlipped
                                          boolean/_
MaskGroupBasedCorrMaskFlow
                                          real/_
MaskGroupBasedCorrMaskFullX
                                          real/
                                          real/_
MaskGroupBasedCorrMaskFullY
                                          string/_
MaskGroupBasedCorrMaskInputDigest
MaskGroupBasedCorrMaskLeft
                                           real/_
                                          boolean/_
MaskGroupBasedCorrMaskMaskActive
MaskGroupBasedCorrMaskMaskBlendMode
                                          integer/_
MaskGroupBasedCorrMaskMaskDigest
                                          string/_
MaskGroupBasedCorrMaskMaskInverted
                                          boolean/_
MaskGroupBasedCorrMaskMaskName
                                          string/_
MaskGroupBasedCorrMaskMasks
                                           CorrectionMask Struct_+
MaskGroupBasedCorrMaskMasksAlpha
                                          real/_
MaskGroupBasedCorrMaskMasksAngle
                                           real/_
                                           real/_
MaskGroupBasedCorrMaskMasksBottom
                                           real/_
MaskGroupBasedCorrMaskMasksCenterValue
                                            real/_
MaskGroupBasedCorrMaskMasksCenterWeight
MaskGroupBasedCorrMaskMasksDabs
                                           string/ +
MaskGroupBasedCorrMaskMasksFeather
                                            real/_
                                          boolean/_
MaskGroupBasedCorrMaskMasksFlipped
                                           real/_
MaskGroupBasedCorrMaskMasksFlow
                                           real/_
MaskGroupBasedCorrMaskMasksFullX
MaskGroupBasedCorrMaskMasksFullY
                                          real/_
                                          string/_
MaskGroupBasedCorrMaskMasksInputDigest
MaskGroupBasedCorrMaskMasksLeft
                                           real/
MaskGroupBasedCorrMaskMasksMaskActive
                                          boolean/
MaskGroupBasedCorrMaskMasksMaskBlendMode
                                          integer/_
MaskGroupBasedCorrMaskMasksMaskDigest
                                          string/
MaskGroupBasedCorrMaskMasksMaskInverted
                                          boolean/_
MaskGroupBasedCorrMaskMasksMaskName
                                          string/_
MaskGroupBasedCorrMaskMasksMaskSubType
                                          string/_
MaskGroupBasedCorrMaskMasksMaskSyncID
                                          string/_
MaskGroupBasedCorrMaskMasksValue
                                          real/_
MaskGroupBasedCorrMaskMasksMaskVersion
                                          string/_
MaskGroupBasedCorrMaskMasksMidpoint
                                          real/_
                                          string/_
MaskGroupBasedCorrMaskMasksOrigin
MaskGroupBasedCorrMaskMasksPerimeterValue
                                          real/_
                                         real/_
string/_
MaskGroupBasedCorrMaskMasksRadius
MaskGroupBasedCorrMaskMasksReferencePoint
                                            real/_
MaskGroupBasedCorrMaskMasksRight
                                          real/_
real/_
MaskGroupBasedCorrMaskMasksRoundness
MaskGroupBasedCorrMaskMasksSizeX
                                           real/_
MaskGroupBasedCorrMaskMasksSizeY
                                           real/_
MaskGroupBasedCorrMaskMasksTop
                                          string/
MaskGroupBasedCorrMaskMaskSubType
                                           integer/_
MaskGroupBasedCorrMaskMasksVersion
                                          string/_
MaskGroupBasedCorrMaskMasksWhat
                                          string/_
MaskGroupBasedCorrMaskMasksWholeImageArea
                                          real/_
MaskGroupBasedCorrMaskMasksX
MaskGroupBasedCorrMaskMasksY
                                          real/
                                          string/_
MaskGroupBasedCorrMaskMaskSyncID
MaskGroupBasedCorrMaskMasksZeroX
                                          real/
MaskGroupBasedCorrMaskMasksZeroY
                                          real/_
                                          real/_
MaskGroupBasedCorrMaskValue
                                          string/_
MaskGroupBasedCorrMaskMaskVersion
MaskGroupBasedCorrMaskMidpoint
                                          real/_
MaskGroupBasedCorrMaskOrigin
                                          string/_
MaskGroupBasedCorrMaskPerimeterValue
                                          real/_
MaskGroupBasedCorrMaskRadius
                                          real/_
MaskGroupBasedCorrMaskReferencePoint
                                          string/_
MaskGroupBasedCorrMaskRight
                                           real/_
                                           real/_
MaskGroupBasedCorrMaskRoundness
                                            real/_
MaskGroupBasedCorrMaskSizeX
                                            real/_
MaskGroupBasedCorrMaskSizeY
MaskGroupBasedCorrMaskTop
                                            real/_
```

```
MaskGroupBasedCorrMaskVersion
                                            integer/_
MaskGroupBasedCorrMaskWhat
                                           string/_
MaskGroupBasedCorrMaskWholeImageArea
                                           string/_
MaskGroupBasedCorrMaskX
                                           real/_
MaskGroupBasedCorrMaskY
                                           real/
MaskGroupBasedCorrMaskZeroX
                                           real/_
MaskGroupBasedCorrMaskZeroY
                                           real/_
MaskGroupBasedCorrCorrectionName
                                           string/_+
MaskGroupBasedCorrRangeMask
                                           CorrRangeMask Struct_+
MaskGroupBasedCorrRangeMaskAreaModels AreaModels Struct_+
MaskGroupBasedCorrRangeMaskAreaModelsComponents string/_+
MaskGroupBasedCorrRangeMaskAreaModelsColorSampleInfo string/_+
MaskGroupBasedCorrRangeMaskColorAmount
                                       real/_+
MaskGroupBasedCorrRangeMaskDepthFeather
                                           real/_+
MaskGroupBasedCorrRangeMaskDepthMax
                                           real/_+
                                           real/_+
boolean/_+
MaskGroupBasedCorrRangeMaskDepthMin
MaskGroupBasedCorrRangeMaskInvert
MaskGroupBasedCorrRangeMaskLumFeather
                                            real/ +
MaskGroupBasedCorrRangeMaskLuminanceDepthSampleInfo string/_+
                                    real/_+
MaskGroupBasedCorrRangeMaskLumMax
MaskGroupBasedCorrRangeMaskLumMin
                                            real/ +
MaskGroupBasedCorrRangeMaskLumRange
                                            string/_+
                                           sur....__
integer/_+
MaskGroupBasedCorrRangeMaskSampleType
                                           string/_+
MaskGroupBasedCorrRangeMaskType
                                           string/_+
MaskGroupBasedCorrRangeMaskVersion
                                           string/_+
MaskGroupBasedCorrCorrectionSyncID
MaskGroupBasedCorrBlacks2012
                                           real/_
MaskGroupBasedCorrBrightness
                                           real/_
MaskGroupBasedCorrClarity
                                           real/
MaskGroupBasedCorrClaritv2012
                                           real/
MaskGroupBasedCorrContrast
                                           real/
MaskGroupBasedCorrContrast2012
                                           real/
MaskGroupBasedCorrDefringe
                                           real/
MaskGroupBasedCorrDehaze
                                           real/_
MaskGroupBasedCorrExposure
                                           real/
MaskGroupBasedCorrExposure2012
                                           real/_
MaskGroupBasedCorrHighlights2012
                                           real/_
MaskGroupBasedCorrHue
                                           real/_
MaskGroupBasedCorrLuminanceNoise
                                           real/_
MaskGroupBasedCorrMoire
                                           real/_
MaskGroupBasedCorrSaturation
                                           real/_
MaskGroupBasedCorrShadows2012
                                           real/_
MaskGroupBasedCorrSharpness
                                           real/_
                                            real/_
MaskGroupBasedCorrTemperature
                                            real/_
MaskGroupBasedCorrTexture
                                            real/_
MaskGroupBasedCorrTint
                                            real/_
MaskGroupBasedCorrToningHue
MaskGroupBasedCorrToningSaturation
                                           real/_
MaskGroupBasedCorrWhites2012
                                            real/_
MaskGroupBasedCorrWhat
                                            string/
                                            string/
MoireFilter
                                            lang-alt/
Name
NegativeCacheLargePreviewSize
                                           integer/
NegativeCacheMaximumSize
                                           real/
NegativeCachePath
                                           string/
OverrideLookVignette
                                           boolean/
PaintBasedCorrections
                                            Correction Struct+
PaintCorrectionActive
                                           boolean/_
                                           real/_
PaintCorrectionAmount
PaintBasedCorrectionMasks
                                           CorrectionMask Struct_+
PaintCorrectionMaskAlpha
                                           real/_
PaintCorrectionMaskAngle
                                           real/_
PaintCorrectionMaskBottom
                                           real/_
PaintCorrectionMaskCenterValue
                                           real/_
PaintCorrectionMaskCenterWeight
                                           real/_
PaintCorrectionMaskRange
                                            CorrRangeMask Struct_+
                                           AreaModels Struct_+
PaintCorrectionMaskRangeAreaModels
PaintCorrectionMaskRangeAreaModelsComponents string/_+
PaintCorrectionMaskRangeAreaModelsColorSampleInfo string/ +
PaintCorrectionMaskRangeColorAmount
                                            real/_+
```

```
PaintCorrectionMaskRangeDepthFeather
                                             real/_+
PaintCorrectionMaskRangeDepthMax
                                             real/ +
PaintCorrectionMaskRangeDepthMin
                                              real/_+
PaintCorrectionMaskRangeInvert
                                              boolean/_+
PaintCorrectionMaskRangeLumFeather
                                              real/ +
PaintCorrectionMaskRangeLuminanceDepthSampleInfo string/_+
PaintCorrectionMaskRangeLumMax
                                             real/_+
PaintCorrectionMaskRangeLumMin
                                             real/_+
PaintCorrectionMaskRangeLumRange
                                             string/_+
PaintCorrectionMaskRangeSampleType
                                             integer/_+
PaintCorrectionMaskRangeType
                                             string/_+
PaintCorrectionMaskRangeVersion
                                             string/_+
PaintCorrectionMaskDabs
                                             string/_
PaintCorrectionMaskFeather
                                              real/_
PaintCorrectionMaskFlipped
                                              boolean/_
PaintCorrectionMaskFlow
                                              real/_
PaintCorrectionMaskFullX
                                              real/_
PaintCorrectionMaskFullY
                                             real/_
PaintCorrectionMaskInputDigest
                                              string/_
PaintCorrectionMaskLeft
                                               real/_
PaintCorrectionMaskMaskActive
                                              boolean/
PaintCorrectionMaskMaskBlendMode
                                              integer/_
                                              string/_
PaintCorrectionMaskMaskDigest
PaintCorrectionMaskMaskInverted
                                              boolean/
PaintCorrectionMaskMaskName
                                              string/_
PaintCorrectionMaskMasks
                                              CorrectionMask Struct_+
PaintCorrectionMaskMasksAlpha
PaintCorrectionMaskMasksAngle
PaintCorrectionMaskMasksBottom
                                             real/_
                                             real/_
                                             real/
PaintCorrectionMaskMasksCenterValue
                                             real/
PaintCorrectionMaskMasksCenterWeight
                                             real/
PaintCorrectionMaskMasksDabs
                                              string/ +
PaintCorrectionMaskMasksFeather
                                              real/
PaintCorrectionMaskMasksFlipped
                                             boolean/
PaintCorrectionMaskMasksFlow
                                             real/_
PaintCorrectionMaskMasksFullX
PaintCorrectionMaskMasksFullY
                                             real/
                                             real/_
PaintCorrectionMaskMasksInputDigest
                                             string/_
PaintCorrectionMaskMasksLeft
PaintCorrectionMaskMasksLeft
PaintCorrectionMaskMasksMaskActive
                                             real/_
                                             boolean/_
PaintCorrectionMaskMasksMaskBlendMode
                                             integer/_
PaintCorrectionMaskMasksMaskDigest
PaintCorrectionMaskMasksMaskInverted
                                            string/_
boolean/_
PaintCorrectionMaskMasksMaskName
                                             string/_
                                             string/_
PaintCorrectionMaskMasksMaskSubType
PaintCorrectionMaskMasksMaskSyncID
                                             string/_
real/_
PaintCorrectionMaskMasksValue
                                             string/_
real/_
PaintCorrectionMaskMasksMaskVersion
PaintCorrectionMaskMasksMidpoint
PaintCorrectionMaskMasksOrigin
                                             string/_
                                            real/_
PaintCorrectionMaskMasksPerimeterValue
                                             real/_
PaintCorrectionMaskMasksRadius
                                             string/_
PaintCorrectionMaskMasksReferencePoint
                                             real/_
PaintCorrectionMaskMasksRight
PaintCorrectionMaskMasksRoundness
                                             real/
PaintCorrectionMaskMasksSizeX
                                             real/_
PaintCorrectionMaskMasksSizeY
                                             real/
PaintCorrectionMaskMasksTop
                                             real/_
PaintCorrectionMaskMaskSubType
                                             string/
PaintCorrectionMaskMasksVersion
                                             integer/_
PaintCorrectionMaskMasksWhat
                                             string/_
PaintCorrectionMaskMasksWholeImageArea
                                             string/_
PaintCorrectionMaskMasksX
                                              real/_
PaintCorrectionMaskMasksY
                                              real/_
PaintCorrectionMaskMaskSyncID
                                             string/_
                                             real/_
PaintCorrectionMaskMasksZeroX
                                              real/_
PaintCorrectionMaskMasksZeroY
                                              real/_
PaintCorrectionMaskValue
PaintCorrectionMaskMaskVersion
                                               string/_
PaintCorrectionMaskMidpoint
                                               real/_
```

```
PaintCorrectionMaskOrigin
                                             string/_
PaintCorrectionMaskPerimeterValue
                                             real/_
PaintCorrectionMaskRadius
                                             real/
                                             string/_
PaintCorrectionMaskReferencePoint
PaintCorrectionMaskRight
                                             real/
PaintCorrectionMaskRoundness
                                            real/_
PaintCorrectionMaskSizeX
                                            real/_
PaintCorrectionMaskSizeY
                                            real/_
PaintCorrectionMaskTop
                                            real/_
PaintCorrectionMaskVersion
                                            integer/_
PaintCorrectionMaskWhat
                                            string/_
PaintCorrectionMaskWholeImageArea
                                            string/_
PaintCorrectionMaskX
                                             real/_
PaintCorrectionMaskY
                                             real/_
PaintCorrectionMaskZeroX
                                             real/_
                                             real/_
PaintCorrectionMaskZeroY
PaintCorrectionCorrectionName
                                             string/_+
PaintCorrectionRangeMask
                                             CorrRangeMask Struct +
PaintCorrectionRangeMaskAreaModels AreaModels Struct_+
PaintCorrectionRangeMaskAreaModelsComponents string/_+
PaintCorrectionRangeMaskAreaModelsColorSampleInfo string/ +
PaintCorrectionRangeMaskColorAmount
                                             real/_+
                                             real/_+
PaintCorrectionRangeMaskDepthFeather
                                             real/ +
PaintCorrectionRangeMaskDepthMax
PaintCorrectionRangeMaskDepthMin
                                             real/_+
PaintCorrectionRangeMaskInvert
                                             boolean/ +
PaintCorrectionRangeMaskLumFeather
                                             real/ +
PaintCorrectionRangeMaskLuminanceDepthSampleInfo string/_+
PaintCorrectionRangeMaskLumMax
                                            real/ +
PaintCorrectionRangeMaskLumMin
                                            real/ +
PaintCorrectionRangeMaskLumRange
                                            string/ +
PaintCorrectionRangeMaskSampleType
                                            integer/ +
PaintCorrectionRangeMaskType
                                            string/ +
PaintCorrectionRangeMaskVersion
                                            string/_+
PaintCorrectionCorrectionSyncID
                                            string/ +
PaintCorrectionBlacks2012
                                            real/_
PaintCorrectionBrightness
                                            real/_
                                             real/_
PaintCorrectionClarity
PaintCorrectionClarity2012
                                             real/_
PaintCorrectionContrast
                                             real/_
                                             real/_
PaintCorrectionContrast2012
PaintCorrectionDefringe
                                             real/_
                                             real/_
PaintCorrectionDehaze
PaintCorrectionExposure
                                             real/_
PaintCorrectionExposure2012
                                             real/_
                                             real/_
PaintCorrectionHighlights2012
PaintCorrectionHue
                                             real/
PaintCorrectionLuminanceNoise
                                             real/_
PaintCorrectionMoire
                                             real/_
PaintCorrectionSaturation
                                             real/
PaintCorrectionShadows2012
                                             real/
                                             real/_
PaintCorrectionSharpness
                                             real/
PaintCorrectionTemperature
                                             real/
PaintCorrectionTexture
PaintCorrectionTint
                                             real/
PaintCorrectionToningHue
                                             real/
PaintCorrectionToningSaturation
                                             real/
PaintCorrectionWhites2012
                                            real/_
PaintCorrectionWhat
                                             string/
ParametricDarks
                                             integer/
ParametricHighlights
                                             integer/
ParametricHighlightSplit
                                             integer/
ParametricLights
                                             integer/
ParametricMidtoneSplit
                                             integer/
ParametricShadows
                                             integer/
ParametricShadowSplit
                                             integer/
PerspectiveAspect
                                             integer/
PerspectiveHorizontal
                                             integer/
PerspectiveRotate
                                             real/
PerspectiveScale
                                              integer/
```

```
PerspectiveUpright
                                              integer/
PerspectiveVertical
                                              integer/
PerspectiveX
                                              real/
PerspectiveY
                                              real/
PostCropVignetteAmount
                                              integer/
PostCropVignetteFeather
                                              integer/
PostCropVignetteHighlightContrast
                                             integer/
PostCropVignetteMidpoint
                                             integer/
PostCropVignetteRoundness
                                              integer/
PostCropVignetteStyle
                                              integer/
PresetType
                                              string/
ProcessVersion
                                              string/
RangeMask
                                              RangeMask Struct
RangeMaskMapInfo
                                              MapInfo Struct_
RangeMaskMapInfoLabMax
                                              string/_
RangeMaskMapInfoLabMin
                                              string/_
RangeMaskMapInfoLumEq
                                              string/_+
                                              string/_
RangeMaskMapInfoRGBMax
                                              string/_
RangeMaskMapInfoRGBMin
RawFileName
                                              string/
RedEyeInfo
                                              string/+
RedHue
                                              integer/
RedSaturation
                                              integer/
RetouchAreas
                                              RetouchArea Struct+
RetouchAreaFeather
                                              real/_
RetouchAreaMasks
                                              CorrectionMask Struct +
                                              real/_
RetouchAreaMaskAlpha
RetouchAreaMaskAngle
                                              real/
RetouchAreaMaskBottom
                                              real/
RetouchAreaMaskCenterValue
                                              real/
RetouchAreaMaskCenterWeight
                                             real/
RetouchAreaMaskRange
                                              CorrRangeMask Struct +
RetouchAreaMaskRangeAreaModels
                                             AreaModels Struct +
                                           string/_+
RetouchAreaMaskRangeAreaModelsComponents
RetouchAreaMaskRangeAreaModelsColorSampleInfo string/ +
RetouchAreaMaskRangeColorAmount
                                             real/_+
RetouchAreaMaskRangeDepthFeather
                                              real/_+
                                              real/_+
RetouchAreaMaskRangeDepthMax
                                              real/_+
RetouchAreaMaskRangeDepthMin
RetouchAreaMaskRangeInvert
                                              boolean/_+
RetouchAreaMaskRangeLumFeather
                                              real/ +
RetouchAreaMaskRangeLuminanceDepthSampleInfo string/_+
RetouchAreaMaskRangeLumMax
                                              real/_+
RetouchAreaMaskRangeLumMin
                                              real/ +
RetouchAreaMaskRangeLumRange
                                              string/ +
RetouchAreaMaskRangeSampleType
                                              integer/_+
RetouchAreaMaskRangeType
                                              string/_+
RetouchAreaMaskRangeVersion
                                              string/_+
RetouchAreaMaskDabs
                                              string/_
RetouchAreaMaskFeather
                                              real/_
RetouchAreaMaskFlipped
                                              boolean/_
RetouchAreaMaskFlow
                                              real/_
RetouchAreaMaskFullX
                                              real/
                                             real/_
RetouchAreaMaskFullY
                                             string/_
RetouchAreaMaskInputDigest
RetouchAreaMaskLeft
                                              real/
RetouchAreaMaskMaskActive
                                              boolean/
RetouchAreaMaskMaskBlendMode
                                              integer/_
                                              string/_
RetouchAreaMaskMaskDigest
RetouchAreaMaskMaskInverted
                                              boolean/_
RetouchAreaMaskMaskName
                                              string/_
RetouchAreaMaskMasks
                                              CorrectionMask Struct_+
RetouchAreaMaskMasksAlpha
                                              real/_
RetouchAreaMaskMasksAngle
                                              real/_
RetouchAreaMaskMasksBottom
                                              real/_
                                              real/_
RetouchAreaMaskMasksCenterValue
                                              real/_
RetouchAreaMaskMasksCenterWeight
RetouchAreaMaskMasksDabs
                                              string/ +
RetouchAreaMaskMasksFeather
                                              real/_
RetouchAreaMaskMasksFlipped
                                              boolean/_
```

RetouchAreaMaskMasksFlow real/\_ RetouchAreaMaskMasksFullX real/\_ RetouchAreaMaskMasksFullY real/\_ string/\_ RetouchAreaMaskMasksInputDigest RetouchAreaMaskMasksLeft real/ RetouchAreaMaskMasksMaskActive boolean/\_ RetouchAreaMaskMasksMaskBlendMode integer/\_ RetouchAreaMaskMasksMaskDigest string/ RetouchAreaMaskMasksMaskInverted boolean/\_ RetouchAreaMaskMasksMaskName string/\_ RetouchAreaMaskMaskSubType string/\_ RetouchAreaMaskMasksMaskSyncID string/\_ RetouchAreaMaskMasksValue real/\_ RetouchAreaMaskMasksMaskVersion string/\_ RetouchAreaMaskMasksMidpoint real/\_ RetouchAreaMaskMasksOrigin string/\_ RetouchAreaMaskMasksPerimeterValue real/\_ RetouchAreaMaskMasksRadius real/\_ RetouchAreaMaskMasksReferencePoint string/\_ RetouchAreaMaskMasksRight real/\_ RetouchAreaMaskMasksRoundness real/\_ real/\_ RetouchAreaMaskMasksSizeX RetouchAreaMaskMasksSizeY real/ RetouchAreaMaskMasksTop real/ RetouchAreaMaskMaskSubType string/ RetouchAreaMaskMasksVersion integer/ RetouchAreaMaskMasksWhat string/ string/\_ RetouchAreaMaskMasksWholeImageArea real/\_ RetouchAreaMaskMasksX RetouchAreaMaskMasksY real/ RetouchAreaMaskMaskSyncID string/ RetouchAreaMaskMasksZeroX real/\_ RetouchAreaMaskMasksZeroY real/ RetouchAreaMaskValue real/ RetouchAreaMaskMaskVersion string/ RetouchAreaMaskMidpoint real/ string/ RetouchAreaMaskOrigin RetouchAreaMaskPerimeterValue real/\_ RetouchAreaMaskRadius real/ RetouchAreaMaskReferencePoint string/\_ real/\_ RetouchAreaMaskRight real/\_ RetouchAreaMaskRoundness real/\_ RetouchAreaMaskSizeX real/\_ RetouchAreaMaskSizeY RetouchAreaMaskTop real/ integer/\_ RetouchAreaMaskVersion string/\_ RetouchAreaMaskWhat string/\_ RetouchAreaMaskWholeImageArea RetouchAreaMaskX real/\_ RetouchAreaMaskY real/ real/\_ RetouchAreaMaskZeroX RetouchAreaMaskZeroY real/ string/\_ RetouchAreaMethod real/\_ RetouchAreaOffsetY RetouchAreaOpacity real/ integer/\_ RetouchAreaSeed RetouchAreaSourceState string/ RetouchAreaSourceX RetouchAreaSpotType string/ RetouchInfo string/+ Saturation integer/ SaturationAdjustmentAqua integer/ SaturationAdjustmentBlue integer/ SaturationAdjustmentGreen integer/ SaturationAdjustmentMagenta integer/ SaturationAdjustmentOrange integer/ SaturationAdjustmentPurple integer/ SaturationAdjustmentRed integer/ SaturationAdjustmentYellow integer/ SDRBlend real/

EXILITOOL 13.24 Tag Names	_
SDRBrightness	real/
SDRContrast	real/
SDRHighlights	real/
SDRShadows	real/
SDRWhites	real/
Shadows	integer/
Shadows2012	integer/
ShadowTint	integer/
SharpenDetail	integer/
SharpenEdgeMasking SharpenRadius	integer/ real/
Sharpness	integer/
ShortName	lang-alt/
Smoothness	integer/
SortName	lang-alt/
SplitToningBalance	integer/
SplitToningHighlightHue	integer/
SplitToningHighlightSaturation	integer/
SplitToningShadowHue	integer/
SplitToningShadowSaturation	integer/
SupportsAmount	boolean/
SupportsColor	boolean/
SupportsHighDynamicRange	boolean/
SupportsMonochrome	boolean/
SupportsNormalDynamicRange	boolean/
SupportsOutputReferred	boolean/
SupportsSceneReferred	boolean/
ColorTemperature	integer/
Texture	integer/
TIFFHandling	string/
Tint TaggleStyleAmount	integer/ integer/
ToggleStyleAmount ToggleStyleDigest	string/
ToneCurve	string/+
ToneCurveBlue	string/+
ToneCurveGreen	string/+
ToneCurveName	string/
ToneCurveName2012	string/
ToneCurvePV2012	string/+
ToneCurvePV2012Blue	string/+
ToneCurvePV2012Green	string/+
ToneCurvePV2012Red	string/+
ToneCurveRed	string/+
ToneMapStrength	real/
UprightCenterMode	integer/
UprightCenterNormX	real/
UprightCenterNormY	real/
UprightDependentDigest	string/
UprightFocalLength35mm	real/
UprightFocalMode	integer/
UprightFourSegments_0	string/
UprightFourSegments_1	string/
UprightFourSegments_2 UprightFourSegments_3	string/ string/
UprightFourSegmentsCount	integer/
UprightGuidedDependentDigest	string/
UprightPreview	boolean/
UprightTransform_0	string/
UprightTransform_1	string/
UprightTransform_2	string/
UprightTransform_3	string/
UprightTransform_4	string/
UprightTransform_5	string/
UprightTransformCount	integer/
UprightVersion	integer/
UUID	string/
Version	string/
Vibrance	integer/
VignetteAmount	integer/
VignetteMidpoint	integer/

What string/ WhiteBalance string/ Whites2012 integer/

### XMP Correction Struct

Field Name Writable CorrectionActive boolean CorrectionAmount real

CorrectionMasks CorrectionMask Struct+

string

real

CorrectionName string

CorrRangeMask CorrRangeMask Struct

CorrectionSyncID LocalBlacks2012 LocalBrightness LocalClarity LocalClarity2012 LocalContrast LocalContrast2012 LocalDefringe LocalDehaze LocalExposure

real real real real real real real LocalExposure2012 real LocalHighlights2012 real LocalHue real LocalLuminanceNoise real LocalMoire real LocalSaturation real LocalShadows2012 real LocalSharpness real LocalTemperature real LocalTexture real LocalTint real LocalToningHue real LocalToningSaturation real LocalWhites2012 real What string

# XMP CorrectionMask Struct

MaskVersion

Field Name Writable \_\_\_\_\_\_ \_\_\_\_\_ Alpha real Angle real Bottom real CenterValue real CenterWeight real

CorrRangeMask CorrRangeMask Struct

string

Dabs string+ Feather real Flipped boolean Flow real FullX real FullY real InputDigest string Left real MaskActive boolean MaskBlendMode integer MaskDigest string MaskInverted boolean MaskName string MaskSubType string MaskSyncID string MaskValue real

Masks CorrectionMask Struct

Midpoint real Origin string PerimeterValue real Radius real ReferencePoint string Right real Roundness real SizeX real SizeY real Top real Version integer What string WholeImageArea string Χ real Y real ZeroX real ZeroY real

### XMP CorrRangeMask Struct

Called CorrectionRangeMask by the spec.

Field Name Writable AreaModels Struct+ AreaModels ColorAmount real DepthFeather real DepthMax real DepthMin real Invert boolean LumFeather real LumMax real LumMin real LumRange string LuminanceDepthSampleInfo string SampleType integer Type string Version string

#### XMP AreaModels Struct

Field Name Writable
-----AreaComponents string+
ColorRangeMaskAreaSampleInfo string

# XMP DepthBasedCorr Struct

Field Name Writable
----CorrectionActive boolean
CorrectionAmount real

CorrectionMasks CorrectionMask Struct+

CorrectionSyncIDstringLocalCorrectedDepthrealLocalCurveRefineSaturationrealWhatstring

# XMP DepthMapInfo Struct

Writable Field Name BaseHighlightGuideInputDigest string BaseHighlightGuideTable string BaseHighlightGuideVersion string BaseLayeredDepthInputDigest string BaseLayeredDepthTable string BaseLayeredDepthVersion string BaseRawDepthInputDigest string BaseRawDepthTable string BaseRawDepthVersion string

DepthSource string

### XMP LensBlur Struct

Field Name Writable Active boolean BlurAmount real BokehAspect real BokehRotation real BokehShape real BokehShapeDetail real CatEyeAmount real CatEyeScale real FocalRange string FocalRangeSource real HighlightsBoost real HighlightsThreshold real SampledArea string SampledRange string SphericalAberration real SubjectRange string Version string

# XMP Look Struct

Field Name Writable Amount string Cluster string Copyright string Group lang-alt Name string Parameters LookParms Struct SupportsAmount string SupportsMonochrome string SupportsOutputReferred string UUID string

### XMP LookParms Struct

Field Name Writable \_\_\_\_\_ CameraProfile string Clarity2012 string ConvertToGrayscale string Highlights2012 string LookTable string ProcessVersion string Shadows2012 string ToneCurvePV2012 string+ ToneCurvePV2012Blue string+ ToneCurvePV2012Green string+ ToneCurvePV2012Red string+ Version string

#### XMP RangeMask Struct

This structure is actually called RangeMaskMapInfo, but it only contains one element which is a RangeMaskMapInfo structure (Yes, really!). So these are renamed to RangeMask and MapInfo respectively to avoid confusion and redundancy in the tag names.

Field Name Writable -----RangeMaskMapInfo MapInfo Struct

#### XMP MapInfo Struct

Called RangeMaskMapInfo by the specification, the same as the

containing structure.

Field Name Writable LabMax string LabMin string LumEq string+ RGBMax string RGBMin string

#### XMP RetouchArea Struct

Field Name Writable Feather real CorrectionMask Struct+ Masks

Method string OffsetY real Opacity real Seed integer SourceState string

SourceX real SpotType string

#### XMP creatorAtom Tags

Adobe creatorAtom tags, written by After Effects.

These tags belong to the ExifTool XMP-creatorAtom family 1 group.

Tag Name Writable \_\_\_\_\_ \_\_\_\_\_ AeProjectLink AEProjectLink Struct AeProjectLinkCompositionID AeProjectLinkFullPath string AeProjectLinkRenderOutputModuleIndex string AeProjectLinkRenderQueueItemID string\_ AeProjectLinkRenderTimeStamp integer MacAtom Struct MacAtom MacAtomApplicationCode string\_ MacAtomInvocationAppleEvent string string\_ MacAtomPosixProjectPath WindowsAtom WindowsAtom Struct WindowsAtomExtension string WindowsAtomInvocationFlags string WindowsAtomUncProjectPath string\_

# XMP AEProjectLink Struct

Field Name Writable CompositionID string FullPath string RenderOutputModuleIndex string RenderOueueItemID string RenderTimeStamp integer

# XMP MacAtom Struct

Field Name Writable ApplicationCode string string InvocationAppleEvent PosixProjectPath string

### XMP WindowsAtom Struct

Field Name Writable Extension string

InvocationFlags string UncProjectPath string

# XMP crs Tags

Photoshop Camera Raw namespace tags. It is a shame that Adobe pollutes the metadata space with these incredibly bulky image editing parameters.

These tags belong to the ExifTool XMP-crs family 1 group.

Tag Name	Writable
AlreadyApplied	boolean
AutoBrightness	boolean
AutoContrast	boolean
AutoExposure	boolean
AutoLateralCA	integer
AutoShadows	boolean
AutoTone	boolean
AutoToneDigest	string
AutoToneDigestNoSat	string
AutoWhiteVersion	integer
Blacks2012	integer
BlueHue	integer
BlueSaturation	integer
Brightness	integer
CameraModelRestriction	string
CameraProfile	string
CameraProfileDigest	string
ChromaticAberrationB	integer
ChromaticAberrationR	integer
CircularGradientBasedCorrections	Correction Struct+
CircGradBasedCorrActive	boolean_
CircGradBasedCorrAmount	real_
CircGradBasedCorrMasks	CorrectionMask Struct_+
CircGradBasedCorrMaskAlpha	real_
CircGradBasedCorrMaskAngle	real_
CircGradBasedCorrMaskBottom	real_
CircGradBasedCorrMaskCenterValue	real_
CircGradBasedCorrMaskCenterWeight	real_
CircGradBasedCorrMaskRange	CorrRangeMask Struct_+
CircGradBasedCorrMaskRangeAreaModels	AreaModels Struct_+
CircGradBasedCorrMaskRangeAreaModelsComponent	
CircGradBasedCorrMaskRangeAreaModelsColorSamp	
CircGradBasedCorrMaskRangeColorAmount CircGradBasedCorrMaskRangeDepthFeather	real_+
	real_+
CircGradBasedCorrMaskRangeDepthMax	real_+
CircGradBasedCorrMaskRangeDepthMin CircGradBasedCorrMaskRangeInvert	real_+ boolean +
CircGradBasedCorrMaskRangeLumFeather	real_+
CircGradBasedCorrMaskRangeLuminanceDepthSampl	
CircGradBasedCorrMaskRangeLumMax	real_+
CircGradBasedCorrMaskRangeLumMin	real_+
CircGradBasedCorrMaskRangeLumRange	string_+
CircGradBasedCorrMaskRangeSampleType	integer_+
CircGradBasedCorrMaskRangeType	string_+
CircGradBasedCorrMaskRangeVersion	string_+
CircGradBasedCorrMaskDabs	string_
CircGradBasedCorrMaskFeather	real_
CircGradBasedCorrMaskFlipped	boolean_
CircGradBasedCorrMaskFlow	real_
CircGradBasedCorrMaskFullX	real_
CircGradBasedCorrMaskFullY	real_
CircGradBasedCorrMaskInputDigest	string_
CircGradBasedCorrMaskLeft	real_
CircGradBasedCorrMaskMaskActive	boolean_
CircGradBasedCorrMaskMaskBlendMode	integer_
CircGradBasedCorrMaskMaskDigest	string_
CircGradBasedCorrMaskMaskInverted	boolean_

```
CircGradBasedCorrMaskMaskName
                                           string_
CircGradBasedCorrMaskMasks
                                           CorrectionMask Struct_+
CircGradBasedCorrMaskMasksAlpha
                                          real_
                                          real_
CircGradBasedCorrMaskMasksAngle
CircGradBasedCorrMaskMasksBottom
                                          real
CircGradBasedCorrMaskMasksCenterValue
                                          real_
CircGradBasedCorrMaskMasksCenterWeight
CircGradBasedCorrMaskMasksDabs
                                          string +
CircGradBasedCorrMaskMasksFeather
                                          real
CircGradBasedCorrMaskMasksFlipped
                                          boolean_
CircGradBasedCorrMaskMasksFlow
                                          real_
CircGradBasedCorrMaskMasksFullX
                                          real_
CircGradBasedCorrMaskMasksFullY
                                          real_
CircGradBasedCorrMaskMasksInputDigest
                                          string_
CircGradBasedCorrMaskMasksLeft
                                          real_
CircGradBasedCorrMaskMasksMaskActive
                                          boolean_
CircGradBasedCorrMaskMasksMaskBlendMode
                                          integer_
CircGradBasedCorrMaskMasksMaskDigest
                                           string
CircGradBasedCorrMaskMasksMaskInverted
                                          boolean_
CircGradBasedCorrMaskMasksMaskName
                                           string
                                          string
CircGradBasedCorrMaskMasksMaskSubType
CircGradBasedCorrMaskMasksMaskSyncID
CircGradBasedCorrMaskMasksValue
                                           real
CircGradBasedCorrMaskMasksMaskVersion
                                           string_
CircGradBasedCorrMaskMasksMidpoint
CircGradBasedCorrMaskMasksOrigin
                                          real_
                                           string_
                                          real_
CircGradBasedCorrMaskMasksPerimeterValue
CircGradBasedCorrMaskMasksRadius
                                          real_
                                          string_
CircGradBasedCorrMaskMasksReferencePoint
CircGradBasedCorrMaskMasksRight
                                          real
CircGradBasedCorrMaskMasksRoundness
                                          real
CircGradBasedCorrMaskMasksSizeX
                                          real
CircGradBasedCorrMaskMasksSizeY
                                          real
CircGradBasedCorrMaskMasksTop
                                          real
CircGradBasedCorrMaskMaskSubType
                                          string_
CircGradBasedCorrMaskMasksVersion
                                          integer
CircGradBasedCorrMaskMasksWhat
                                          string_
CircGradBasedCorrMaskMasksWholeImageArea
                                         string_
CircGradBasedCorrMaskMasksX
                                           real_
CircGradBasedCorrMaskMasksY
                                           real_
CircGradBasedCorrMaskMaskSyncID
                                           string
                                           real_
CircGradBasedCorrMaskMasksZeroX
CircGradBasedCorrMaskMasksZeroY
                                           real_
CircGradBasedCorrMaskValue
                                           real
CircGradBasedCorrMaskMaskVersion
                                           string
CircGradBasedCorrMaskMidpoint
CircGradBasedCorrMaskOrigin
                                           real
                                           string
CircGradBasedCorrMaskPerimeterValue
                                           real_
CircGradBasedCorrMaskRadius
                                           real
                                          string_
CircGradBasedCorrMaskReferencePoint
CircGradBasedCorrMaskRight
                                          real_
CircGradBasedCorrMaskRoundness
                                          real_
CircGradBasedCorrMaskSizeX
                                          real_
CircGradBasedCorrMaskSizeY
                                          real
CircGradBasedCorrMaskTop
                                          real_
CircGradBasedCorrMaskVersion
                                           integer
CircGradBasedCorrMaskWhat
                                          string
CircGradBasedCorrMaskWholeImageArea
CircGradBasedCorrMaskX
CircGradBasedCorrMaskY
                                           real_
CircGradBasedCorrMaskZeroX
                                           real_
CircGradBasedCorrMaskZeroY
                                          real_
CircGradBasedCorrCorrectionName
                                          string_+
CircGradBasedCorrRangeMask
                                          CorrRangeMask Struct_+
CircGradBasedCorrRangeMaskAreaModels
                                          AreaModels Struct_+
CircGradBasedCorrRangeMaskAreaModelsComponents string_+
CircGradBasedCorrRangeMaskAreaModelsColorSampleInfo string_+
CircGradBasedCorrRangeMaskColorAmount real_+
CircGradBasedCorrRangeMaskDepthFeather
                                           real +
CircGradBasedCorrRangeMaskDepthMax
                                           real_+
```

CircGradBasedCorrRangeMaskDepthMin real\_+ CircGradBasedCorrRangeMaskInvert boolean\_+ CircGradBasedCorrRangeMaskLumFeather real\_+ CircGradBasedCorrRangeMaskLuminanceDepthSampleInfo string\_+ CircGradBasedCorrRangeMaskLumMax real\_+ CircGradBasedCorrRangeMaskLumMin real\_+ CircGradBasedCorrRangeMaskLumRange string\_+ CircGradBasedCorrRangeMaskSampleType integer + CircGradBasedCorrRangeMaskType string\_+ CircGradBasedCorrRangeMaskVersion string\_+ CircGradBasedCorrCorrectionSyncID string\_+ CircGradBasedCorrBlacks2012 real\_ CircGradBasedCorrBrightness real\_ CircGradBasedCorrClarity real\_ CircGradBasedCorrClarity2012 real\_ CircGradBasedCorrContrast real\_ CircGradBasedCorrContrast2012 real CircGradBasedCorrDefringe real\_ CircGradBasedCorrDehaze real\_ CircGradBasedCorrExposure real CircGradBasedCorrExposure2012 real CircGradBasedCorrHighlights2012 real\_ CircGradBasedCorrHue real CircGradBasedCorrLuminanceNoise real CircGradBasedCorrMoire real CircGradBasedCorrSaturation real\_ CircGradBasedCorrShadows2012 real CircGradBasedCorrSharpness real\_ CircGradBasedCorrTemperature real CircGradBasedCorrTexture real CircGradBasedCorrTint real CircGradBasedCorrToningHue real\_ CircGradBasedCorrToningSaturation real\_ CircGradBasedCorrWhites2012 real CircGradBasedCorrWhat string Clarity integer Clarity2012 integer ClipboardAspectRatio integer ClipboardOrientation integer Cluster string ColorGradeBlending integer ColorGradeGlobalHue integer ColorGradeGlobalLum integer ColorGradeGlobalSat integer ColorGradeHighlightLum integer ColorGradeMidtoneHue integer ColorGradeMidtoneLum integer ColorGradeMidtoneSat integer ColorGradeShadowLum integer ColorNoiseReduction integer ColorNoiseReductionDetail integer ColorNoiseReductionSmoothness integer CompatibleVersion string ContactInfo string Contrast integer/ Contrast2012 integer Converter string ConvertToGrayscale boolean Copyright string/ CropAngle real real CropBottom CropConstrainToWarp integer CropHeight real CropLeft real CropRight real CropTop real CropUnit integer CropUnits integer CropWidth real DefaultAutoGray boolean

```
DefaultAutoTone
                                             boolean
DefaultsSpecificToISO
                                             boolean
DefaultsSpecificToSerial
                                             boolean
Defringe
                                             integer
DefringeGreenAmount
                                             integer
DefringeGreenHueHi
                                             integer
DefringeGreenHueLo
                                             integer
DefringePurpleAmount
                                             integer
DefringePurpleHueHi
                                             integer
DefringePurpleHueLo
                                             integer
Dehaze
                                             real
DepthBasedCorrections
                                             DepthBasedCorr Struct+
DepthBasedCorrCorrectionActive
                                            boolean_+
DepthBasedCorrCorrectionAmount
                                            real_+
{\tt DepthBasedCorrMask}
                                             CorrectionMask Struct_+
DepthBasedCorrMaskAlpha
                                             real_
DepthBasedCorrMaskAngle
                                             real_
DepthBasedCorrMaskBottom
                                             real_
DepthBasedCorrMaskCenterValue
                                             real_
DepthBasedCorrMaskCenterWeight
                                             real
DepthBasedCorrMaskRange
                                             CorrRangeMask Struct +
DepthBasedCorrMaskRangeAreaModels
                                             AreaModels Struct_+
DepthBasedCorrMaskRangeAreaModelsComponents string +
DepthBasedCorrMaskRangeAreaModelsColorSampleInfo string +
DepthBasedCorrMaskRangeColorAmount
                                            real +
DepthBasedCorrMaskRangeDepthFeather
                                             real +
DepthBasedCorrMaskRangeDepthMax
                                             real +
DepthBasedCorrMaskRangeDepthMin
                                             real +
DepthBasedCorrMaskRangeInvert
                                            boolean_+
DepthBasedCorrMaskRangeLumFeather
                                             real +
DepthBasedCorrMaskRangeLuminanceDepthSampleInfo string_+
DepthBasedCorrMaskRangeLumMax
                                            real +
DepthBasedCorrMaskRangeLumMin
                                            real +
DepthBasedCorrMaskRangeLumRange
                                            string +
DepthBasedCorrMaskRangeSampleType
                                            integer +
DepthBasedCorrMaskRangeType
                                            string +
DepthBasedCorrMaskRangeVersion
                                            string_+
DepthBasedCorrMaskDabs
                                            string +
DepthBasedCorrMaskFeather
                                             real
DepthBasedCorrMaskFlipped
                                             boolean_
                                             real_
DepthBasedCorrMaskFlow
                                             real_
DepthBasedCorrMaskFullX
DepthBasedCorrMaskFullY
                                             real
DepthBasedCorrMaskInputDigest
                                             string
DepthBasedCorrMaskLeft
                                             real
DepthBasedCorrMaskMaskActive
                                             boolean
                                            integer_
DepthBasedCorrMaskMaskBlendMode
DepthBasedCorrMaskMaskDigest
                                             string
                                            boolean_
DepthBasedCorrMaskMaskInverted
DepthBasedCorrMaskMaskName
                                             string
DepthBasedCorrMaskMasks
                                            CorrectionMask Struct_+
DepthBasedCorrMaskMasksAlpha
                                            real_
DepthBasedCorrMaskMasksAngle
                                            real_
                                            real
DepthBasedCorrMaskMasksBottom
DepthBasedCorrMaskMasksCenterValue
                                            real
DepthBasedCorrMaskMasksCenterWeight
                                            real
DepthBasedCorrMaskMasksDabs
                                            string +
DepthBasedCorrMaskMasksFeather
                                             real_
DepthBasedCorrMaskMasksFlipped
                                            boolean
                                            real_
DepthBasedCorrMaskMasksFlow
DepthBasedCorrMaskMasksFullX
                                            real_
DepthBasedCorrMaskMasksFullY
                                            real_
DepthBasedCorrMaskMasksInputDigest
                                            string_
DepthBasedCorrMaskMasksLeft
                                            real_
DepthBasedCorrMaskMasksMaskActive
                                            boolean_
DepthBasedCorrMaskMasksMaskBlendMode
                                           integer_
DepthBasedCorrMaskMasksMaskDigest
                                             string
                                            boolean_
DepthBasedCorrMaskMasksMaskInverted
DepthBasedCorrMaskMasksMaskName
                                             string
DepthBasedCorrMaskMasksMaskSubType
                                             string_
```

```
DepthBasedCorrMaskMasksMaskSyncID
                                            string_
DepthBasedCorrMaskMasksValue
                                           real_
DepthBasedCorrMaskMasksMaskVersion
                                           string_
DepthBasedCorrMaskMasksMidpoint
                                           real
DepthBasedCorrMaskMasksOrigin
                                           string
DepthBasedCorrMaskMasksPerimeterValue
                                           real_
DepthBasedCorrMaskMasksRadius
                                           real_
DepthBasedCorrMaskMasksReferencePoint
                                           string_
DepthBasedCorrMaskMasksRight
                                           real_
DepthBasedCorrMaskMasksRoundness
                                           real_
DepthBasedCorrMaskMasksSizeX
                                           real_
DepthBasedCorrMaskMasksSizeY
                                           real_
DepthBasedCorrMaskMasksTop
                                           real_
DepthBasedCorrMaskMaskSubType
                                           string_
DepthBasedCorrMaskMasksVersion
                                            integer_
DepthBasedCorrMaskMasksWhat
                                           string_
DepthBasedCorrMaskMasksWholeImageArea
                                            string
DepthBasedCorrMaskMasksX
                                            real_
DepthBasedCorrMaskMasksY
                                            real_
DepthBasedCorrMaskMaskSyncID
                                            string_
DepthBasedCorrMaskMasksZeroX
                                            real
DepthBasedCorrMaskMasksZeroY
                                            real_
DepthBasedCorrMaskValue
                                            real
DepthBasedCorrMaskMaskVersion
                                            string
DepthBasedCorrMaskMidpoint
                                            real_
DepthBasedCorrMaskOrigin
                                            string
DepthBasedCorrMaskPerimeterValue
                                            real
DepthBasedCorrMaskRadius
                                            real
DepthBasedCorrMaskReferencePoint
                                            string
                                            real_
DepthBasedCorrMaskRight
DepthBasedCorrMaskRoundness
                                            real_
DepthBasedCorrMaskSizeX
                                            real
DepthBasedCorrMaskSizeY
                                           real_
DepthBasedCorrMaskTop
                                           real
DepthBasedCorrMaskVersion
                                            integer
DepthBasedCorrMaskWhat
                                            string
DepthBasedCorrMaskWholeImageArea
                                            string_
DepthBasedCorrMaskX
                                            real_
DepthBasedCorrMaskY
                                            real_
                                            real_
DepthBasedCorrMaskZeroX
DepthBasedCorrMaskZeroY
                                            real
DepthBasedCorrCorrectionSyncID
                                            string_+
DepthBasedCorrLocalCorrectedDepth
                                            real +
DepthBasedCorrLocalCurveRefineSaturation
                                            real +
DepthBasedCorrWhat
                                             string +
DepthMapInfo
                                             DepthMapInfo Struct
DepthMapInfoBaseHighlightGuideInputDigest
                                            string
DepthMapInfoBaseHighlightGuideTable
                                            string
DepthMapInfoBaseHighlightGuideVersion
                                            string_
                                           string_
DepthMapInfoBaseLayeredDepthInputDigest
DepthMapInfoBaseLayeredDepthTable
                                            string
DepthMapInfoBaseLayeredDepthVersion
                                            string
DepthMapInfoBaseRawDepthInputDigest
                                            string
DepthMapInfoBaseRawDepthTable
                                            string
DepthMapInfoBaseRawDepthVersion
                                            string
DepthMapInfoDepthSource
                                            string
Description
                                            lang-alt/
DNGIgnoreSidecars
                                            boolean
Exposure
                                            real
Exposure2012
                                            real
FillLight
                                            integer
GradientBasedCorrections
                                            Correction Struct+
GradientBasedCorrActive
                                            boolean_
GradientBasedCorrAmount
                                            real_
GradientBasedCorrMasks
                                            CorrectionMask Struct_+
                                            real_
GradientBasedCorrMaskAlpha
                                            real_
GradientBasedCorrMaskAngle
                                            real_
GradientBasedCorrMaskBottom
GradientBasedCorrMaskCenterValue
                                            real
GradientBasedCorrMaskCenterWeight
                                            real_
```

```
GradientBasedCorrMaskRange
                                            CorrRangeMask Struct_+
GradientBasedCorrMaskRangeAreaModels
                                           AreaModels Struct_+
GradientBasedCorrMaskRangeAreaModelsComponents string_+
GradientBasedCorrMaskRangeAreaModelsColorSampleInfo string_+
GradientBasedCorrMaskRangeColorAmount real_+
GradientBasedCorrMaskRangeDepthFeather
                                           real_+
GradientBasedCorrMaskRangeDepthMax
                                           real_+
GradientBasedCorrMaskRangeDepthMin
                                           real +
GradientBasedCorrMaskRangeInvert
                                           boolean_+
GradientBasedCorrMaskRangeLumFeather
                                           real_+
GradientBasedCorrMaskRangeLuminanceDepthSampleInfo string_+
GradientBasedCorrMaskRangeLumMax real_+
GradientBasedCorrMaskRangeLumMin
                                           real_+
GradientBasedCorrMaskRangeLumRange
                                           string_+
GradientBasedCorrMaskRangeSampleType
                                           integer_+
GradientBasedCorrMaskRangeType
                                           string_+
GradientBasedCorrMaskRangeVersion
                                           string +
GradientBasedCorrMaskDabs
                                           string
GradientBasedCorrMaskFeather
                                            real_
GradientBasedCorrMaskFlipped
                                            boolean
GradientBasedCorrMaskFlow
                                            real
GradientBasedCorrMaskFullX
                                            real_
GradientBasedCorrMaskFullY
                                            real
GradientBasedCorrMaskInputDigest
                                            string
GradientBasedCorrMaskLeft
                                            real
GradientBasedCorrMaskMaskActive
                                            boolean
GradientBasedCorrMaskMaskBlendMode
                                            integer_
GradientBasedCorrMaskMaskDigest
                                            string
GradientBasedCorrMaskMaskInverted
                                           boolean
GradientBasedCorrMaskMaskName
                                           string
GradientBasedCorrMaskMasks
                                           CorrectionMask Struct +
GradientBasedCorrMaskMasksAlpha
                                           real_
GradientBasedCorrMaskMasksAngle
GradientBasedCorrMaskMasksBottom
GradientBasedCorrMaskMasksBottom
                                           real
                                           real_
GradientBasedCorrMaskMasksCenterValue
                                           real_
GradientBasedCorrMaskMasksCenterWeight
                                           real
GradientBasedCorrMaskMasksDabs
                                           string_+
GradientBasedCorrMaskMasksFeather
                                           real_
GradientBasedCorrMaskMasksFlipped
                                           boolean_
GradientBasedCorrMaskMasksFlow
                                           real_
GradientBasedCorrMaskMasksFullX
GradientBasedCorrMaskMasksFullY
                                           real_
                                           real
GradientBasedCorrMaskMasksInputDigest
                                           string_
GradientBasedCorrMaskMasksLeft
                                            real
GradientBasedCorrMaskMasksMaskActive
                                          boolean_
integer_
GradientBasedCorrMaskMasksMaskBlendMode
GradientBasedCorrMaskMasksMaskDigest
                                            string
GradientBasedCorrMaskMasksMaskInverted
                                         boolean_
                                            string_
GradientBasedCorrMaskMasksMaskName
                                           string_
string_
GradientBasedCorrMaskMasksMaskSubType
GradientBasedCorrMaskMasksMaskSyncID
GradientBasedCorrMaskMasksValue
                                           real_
GradientBasedCorrMaskMasksMaskVersion
                                           string
GradientBasedCorrMaskMasksMidpoint
GradientBasedCorrMaskMasksOrigin
                                           real_
                                           string
GradientBasedCorrMaskMasksPerimeterValue real_
GradientBasedCorrMaskMasksRadius
                                           real
GradientBasedCorrMaskMasksReferencePoint string_
GradientBasedCorrMaskMasksRight
GradientBasedCorrMaskMasksRoundness
                                           real_
GradientBasedCorrMaskMasksSizeX
                                           real_
GradientBasedCorrMaskMasksSizeY
                                           real_
GradientBasedCorrMaskMasksTop
                                           real_
GradientBasedCorrMaskMaskSubType
                                           string_
GradientBasedCorrMaskMasksVersion
                                           integer_
GradientBasedCorrMaskMasksWhat
                                           string_
                                           string_
GradientBasedCorrMaskMasksWholeImageArea
GradientBasedCorrMaskMasksX
                                            real_
GradientBasedCorrMaskMasksY
                                            real
GradientBasedCorrMaskMaskSyncID
                                             string_
```

```
GradientBasedCorrMaskMasksZeroX
                                           real
GradientBasedCorrMaskMasksZeroY
                                           real_
GradientBasedCorrMaskValue
                                          real
GradientBasedCorrMaskMaskVersion
                                          string_
GradientBasedCorrMaskMidpoint
                                          real
GradientBasedCorrMaskOrigin
                                          string_
GradientBasedCorrMaskPerimeterValue
GradientBasedCorrMaskRadius
GradientBasedCorrMaskReferencePoint
GradientBasedCorrMaskRight
GradientBasedCorrMaskRoundness
                                          real_
GradientBasedCorrMaskSizeX
                                          real_
GradientBasedCorrMaskSizeY
                                          real_
GradientBasedCorrMaskTop
                                          real_
GradientBasedCorrMaskVersion
                                          integer_
GradientBasedCorrMaskWhat
                                          string_
GradientBasedCorrMaskWholeImageArea
                                           string
GradientBasedCorrMaskX
                                           real
GradientBasedCorrMaskY
                                           real_
GradientBasedCorrMaskZeroX
                                           real
GradientBasedCorrMaskZeroY
                                           real
GradientBasedCorrCorrectionName
                                           string_+
GradientBasedCorrRangeMask
                                           CorrRangeMask Struct +
GradientBasedCorrRangeMaskAreaModels
                                          AreaModels Struct_+
GradientBasedCorrRangeMaskAreaModelsComponents string_+
GradientBasedCorrRangeMaskAreaModelsColorSampleInfo string_+
GradientBasedCorrRangeMaskColorAmount real_+
GradientBasedCorrRangeMaskDepthFeather
                                          real_+
GradientBasedCorrRangeMaskDepthMax
                                          real +
GradientBasedCorrRangeMaskDepthMin
                                          real +
GradientBasedCorrRangeMaskInvert
                                          boolean +
GradientBasedCorrRangeMaskLumFeather
                                          real +
GradientBasedCorrRangeMaskLuminanceDepthSampleInfo string +
GradientBasedCorrRangeMaskLumMax real_+
GradientBasedCorrRangeMaskLumMin
                                          real +
GradientBasedCorrRangeMaskLumRange
                                          string_+
GradientBasedCorrRangeMaskSampleType
                                          integer_+
GradientBasedCorrRangeMaskType
                                          string +
GradientBasedCorrRangeMaskVersion
                                          string_+
GradientBasedCorrCorrectionSyncID
                                          string_+
GradientBasedCorrBlacks2012
                                          real_
GradientBasedCorrBrightness
                                          real_
                                          real_
GradientBasedCorrClarity
GradientBasedCorrClarity2012
                                          real
GradientBasedCorrContrast
                                          real
GradientBasedCorrContrast2012
GradientBasedCorrDefringe
                                           real
GradientBasedCorrDehaze
                                           real
GradientBasedCorrExposure
                                           real
GradientBasedCorrExposure2012
                                          real_
GradientBasedCorrHighlights2012
                                          real
GradientBasedCorrHue
                                          real_
GradientBasedCorrLuminanceNoise
                                          real
GradientBasedCorrMoire
                                          real
GradientBasedCorrSaturation
                                          real
GradientBasedCorrShadows2012
                                          real
GradientBasedCorrSharpness
                                          real
GradientBasedCorrTemperature
                                          real_
GradientBasedCorrTexture
GradientBasedCorrTint
                                          real_
GradientBasedCorrToningHue
                                          real_
GradientBasedCorrToningSaturation
                                          real_
GradientBasedCorrWhites2012
                                           real_
GradientBasedCorrWhat.
                                           string_
GrainAmount
                                           integer
GrainFrequency
                                           integer
GrainSeed
                                           integer
GrainSize
                                           integer
GrayMixerAqua
                                           integer
GrayMixerBlue
                                           integer
```

GrayMixerGreen integer GrayMixerMagenta integer GrayMixerOrange integer GrayMixerPurple integer GrayMixerRed integer GrayMixerYellow integer GreenHue integer GreenSaturation integer Group lang-alt/ HasCrop boolean boolean HasSettings HDREditMode integer Highlight2012 integer HighlightRecovery integer Highlights2012 integer HueAdjustmentAqua integer HueAdjustmentBlue integer HueAdjustmentGreen integer HueAdjustmentMagenta integer HueAdjustmentOrange integer HueAdjustmentPurple integer HueAdjustmentRed integer HueAdjustmentYellow integer IncrementalTemperature integer IncrementalTint integer JPEGHandling string LensBlur LensBlur Struct LensBlurActive boolean\_ real\_ LensBlurAmount LensBlurBokehAspect real LensBlurBokehRotation real LensBlurBokehShape real LensBlurBokehShapeDetail real LensBlurCatEyeAmount real\_ LensBlurCatEyeScale real LensBlurFocalRange string LensBlurFocalRangeSource real\_ real\_ LensBlurHighlightsBoost LensBlurHighlightsThreshold real\_ LensBlurSampledArea string LensBlurSampledRange string LensBlurSphericalAberration real LensBlurSubjectRange string LensBlurVersion string LensManualDistortionAmount integer LensProfileChromaticAberrationScale integer LensProfileDigest string LensProfileDistortionScale integer LensProfileEnable integer LensProfileFilename string LensProfileIsEmbedded boolean LensProfileMatchKeyCameraModelName string LensProfileMatchKeyExifMake string LensProfileMatchKevExifModel string LensProfileMatchKeyIsRaw boolean LensProfileMatchKeyLensID string LensProfileMatchKeyLensInfo string LensProfileMatchKeyLensName string LensProfileMatchKeySensorFormatFactor real LensProfileName string LensProfileSetup string LensProfileVignettingScale integer Look Struct Look LookAmount string\_ LookCluster string\_ LookCopyright string lang-alt\_ LookGroup LookName string LookParameters LookParms Struct LookParametersCameraProfile string\_

```
LookParametersClarity2012
                                            string
LookParametersConvertToGrayscale
                                            strina
LookParametersHighlights2012
                                            string_
LookParametersLookTable
                                            string
LookParametersProcessVersion
                                           string
LookParametersShadows2012
                                           string_
LookParametersToneCurvePV2012
                                           string_+
LookParametersToneCurvePV2012Blue
                                           string +
LookParametersToneCurvePV2012Green
                                           string_+
LookParametersToneCurvePV2012Red
                                           string_+
LookParametersVersion
                                            string_
LookSupportsAmount
                                            string
LookSupportsMonochrome
                                            string_
LookSupportsOutputReferred
                                            string_
LookUUID
                                            string_
LuminanceAdjustmentAqua
                                            integer
LuminanceAdjustmentBlue
                                            integer
LuminanceAdjustmentGreen
                                            integer
LuminanceAdjustmentMagenta
                                            integer
LuminanceAdjustmentOrange
                                            integer
LuminanceAdjustmentPurple
                                            integer
LuminanceAdjustmentRed
                                            integer
LuminanceAdjustmentYellow
                                            integer
LuminanceNoiseReductionContrast
                                            integer
LuminanceNoiseReductionDetail
                                            integer
LuminanceSmoothing
                                            integer
MaskGroupBasedCorrections
                                            Correction Struct+
MaskGroupBasedCorrActive
                                           boolean_
MaskGroupBasedCorrAmount
                                           real
MaskGroupBasedCorrMask
                                           CorrectionMask Struct +
MaskGroupBasedCorrMaskAlpha
                                           real_
MaskGroupBasedCorrMaskAngle
                                           real_
MaskGroupBasedCorrMaskBottom
                                           real
MaskGroupBasedCorrMaskCenterValue
                                           real_
MaskGroupBasedCorrMaskCenterWeight
                                           real
MaskGroupBasedCorrMaskRange
                                           CorrRangeMask Struct +
MaskGroupBasedCorrMaskRangeAreaModels
                                           AreaModels Struct_+
MaskGroupBasedCorrMaskRangeAreaModelsComponents string_+
MaskGroupBasedCorrMaskRangeAreaModelsColorSampleInfo string_+
MaskGroupBasedCorrMaskRangeColorAmount
                                       real_+
                                           real_+
MaskGroupBasedCorrMaskRangeDepthFeather
                                           real_+
MaskGroupBasedCorrMaskRangeDepthMax
MaskGroupBasedCorrMaskRangeDepthMin
                                            real +
MaskGroupBasedCorrMaskRangeInvert
                                            boolean +
MaskGroupBasedCorrMaskRangeLumFeather
                                           real_+
MaskGroupBasedCorrMaskRangeLuminanceDepthSampleInfo string_+
                                     real_+
MaskGroupBasedCorrMaskRangeLumMax
MaskGroupBasedCorrMaskRangeLumMin
                                            real +
MaskGroupBasedCorrMaskRangeLumRange
                                            string_+
                                           integer_+
MaskGroupBasedCorrMaskRangeSampleType
                                           string_+
MaskGroupBasedCorrMaskRangeType
MaskGroupBasedCorrMaskRangeVersion
                                           string_+
MaskGroupBasedCorrMaskDabs
                                           string_+
MaskGroupBasedCorrMaskFeather
                                            real
MaskGroupBasedCorrMaskFlipped
                                           boolean
MaskGroupBasedCorrMaskFlow
                                           real_
MaskGroupBasedCorrMaskFullX
                                           real
MaskGroupBasedCorrMaskFullY
                                           real_
MaskGroupBasedCorrMaskInputDigest
                                           string
MaskGroupBasedCorrMaskLeft
                                           real
MaskGroupBasedCorrMaskMaskActive
                                           boolean_
MaskGroupBasedCorrMaskMaskBlendMode
                                           integer_
MaskGroupBasedCorrMaskMaskDigest
                                           string
MaskGroupBasedCorrMaskMaskInverted
                                           boolean_
MaskGroupBasedCorrMaskMaskName
                                           string
MaskGroupBasedCorrMaskMasks
                                            CorrectionMask Struct +
                                           real_
MaskGroupBasedCorrMaskMasksAlpha
MaskGroupBasedCorrMaskMasksAngle
                                           real_
MaskGroupBasedCorrMaskMasksBottom
                                            real
MaskGroupBasedCorrMaskMasksCenterValue
                                            real
```

```
MaskGroupBasedCorrMaskMasksCenterWeight
                                             real_
{\tt MaskGroupBasedCorrMaskMasksDabs}
                                             string_+
MaskGroupBasedCorrMaskMasksFeather
                                            real
MaskGroupBasedCorrMaskMasksFlipped
                                           boolean_
MaskGroupBasedCorrMaskMasksFlow
                                           real
MaskGroupBasedCorrMaskMasksFullX
                                           real_
MaskGroupBasedCorrMaskMasksFullY
                                           real_
MaskGroupBasedCorrMaskMasksInputDigest
                                           string
{\tt MaskGroupBasedCorrMaskMasksLeft}
                                           real_
                                           boolean_
MaskGroupBasedCorrMaskMasksMaskActive
MaskGroupBasedCorrMaskMasksMaskBlendMode
                                           integer_
MaskGroupBasedCorrMaskMasksMaskDigest
                                           string_
MaskGroupBasedCorrMaskMasksMaskInverted
                                           boolean_
MaskGroupBasedCorrMaskMasksMaskName
                                           string_
MaskGroupBasedCorrMaskMasksMaskSubType
                                           string_
MaskGroupBasedCorrMaskMasksMaskSyncID
                                           string_
MaskGroupBasedCorrMaskMasksValue
                                            real_
MaskGroupBasedCorrMaskMasksMaskVersion
                                            string
MaskGroupBasedCorrMaskMasksMidpoint
                                             real_
MaskGroupBasedCorrMaskMasksOrigin
                                             string_
MaskGroupBasedCorrMaskMasksPerimeterValue
                                             real
MaskGroupBasedCorrMaskMasksRadius
                                             real
MaskGroupBasedCorrMaskMasksReferencePoint
                                             string
MaskGroupBasedCorrMaskMasksRight
                                            real
MaskGroupBasedCorrMaskMasksRoundness
                                            real
MaskGroupBasedCorrMaskMasksSizeX
                                            real_
MaskGroupBasedCorrMaskMasksSizeY
                                            real
MaskGroupBasedCorrMaskMasksTop
                                            real
MaskGroupBasedCorrMaskMaskSubType
                                            string
MaskGroupBasedCorrMaskMasksVersion
                                            integer
MaskGroupBasedCorrMaskMasksWhat
                                           string
MaskGroupBasedCorrMaskMasksWholeImageArea
                                           string
MaskGroupBasedCorrMaskMasksX
                                            real
MaskGroupBasedCorrMaskMasksY
                                            real
MaskGroupBasedCorrMaskMaskSyncID
                                            string
MaskGroupBasedCorrMaskMasksZeroX
                                            real
MaskGroupBasedCorrMaskMasksZeroY
                                            real_
MaskGroupBasedCorrMaskValue
                                            real
MaskGroupBasedCorrMaskMaskVersion
                                            string
MaskGroupBasedCorrMaskMidpoint
                                            real_
MaskGroupBasedCorrMaskOrigin
                                            string
MaskGroupBasedCorrMaskPerimeterValue
                                            real_
MaskGroupBasedCorrMaskRadius
                                            real
MaskGroupBasedCorrMaskReferencePoint
                                            string
MaskGroupBasedCorrMaskRight
                                             real
MaskGroupBasedCorrMaskRoundness
                                            real
MaskGroupBasedCorrMaskSizeX
                                            real
MaskGroupBasedCorrMaskSizeY
                                             real
MaskGroupBasedCorrMaskTop
                                             real_
MaskGroupBasedCorrMaskVersion
                                            integer_
MaskGroupBasedCorrMaskWhat
                                            strina
MaskGroupBasedCorrMaskWholeImageArea
                                            string_
MaskGroupBasedCorrMaskX
                                            real
                                            real
MaskGroupBasedCorrMaskY
MaskGroupBasedCorrMaskZeroX
                                            real
MaskGroupBasedCorrMaskZeroY
                                            real
MaskGroupBasedCorrCorrectionName
                                            string +
MaskGroupBasedCorrRangeMask
                                            CorrRangeMask Struct_+
MaskGroupBasedCorrRangeMaskAreaModels
                                            AreaModels Struct_+
MaskGroupBasedCorrRangeMaskAreaModelsComponents string_+
MaskGroupBasedCorrRangeMaskAreaModelsColorSampleInfo string_+
MaskGroupBasedCorrRangeMaskColorAmount
                                         real_+
                                            real_+
MaskGroupBasedCorrRangeMaskDepthFeather
MaskGroupBasedCorrRangeMaskDepthMax
                                           real_+
MaskGroupBasedCorrRangeMaskDepthMin
                                            real_+
MaskGroupBasedCorrRangeMaskInvert
                                             boolean +
MaskGroupBasedCorrRangeMaskLumFeather
                                            real +
MaskGroupBasedCorrRangeMaskLuminanceDepthSampleInfo string_+
MaskGroupBasedCorrRangeMaskLumMax
                                           real +
MaskGroupBasedCorrRangeMaskLumMin
                                             real_+
```

```
MaskGroupBasedCorrRangeMaskLumRange
                                             string_+
MaskGroupBasedCorrRangeMaskSampleType
                                            integer_+
MaskGroupBasedCorrRangeMaskType
                                           string_+
MaskGroupBasedCorrRangeMaskVersion
                                           string +
MaskGroupBasedCorrCorrectionSyncID
                                           string +
MaskGroupBasedCorrBlacks2012
                                           real_
MaskGroupBasedCorrBrightness
                                           real_
MaskGroupBasedCorrClarity
                                           real_
MaskGroupBasedCorrClarity2012
                                           real_
MaskGroupBasedCorrContrast
                                           real_
MaskGroupBasedCorrContrast2012
                                           real_
MaskGroupBasedCorrDefringe
                                           real_
MaskGroupBasedCorrDehaze
                                            real_
MaskGroupBasedCorrExposure
                                            real_
MaskGroupBasedCorrExposure2012
                                           real_
MaskGroupBasedCorrHighlights2012
                                           real_
MaskGroupBasedCorrHue
                                            real
MaskGroupBasedCorrLuminanceNoise
                                            real
MaskGroupBasedCorrMoire
                                            real_
MaskGroupBasedCorrSaturation
                                             real
MaskGroupBasedCorrShadows2012
                                            real
MaskGroupBasedCorrSharpness
                                            real_
MaskGroupBasedCorrTemperature
                                            real
MaskGroupBasedCorrTexture
                                            real
MaskGroupBasedCorrTint
                                            real
MaskGroupBasedCorrToningHue
                                            real
MaskGroupBasedCorrToningSaturation
                                            real
MaskGroupBasedCorrWhites2012
                                            real
MaskGroupBasedCorrWhat
                                            string
MoireFilter
                                            string
                                            lang-alt/
NegativeCacheLargePreviewSize
                                            integer
NegativeCacheMaximumSize
                                            real
NegativeCachePath
                                            string
OverrideLookVignette
                                            boolean
PaintBasedCorrections
                                            Correction Struct+
PaintCorrectionActive
                                            boolean_
PaintCorrectionAmount
                                            real
PaintBasedCorrectionMasks
                                            CorrectionMask Struct_+
PaintCorrectionMaskAlpha
                                            real_
PaintCorrectionMaskAngle
                                            real
                                            real_
PaintCorrectionMaskBottom
PaintCorrectionMaskCenterValue
                                            real
PaintCorrectionMaskCenterWeight
                                            real
PaintCorrectionMaskRange
                                            CorrRangeMask Struct +
PaintCorrectionMaskRangeAreaModels
                                            AreaModels Struct_+
PaintCorrectionMaskRangeAreaModelsComponents string_+
PaintCorrectionMaskRangeAreaModelsColorSampleInfo string +
PaintCorrectionMaskRangeColorAmount
                                            real_+
PaintCorrectionMaskRangeDepthFeather
                                            real +
PaintCorrectionMaskRangeDepthMax
                                            real +
PaintCorrectionMaskRangeDepthMin
                                            real +
                                            boolean_+
PaintCorrectionMaskRangeInvert
PaintCorrectionMaskRangeLumFeather
                                            real +
PaintCorrectionMaskRangeLuminanceDepthSampleInfo string_+
PaintCorrectionMaskRangeLumMax
                                            real +
PaintCorrectionMaskRangeLumMin
                                           real +
PaintCorrectionMaskRangeLumRange
                                           string_+
PaintCorrectionMaskRangeSampleType
                                            integer +
PaintCorrectionMaskRangeType
                                           string +
PaintCorrectionMaskRangeVersion
                                           string_+
PaintCorrectionMaskDabs
                                            string_
PaintCorrectionMaskFeather
                                            real_
PaintCorrectionMaskFlipped
                                           boolean
PaintCorrectionMaskFlow
                                            real_
                                            real_
PaintCorrectionMaskFullX
                                            real_
PaintCorrectionMaskFullY
PaintCorrectionMaskInputDigest
                                            string
PaintCorrectionMaskLeft
                                             real
PaintCorrectionMaskMaskActive
                                             boolean
```

```
PaintCorrectionMaskMaskBlendMode
                                           integer_
PaintCorrectionMaskMaskDigest
                                           string
PaintCorrectionMaskMaskInverted
                                          boolean_
PaintCorrectionMaskMaskName
                                          string
PaintCorrectionMaskMasks
                                          CorrectionMask Struct +
PaintCorrectionMaskMasksAlpha
                                          real_
PaintCorrectionMaskMasksAngle
PaintCorrectionMaskMasksBottom
PaintCorrectionMaskMasksCenterValue
PaintCorrectionMaskMasksCenterWeight
PaintCorrectionMaskMasksDabs
                                          string_+
PaintCorrectionMaskMasksFeather
                                           real
PaintCorrectionMaskMasksFlipped
                                          boolean_
PaintCorrectionMaskMasksFlow
                                          real_
PaintCorrectionMaskMasksFullX
                                          real_
PaintCorrectionMaskMasksFullY
                                          real_
PaintCorrectionMaskMasksInputDigest
                                          string_
PaintCorrectionMaskMasksLeft
                                          real_
                                          boolean_
PaintCorrectionMaskMasksMaskActive
PaintCorrectionMaskMasksMaskBlendMode
                                           integer
PaintCorrectionMaskMasksMaskDigest
                                           string
PaintCorrectionMaskMasksMaskInverted
                                           boolean
PaintCorrectionMaskMasksMaskName
                                           string
PaintCorrectionMaskMasksMaskSubType
                                           string
                                           string_
PaintCorrectionMaskMasksMaskSyncID
PaintCorrectionMaskMasksValue
                                          real_
PaintCorrectionMaskMasksMaskVersion
                                          string_
PaintCorrectionMaskMasksMidpoint
                                          real_
PaintCorrectionMaskMasksOrigin
                                          strina
                                          real_
PaintCorrectionMaskMasksPerimeterValue
PaintCorrectionMaskMasksRadius
                                          real
PaintCorrectionMaskMasksReferencePoint
                                          strina
PaintCorrectionMaskMasksRight
                                          real
PaintCorrectionMaskMasksRoundness
                                          real_
PaintCorrectionMaskMasksSizeX
                                          real
PaintCorrectionMaskMasksSizeY
                                          real
PaintCorrectionMaskMasksTop
                                          real_
PaintCorrectionMaskMaskSubType
                                          string
PaintCorrectionMaskMasksVersion
PaintCorrectionMaskMasksWhat
                                          integer_
                                          string_
                                          string
PaintCorrectionMaskMasksWholeImageArea
PaintCorrectionMaskMasksX
                                           real
PaintCorrectionMaskMasksY
                                           real
PaintCorrectionMaskMaskSyncID
                                           string
PaintCorrectionMaskMasksZeroX
                                           real
PaintCorrectionMaskMasksZeroY
                                           real
PaintCorrectionMaskValue
                                           real
PaintCorrectionMaskMaskVersion
                                           string
PaintCorrectionMaskMidpoint
                                           real
PaintCorrectionMaskOrigin
                                           strina
PaintCorrectionMaskPerimeterValue
                                           real_
PaintCorrectionMaskRadius
                                           real
PaintCorrectionMaskReferencePoint
                                           string
PaintCorrectionMaskRight
                                           real
PaintCorrectionMaskRoundness
                                           real
PaintCorrectionMaskSizeX
                                           real
PaintCorrectionMaskSizeY
                                           real
PaintCorrectionMaskTop
                                          real
PaintCorrectionMaskVersion
                                           integer
PaintCorrectionMaskWhat
                                          string
PaintCorrectionMaskWholeImageArea
                                          string_
PaintCorrectionMaskX
                                           real_
PaintCorrectionMaskY
                                           real_
PaintCorrectionMaskZeroX
                                           real_
PaintCorrectionMaskZeroY
                                           real_
PaintCorrectionCorrectionName
                                           string_+
PaintCorrectionRangeMask
                                           CorrRangeMask Struct +
                                          AreaModels Struct +
PaintCorrectionRangeMaskAreaModels
PaintCorrectionRangeMaskAreaModelsComponents string +
PaintCorrectionRangeMaskAreaModelsColorSampleInfo string_+
```

PaintCorrectionRangeMaskColorAmount real + PaintCorrectionRangeMaskDepthFeather real + PaintCorrectionRangeMaskDepthMax real + PaintCorrectionRangeMaskDepthMin real + PaintCorrectionRangeMaskInvert boolean + PaintCorrectionRangeMaskLumFeather real\_+ PaintCorrectionRangeMaskLuminanceDepthSampleInfo string\_+ PaintCorrectionRangeMaskLumMax PaintCorrectionRangeMaskLumMin real\_+ PaintCorrectionRangeMaskLumRange string\_+ PaintCorrectionRangeMaskSampleType integer\_+ PaintCorrectionRangeMaskType string\_+ PaintCorrectionRangeMaskVersion string\_+ PaintCorrectionCorrectionSyncID string\_+ PaintCorrectionBlacks2012 real\_ PaintCorrectionBrightness real\_ PaintCorrectionClarity real\_ PaintCorrectionClarity2012 real\_ PaintCorrectionContrast real\_ PaintCorrectionContrast2012 real PaintCorrectionDefringe real PaintCorrectionDehaze real\_ PaintCorrectionExposure real PaintCorrectionExposure2012 real PaintCorrectionHighlights2012 real PaintCorrectionHue real\_ PaintCorrectionLuminanceNoise real PaintCorrectionMoire real\_ PaintCorrectionSaturation real PaintCorrectionShadows2012 real PaintCorrectionSharpness real PaintCorrectionTemperature real\_ PaintCorrectionTexture real\_ PaintCorrectionTint real\_ PaintCorrectionToningHue real\_ PaintCorrectionToningSaturation real\_ PaintCorrectionWhites2012 real\_ PaintCorrectionWhat string ParametricDarks integer ParametricHighlights integer ParametricHighlightSplit integer ParametricLights integer ParametricMidtoneSplit integer ParametricShadows integer ParametricShadowSplit integer PerspectiveAspect integer PerspectiveHorizontal integer PerspectiveRotate real PerspectiveScale integer PerspectiveUpright integer PerspectiveVertical integer PerspectiveX real PerspectiveY real PostCropVignetteAmount integer PostCropVignetteFeather integer PostCropVignetteHighlightContrast integer PostCropVignetteMidpoint integer PostCropVignetteRoundness integer PostCropVignetteStyle integer PresetType string ProcessVersion string RangeMask RangeMask Struct MapInfo Struct\_ RangeMaskMapInfo  ${\tt RangeMaskMapInfoLabMax}$ string\_ RangeMaskMapInfoLabMin string\_ RangeMaskMapInfoLumEq string + RangeMaskMapInfoRGBMax string\_ string\_ RangeMaskMapInfoRGBMin RawFileName string

string+

RedEyeInfo

```
RedHue
                                             integer
RedSaturation
                                             integer
RetouchAreas
                                             RetouchArea Struct+
RetouchAreaFeather
                                             real
RetouchAreaMasks
                                             CorrectionMask Struct +
RetouchAreaMaskAlpha
                                             real_
RetouchAreaMaskAngle
                                             real_
RetouchAreaMaskBottom
                                             real_
RetouchAreaMaskCenterValue
                                             real_
RetouchAreaMaskCenterWeight
                                             real_
                                             CorrRangeMask Struct_+
RetouchAreaMaskRange
RetouchAreaMaskRangeAreaModels
                                             AreaModels Struct_+
RetouchAreaMaskRangeAreaModelsComponents
                                            string_+
RetouchAreaMaskRangeAreaModelsColorSampleInfo string_+
RetouchAreaMaskRangeColorAmount
                                             real +
RetouchAreaMaskRangeDepthFeather
                                             real_+
RetouchAreaMaskRangeDepthMax
                                             real +
RetouchAreaMaskRangeDepthMin
                                             real +
RetouchAreaMaskRangeInvert
                                             boolean_+
RetouchAreaMaskRangeLumFeather
                                             real +
RetouchAreaMaskRangeLuminanceDepthSampleInfo string +
RetouchAreaMaskRangeLumMax
                                             real_+
RetouchAreaMaskRangeLumMin
                                             real +
RetouchAreaMaskRangeLumRange
                                             string +
RetouchAreaMaskRangeSampleType
                                             integer_+
RetouchAreaMaskRangeType
                                             string +
RetouchAreaMaskRangeVersion
                                             string +
RetouchAreaMaskDabs
                                             string_
RetouchAreaMaskFeather
                                             real
RetouchAreaMaskFlipped
                                             boolean
                                             real_
RetouchAreaMaskFlow
RetouchAreaMaskFullX
                                             real
RetouchAreaMaskFullY
                                             real
RetouchAreaMaskInputDigest
                                             string
RetouchAreaMaskLeft
                                             real
RetouchAreaMaskMaskActive
                                             boolean
RetouchAreaMaskMaskBlendMode
                                             integer_
RetouchAreaMaskMaskDigest
                                             string
RetouchAreaMaskMaskInverted
                                             boolean
RetouchAreaMaskMaskName
                                             string_
RetouchAreaMaskMasks
                                             CorrectionMask Struct +
                                             real_
RetouchAreaMaskMasksAlpha
RetouchAreaMaskMasksAngle
                                             real_
RetouchAreaMaskMasksBottom
                                             real
RetouchAreaMaskMasksCenterValue
                                             real
RetouchAreaMaskMasksCenterWeight
                                             real
RetouchAreaMaskMasksDabs
                                             string +
RetouchAreaMaskMasksFeather
                                             real
RetouchAreaMaskMasksFlipped
                                             boolean
RetouchAreaMaskMasksFlow
                                             real
RetouchAreaMaskMasksFullX
                                             real
RetouchAreaMaskMasksFullY
                                             real
RetouchAreaMaskMasksInputDigest
                                             string
RetouchAreaMaskMasksLeft
                                             real
RetouchAreaMaskMasksMaskActive
                                            boolean
RetouchAreaMaskMasksMaskBlendMode
                                             integer
RetouchAreaMaskMasksMaskDigest
                                             strina
RetouchAreaMaskMasksMaskInverted
                                            boolean
RetouchAreaMaskMasksMaskName
                                            string
RetouchAreaMaskMasksMaskSubType
                                            string
RetouchAreaMaskMaskSMaskSyncID
                                             string_
RetouchAreaMaskMasksValue
                                             real_
RetouchAreaMaskMasksMaskVersion
                                             string
RetouchAreaMaskMasksMidpoint
                                             real_
RetouchAreaMaskMasksOrigin
                                             string
RetouchAreaMaskMasksPerimeterValue
                                             real_
RetouchAreaMaskMasksRadius
                                             real
RetouchAreaMaskMasksReferencePoint
                                             string
RetouchAreaMaskMasksRight
                                             real
RetouchAreaMaskMasksRoundness
                                             real
```

RetouchAreaMaskMasksSizeX real RetouchAreaMaskMasksSizeY real\_ RetouchAreaMaskMasksTop real RetouchAreaMaskMaskSubType string RetouchAreaMaskMasksVersion integer RetouchAreaMaskMasksWhat string\_ RetouchAreaMaskMasksWholeImageArea string\_ RetouchAreaMaskMasksX real RetouchAreaMaskMasksY real\_ RetouchAreaMaskMaskSyncID string\_ RetouchAreaMaskMasksZeroX real\_ RetouchAreaMaskMasksZeroY real\_ RetouchAreaMaskValue real\_ RetouchAreaMaskMaskVersion string\_ RetouchAreaMaskMidpoint real\_ RetouchAreaMaskOrigin string\_ RetouchAreaMaskPerimeterValue real\_ RetouchAreaMaskRadius real RetouchAreaMaskReferencePoint string\_ RetouchAreaMaskRight real\_ RetouchAreaMaskRoundness real RetouchAreaMaskSizeX real\_ RetouchAreaMaskSizeY real RetouchAreaMaskTop real RetouchAreaMaskVersion integer\_ RetouchAreaMaskWhat string RetouchAreaMaskWholeImageArea string real\_ RetouchAreaMaskX RetouchAreaMaskY real RetouchAreaMaskZeroX real RetouchAreaMaskZeroY real RetouchAreaMethod string RetouchAreaOffsetY real RetouchAreaOpacity real RetouchAreaSeed integer RetouchAreaSourceState string RetouchAreaSourceX real\_ RetouchAreaSpotType string RetouchInfo string+ Saturation integer/ integer SaturationAdiustmentAqua SaturationAdiustmentBlue integer SaturationAdjustmentGreen integer SaturationAdjustmentMagenta integer SaturationAdjustmentOrange integer SaturationAdjustmentPurple integer SaturationAdjustmentRed integer SaturationAdjustmentYellow integer SDRBlend real SDRBrightness real SDRContrast real SDRHighlights real **SDRShadows** real SDRWhites real Shadows integer Shadows2012 integer ShadowTint integer SharpenDetail integer SharpenEdgeMasking integer SharpenRadius real Sharpness integer/ ShortName lang-alt Smoothness integer SortName lang-alt SplitToningBalance integer SplitToningHighlightHue integer integer SplitToningHighlightSaturation SplitToningShadowHue integer SplitToningShadowSaturation integer SupportsAmount boolean

EXILIOOI	13.21	ıug	Hames	
SupportsColor				boolean
SupportsHighDynamicRange				boolean
SupportsMonochrome				boolean
SupportsNormalDynamicRange				boolean
SupportsOutputReferred				boolean
SupportsSceneReferred				boolean
ColorTemperature				integer
Texture				integer
TIFFHandling				string
Tint				integer
ToggleStyleAmount				integer
ToggleStyleDigest				string
ToneCurve				string+
ToneCurveBlue				string+
ToneCurveGreen				string+
ToneCurveName				string
ToneCurveName2012				string
ToneCurvePV2012				string+
ToneCurvePV2012Blue				string+
ToneCurvePV2012Green				string+
ToneCurvePV2012Red				string+
ToneCurveRed				string+
ToneMapStrength				real
UprightCenterMode				integer
UprightCenterNormX				real
UprightCenterNormY				real
UprightDependentDigest				string
UprightFocalLength35mm				real
UprightFocalMode				integer
UprightFourSegments_0				string
UprightFourSegments_1				string
UprightFourSegments_2				string
UprightFourSegments_3				string
UprightFourSegmentsCount				integer
UprightGuidedDependentDigest				string
UprightPreview				boolean
UprightTransform_0				string
UprightTransform_1				string
UprightTransform_2				string
UprightTransform_3				string
UprightTransform_4				string
UprightTransform_5				string
UprightTransformCount				integer
UprightVersion				integer
UUID				string/
Version				string
Vibrance				integer
VignetteAmount				integer
VignetteMidpoint				integer
What				string
WhiteBalance Whites2012				string/
WIIILUESZUIZ				integer

# XMP dc Tags

Dublin Core namespace tags.

These tags belong to the ExifTool XMP-dc family 1 group.

Tag Name	Writable
Contributor Coverage Creator Date Description	string+ string string+ date+ lang-alt
Format Identifier Language Publisher	string string+ string+

```
Relation string+
Rights lang-alt
Source string/
Subject string+
Title lang-alt
Type string+
```

#### XMP Device Tags

Google depth-map Device tags. See <a href="https://developer.android.com/training/camera2/Dynamic-depth-v1.0.pdf">https://developer.android.com/training/camera2/Dynamic-depth-v1.0.pdf</a> for the specification.

These tags belong to the ExifTool XMP-Device family 1 group.

```
Writable
Tag Name
AppInfo
                                               AppInfo Struct
AppInfoApplication
                                               string_
AppInfoItemURI
                                               string_
AppInfoVersion
                                               string
Cameras
                                               DeviceCameras Struct+
Camera
                                               DeviceCamera Struct +
CameraAppInfo
                                               AppInfo Struct +
CameraAppInfoApplication
                                               string_+
CameraAppInfoItemURI
                                               string +
CameraAppInfoVersion
                                               string +
CameraDepthMap
                                              DeviceDepthMap Struct_+
CameraDepthMapConfidenceURI
                                              string +
CameraDepthMapDepthURI
                                              string +
CameraDepthMapFar
                                              real +
CameraDepthMapFocalTable
                                              string +
CameraDepthMapFocalTableEntryCount
                                              integer +
CameraDepthMapFormat
                                              string_+
CameraDepthMapItemSemantic
                                              string +
CameraDepthMapMeasureType
                                              string +
CameraDepthMapNear
                                              real_+
CameraDepthMapSoftware
                                               string +
CameraDepthMapUnits
                                               string +
CameraImage
                                               DeviceImage Struct_+
CameraImageItemSemantic
                                               string +
CameraImageItemURI
                                               string +
CameraImagingModel
                                               DeviceImagingModel Struct_+
CameraImagingModelDistortion
                                               string +
CameraImagingModelDistortionCount
                                              integer +
CameraImagingModelFocalLengthX
                                              real_+
CameraImagingModelFocalLengthY
                                              real +
CameraImagingModelImageHeight
                                               integer +
CameraImagingModelImageWidth
                                              integer_+
CameraImagingModelPixelAspectRatio
                                              real +
CameraImagingModelPrincipalPointX
                                              real +
CameraImagingModelPrincipalPointY
                                              real +
CameraImagingModelSkew
                                              real +
                                              DeviceLightEstimate Struct_+
CameraLightEstimate
CameraLightEstimateColorCorrectionB
                                              real +
CameraLightEstimateColorCorrectionG
                                              real +
CameraLightEstimateColorCorrectionR
                                              real +
CameraLightEstimatePixelIntensity
                                              real +
CameraPointCloud
                                              DevicePointCloud Struct_+
CameraPointCloudMetric
                                              boolean +
CameraPointCloudPointCloud
                                               integer_+
CameraPointCloudPoints
                                               string_+
CameraPose
                                               Pose Struct_+
CameraPosePositionX
                                              real_+
CameraPosePositionY
                                              real_+
                                              real_+
CameraPosePositionZ
CameraPoseRotationW
                                               real +
                                               real_+
CameraPoseRotationX
CameraPoseRotationY
                                               real +
CameraPoseRotationZ
                                               real_+
```

HAIIIOOI 13.21 lug	Names
CameraPoseTimestamp	integer_+
CameraTrait	string_+
CameraVendorInfo	VendorInfo Struct_+
CameraVendorInfoManufacturer CameraVendorInfoModel	string_+ string_+
CameraVendorInfoNotes	string_+
Container	DeviceContainer Struct
ContainerDirectory	DeviceOntainer Struct +
ContainerDirectoryItem	DeviceItem Struct_+
ContainerDirectoryItemDataURI	string_+
ContainerDirectoryItemLength	integer_+
ContainerDirectoryItemMime	string_+
ContainerDirectoryItemPadding	integer_+
EarthPos	EarthPose Struct
EarthPosAltitude	real_
EarthPosLatitude	real_
EarthPosLongitude	real_
EarthPosRotationW EarthPosRotationX	real_ real
EarthPosRotationY	real_
EarthPosRotationZ	real
EarthPosTimestamp	integer_
Planes	DevicePlanes Struct+
Plane	DevicePlane Struct_+
PlaneBoundary	string_+
PlaneBoundaryVertexCount	integer_+
PlaneExtentX	real_+
PlaneExtentZ	real_+
PlanePose	Pose Struct_+
PlanePosePositionX PlanePosePositionY	real_+
PlanePosePositionZ	real_+ real_+
PlanePoseRotationW	real +
PlanePoseRotationX	real_+
PlanePoseRotationY	real_+
PlanePoseRotationZ	real_+
PlanePoseTimestamp	integer_+
Pose	Pose Struct
PosePositionX	real_
PosePositionY	real_
PosePositionZ PoseRotationW	real_ real
PoseRotationX	real
PoseRotationY	real
PoseRotationZ	real
PoseTimestamp	integer_
Profiles	DeviceProfiles Struct+
Profile	DeviceProfile Struct_+
ProfileCameraIndices	integer_+
ProfileType	string_+
VendorInfo	VendorInfo Struct
VendorInfoManufacturer	string_
VendorInfoModel VendorInfoNotes	string_
	string_
XMP AppInfo Struct	
Field Name	Writable
Application	string
ItemURI	string
Version	string
XMP DeviceCameras Struct	
Field Name	Writable
Camera	DeviceCamera Struct

Field Name Writable

AppInfo AppInfo Struct
DepthMap DeviceDepthMap Struct
Image DeviceImage Struct

ImagingModelDeviceImagingModel StructLightEstimateDeviceLightEstimate StructPointCloudDevicePointCloud Struct

Pose Pose Struct Trait string

VendorInfo VendorInfo Struct

#### XMP DeviceDepthMap Struct

Field Name Writable ConfidenceURI string DepthURI string Far real FocalTable string FocalTableEntryCount integer Format string ItemSemantic string string MeasureType Near real Software string Units string

#### XMP DeviceImage Struct

Field Name Writable
----ItemSemantic string
ItemURI string

### XMP DeviceImagingModel Struct

Field Name Writable -----\_\_\_\_\_ Distortion string DistortionCount integer FocalLengthX real FocalLengthY real ImageHeight integer ImageWidth integer PixelAspectRatio real PrincipalPointX real PrincipalPointY real Skew real

### XMP DeviceLightEstimate Struct

Field Name Writable
----ColorCorrectionB real
ColorCorrectionG real
ColorCorrectionR real
PixelIntensity real

# XMP DevicePointCloud Struct

Field Name Writable
----Metric boolean
PointCloud integer
Points string

### XMP Pose Struct

Field Name Writable PositionX real PositionY real PositionZ real RotationW real RotationX real RotationY real RotationZ real Timestamp integer

#### XMP VendorInfo Struct

Field Name Writable
----Manufacturer string
Model string
Notes string

#### XMP DeviceContainer Struct

Field Name Writable

Directory DeviceDirectory Struct+

#### XMP DeviceDirectory Struct

Field Name Writable

Item DeviceItem Struct

### XMP DeviceItem Struct

Field Name Writable
----DataURI string
Length integer
Mime string
Padding integer

# XMP EarthPose Struct

Field Name Writable ------Altitude real Latitude real Longitude real RotationW real RotationX real RotationY real RotationZ real integer Timestamp

#### XMP DevicePlanes Struct

Field Name Writable

Plane DevicePlane Struct

#### XMP DevicePlane Struct

Field Name Writable
----Boundary string
BoundaryVertexCount integer
ExtentX real
ExtentZ real
Pose Pose Struct

XMP DeviceProfiles Struct

Field Name Writable

Profile DeviceProfile Struct

#### XMP DeviceProfile Struct

Field Name Writable
----CameraIndices integer+
Type string

#### XMP dex Tags

Description Explorer namespace tags. These tags are not very common. The Source and Rating tags are avoided when writing due to name conflicts with other XMP tags. (see <a href="http://www.optimasc.com/products/fileid/">http://www.optimasc.com/products/fileid/</a>)

These tags belong to the ExifTool XMP-dex family 1 group.

Tag Name \_\_\_\_\_ \_\_\_\_\_ CRC32 integer FFID string LicenseType string OS integer string/ Rating Revision string ShortDescription lang-alt Source string/

#### XMP DICOM Tags

DICOM namespace tags. These XMP tags allow some DICOM information to be stored in files of other than DICOM format. See the DICOM Tags documentation for a list of tags available in DICOM-format files.

These tags belong to the ExifTool XMP-DICOM family 1 group.

Tag Name Writable EquipmentInstitution string EquipmentManufacturer string PatientBirthDate date PatientID string PatientName string PatientSex string SeriesDateTime date SeriesDescription string SeriesModality string SeriesNumber string StudyDateTime date StudyDescription string StudyID string StudyPhysician string

# XMP digiKam Tags

DigiKam namespace tags.

These tags belong to the ExifTool XMP-digiKam family 1 group.

Tag Name	Writable
CaptionsAuthorNames CaptionsDateTimeStamps ColorLabel ImageHistory	lang-alt lang-alt string string/
ImageUniqueID	string/

LensCorrectionSettings string PicasawebGPhotoId string PickLabel string TagsList string+

#### XMP ExifTool Tags

These tags belong to the ExifTool XMP-et family 1 group.

Tag Name Writable OriginalImageHash string OriginalImageHashType string OriginalImageMD5 string

#### XMP exif Tags

EXIF namespace for EXIF tags. See <https://web.archive.org/web/20180921145139if\_/http://www.cipa.jp:80/std/documents</pre> /e/DC-010-2017\_E.pdf>

for the specification.

These tags belong to the ExifTool XMP-exif family 1 group.

Tag Name Writable \_\_\_\_\_ ApertureValue rational BrightnessValue rational

CFAPattern CFAPattern Struct

integer\_ CFAPatternColumns **CFAPatternRows** integer CFAPatternValues integer + ColorSpace integer ComponentsConfiguration integer+ CompressedBitsPerPixel rational Contrast integer CustomRendered integer DateTimeDigitized date DateTimeOriginal date

DeviceSettingDescription DeviceSettings Struct

DeviceSettingDescriptionColumns integer\_ integer\_ DeviceSettingDescriptionRows DeviceSettingDescriptionSettings string + DigitalZoomRatio rational ExifVersion string ExposureCompensation rational ExposureIndex rational ExposureMode integer ExposureProgram integer rational integer

ExposureTime FileSource Flash Flash Struct FlashEnergy rational FlashFired boolean FlashFunction boolean FlashMode integer FlashpixVersion string FlashRedEyeMode boolean

FlashReturn integer FNumber rational FocalLength rational FocalLengthIn35mmFormat integer FocalPlaneResolutionUnit integer FocalPlaneXResolution rational FocalPlaneYResolution rational GainControl integer **GPSAltitude** rational

GPSAltitudeRef integer **GPSAreaInformation** string GPSDestBearing rational GPSDestBearingRef string **GPSDestDistance** rational GPSDestDistanceRef string **GPSDestLatitude** string GPSDestLongitude string **GPSDifferential** integer **GPSDOP** rational GPSHPositioningError rational GPSImgDirection rational GPSImgDirectionRef string GPSLatitude string GPSLongitude string GPSMapDatum string GPSMeasureMode integer GPSProcessingMethod string **GPSSatellites** string **GPSSpeed** rational GPSSpeedRef string **GPSStatus** string **GPSDateTime** date **GPSTrack** rational GPSTrackRef string GPSVersionID string ImageUniqueID string/ ISO integer+ LightSource string MakerNote string MaxApertureValue rational MeteringMode integer NativeDigest string Opto-ElectricConvFactor OECF Struct OECFColumns integer **OECFNames** string + **OECFRows** integer\_ **OECFValues** rational + ExifImageWidth integer ExifImageHeight integer RelatedSoundFile string Saturation integer SceneCaptureType integer SceneType integer SensingMethod integer integer Sharpness ShutterSpeedValue rational SpatialFrequencyResponse OECF Struct SpatialFrequencyResponseColumns integer\_ SpatialFrequencyResponseNames string + SpatialFrequencyResponseRows integer SpatialFrequencyResponseValues rational\_+ SpectralSensitivity string SubjectArea integer+ SubjectDistance rational SubjectDistanceRange integer SubjectLocation integer+

# XMP CFAPattern Struct

UserComment

WhiteBalance

Field Name Writable
----Columns integer
Rows integer
Values integer+

lang-alt

integer

### XMP DeviceSettings Struct

Field Name Writable
----Columns integer

Rows integer Settings string+

### XMP Flash Struct

Field Name Writable
----Fired boolean
Function boolean
Mode integer
RedEyeMode boolean
Return integer

#### XMP OECF Struct

Field Name Writable
----Columns integer
Names string+
Rows integer
Values rational+

#### XMP exifEX Tags

RecommendedExposureIndex

SensitivityType

EXIF tags added by the EXIF 2.32 for XMP specification (see <a href="https://cipa.jp/std/documents/download\_e.html?DC-010-2020\_E">https://cipa.jp/std/documents/download\_e.html?DC-010-2020\_E</a>).

These tags belong to the ExifTool XMP-exifEX family 1 group.

Tag Name Writable Acceleration rational SerialNumber string CameraElevationAngle rational CameraFirmware string OwnerName string CompositeImage integer CompositeImageCount integer+ CompositeImageExposureTimes CompImageExp Struct rational\_ CompImageMaxExposureAll rational\_ CompImageMaxExposureUsed rational\_ CompImageMinExposureAll CompImageMinExposureUsed rational CompImageImagesPerSequence integer CompImageNumSequences integer CompImageSumExposureAll rational\_ CompImageSumExposureUsed rational CompImageTotalExposurePeriod rational CompImageValues rational\_+ Gamma rational Humidity rational ImageEditingSoftware string ImageEditor string string ImageTitle ImageUniqueID string InteropIndex string **ISOSpeed** integer ISOSpeedLatitudeyyy integer ISOSpeedLatitudezzz integer LensMake string LensModel string LensSerialNumber string LensInfo rational+ MetadataEditingSoftware string Photographer string PhotographicSensitivity integer Pressure rational RAWDevelopingSoftware string

integer

integer

StandardOutputSensitivity	integer
AmbientTemperature	rational
WaterDepth	rational

# XMP CompImageExp Struct

Field Name	Writable
MaxExposureTimesOfAll	rational
MaxExposureTimesOfUsed	rational
MinExposureTimesOfAll	rational
MinExposureTimesOfUsed	rational
NumberOfImagesInSequences	integer
NumberOfSequences	integer
SumOfExposureTimesOfAll	rational
SumOfExposureTimesOfUsed	rational
TotalExposurePeriod	rational
Values	rational+

#### XMP ExpressionMedia Tags

Microsoft Expression Media namespace tags. These tags are avoided when writing due to name conflicts with tags in other schemas.

These tags belong to the ExifTool XMP-expressionmedia family 1 group.

Tag Name	Writable
CatalogSets	string/+
Event	string/
People	string/+
Status	string/

### XMP extensis Tags

Tags used by Extensis Portfolio.

These tags belong to the ExifTool XMP-extensis family 1 group.

ApprovedBy s ClientName s JobName s JobStatus s RoutedTo s RoutingNotes s	Vritable
ApprovedBy s ClientName s JobName s JobStatus s RoutedTo s RoutingNotes s	
WorkToDo	ooolean string string string string string
MOINIODO	string

### XMP fpv Tags

```
Fast Picture Viewer tags (see
<http://www.fastpictureviewer.com/help/#rtfcomments>).
```

These tags belong to the ExifTool XMP-fpv family 1 group.

Tag Name	Writable
RichTextComment	string

#### XMP GAudio Tags

These tags belong to the ExifTool XMP-GAudio family 1 group.

Tag Name	Writable
AudioData AudioMimeType	string string

#### XMP GCamera Tags

Camera information found in Google panorama images.

These tags belong to the ExifTool XMP-GCamera family 1 group.

Tag Name	Writable
BurstID	string
BurstPrimary	string
DisableAutoCreation	string+
DisableSuggestedAction	string+
HDRPMakerNote	string
HdrPlusMakernote	string
MicroVideo	integer
MicroVideoOffset	integer
MicroVideoPresentationTimestampUs	integer
MicroVideoVersion	integer
MotionPhoto	integer
MotionPhotoPresentationTimestampUs	integer
MotionPhotoVersion	integer
PortraitNote	string
PortraitRequest	string
PortraitVersion	string
ShotLogData	string
SpecialTypeID	string+

# XMP GContainer Tags

Google Container namespace. ExifTool uses the prefix 'GContainer' instead of 'Container' to avoid a conflict with the Google Device Container namespace.

These tags belong to the ExifTool XMP-GContainer family 1 group.

Writable
Directory Struct+
<pre>Item Struct_+</pre>
string_+
integer_+
string_+
integer_+
string_+
string_+

# XMP Directory Struct

Field Name	Writable
Ttem	Item Struct

# XMP Item Struct

Field Name	Writable
Label	string
Length	integer
Mime	string
Padding	integer
Semantic	string
URI	string

# XMP GCreations Tags

Google creations tags.

These tags belong to the ExifTool XMP-GCreations family 1 group.

Tag Name Writable

CameraBurstID string
Type string/

### XMP GDepth Tags

Google depthmap information. See <a href="https://developers.google.com/depthmap-metadata/">https://developers.google.com/depthmap-metadata/</a> for the specification.

These tags belong to the ExifTool XMP-GDepth family 1 group.

Tag Name Writable Confidence string/ ConfidenceMime string/ DepthImage string/ Far real/ Format string/ ImageHeight real/ ImageWidth real/ Manufacturer string/ MeasureType string/ Mime string/ Model string/ Near real/ Software string/ Units string/

#### XMP GettyImages Tags

The actual Getty Images namespace prefix is "GettyImagesGIFT", which is the prefix recorded in the file, but ExifTool shortens this for the family 1 group name.

These tags belong to the ExifTool XMP-getty family 1 group.

Tag Name Writable \_\_\_\_\_ \_\_\_\_\_ AssetID string CallForImage string string CameraFilename CameraMakeModel string/ CameraSerialNumber string/ Composition string ExclusiveCoverage string GIFTFtpPriority string ImageRank string MediaEventIdDate string OriginalCreateDateTime date/ OriginalFileName string ParentMediaEventID string ParentMEID string Personality string+ PrimaryFTP string+ RoutingDestinations string+ RoutingExclusions string+ SecondaryFTP string+ TimeShot string

### XMP GFocus Tags

Focus information found in Google depthmap images.

These tags belong to the ExifTool XMP-GFocus family 1 group.

Tag Name	Writable
BlurAtInfinity	real
FocalDistance	real

FocalPointX real FocalPointY real

#### XMP GImage Tags

These tags belong to the ExifTool XMP-GImage family 1 group.

Tag Name	Writable
ImageData	string
ImageMimeType	string

#### XMP GPano Tags

Panorama tags written by Google Photosphere. See <a href="https://developers.google.com/panorama/metadata/">https://developers.google.com/panorama/metadata/</a> for the specification.

These tags belong to the ExifTool XMP-GPano family 1 group.

Tag Name	Writable
Tag Name	writable string real real real real real real real real

### XMP GSpherical Tags

Not actually XMP. These RDF/XML tags are used in Google spherical MP4 videos. These tags are written into the video track of MOV/MP4 files, and not at the top level like other XMP tags. See <a href="https://github.com/google/spatial-media/blob/master/docs/spherical-video-rfc.md">https://github.com/google/spatial-media/blob/master/docs/spherical-video-rfc.md</a> for the specification.

These tags belong to the ExifTool XMP-GSpherical family 1 group.

Writable
integer/
real/
real/

InitialViewRollDegrees real/ ProjectionType string/ SourceCount integer/ Spherical boolean/ StereoMode string/ Stitched boolean/ StitchingSoftware string/ TimeStamp integer/

#### XMP hdr Tags

HDR metadata namespace tags written by ACR 15.1. The actual namespace prefix is "hdr\_metadata", which is the prefix recorded in the file, but ExifTool shortens this for the family 1 group name.

These tags belong to the ExifTool XMP-hdr family 1 group.

Tag Name Writable
----
CCVAvgLuminanceNits real

CCVMaxLuminanceNits real

CCVMinLuminanceNits real

CCVPrimariesXY string

CCVWhiteXY string

SceneReferred boolean

#### XMP HDRGainMap Tags

Used in Apple HDR GainMap images.

These tags belong to the ExifTool XMP-HDRGainMap family 1 group.

Tag Name Writable
----HDRGainMapVersion string

### XMP hdrgm Tags

Tags used in Adobe gain map images.

These tags belong to the ExifTool XMP-hdrgm family 1 group.

Tag Name Writable \_\_\_\_\_ BaseRenditionIsHDR boolean GainMapMax real+ GainMapMin real+ Gamma real/+  ${\tt HDRCapacityMax}$ real HDRCapacityMin real OffsetHDR real+ OffsetSDR real+ Version string/

### XMP ics Tags

Tags used by IDimager. Nested TagStructure structures are unrolled to an arbitrary depth of 6 to avoid infinite recursion.

These tags belong to the ExifTool XMP-ics family 1 group.

Tag Name Writable AppVersion string/ ImageRef string SubVersions SubVersion Struct+ SubVersionFileName string\_+ string\_+ SubVersionReference TagStructure TagStructure Struct+ LabelName1 string\_+

<del>-</del>		
ParentReferencel	string_+	
Reference1	string_+	
SubLabels1	TagStructure	Struct_+
LabelName2	string_+	
ParentReference2	string_+	
Reference2	string_+	
SubLabels2	TagStructure	Struct_+
LabelName3	string_+	
ParentReference3	string_+	
Reference3	string_+	
SubLabels3	TagStructure	Struct_+
LabelName4	string_+	
ParentReference4	string_+	
Reference4	string_+	
SubLabels4	TagStructure	Struct
LabelName5	string_+	
ParentReference5	string_+	
Reference5	string_+	
SubLabels5	TagStructure	Struct
LabelName6	string_+	
ParentReference6	string_+	
Reference6	string_+	
TimeStamp	date/	

## XMP SubVersion Struct

Field Name	Writable
FileName	string
VersRef	string

#### XMP TagStructure Struct

Field Name	Writable
LabelName	string
ParentReference	string
Reference	string
SubLabels	TagStructure Struct+

# XMP iptcCore Tags

IPTC Core namespace tags. The actual IPTC Core namespace prefix is "Iptc4xmpCore", which is the prefix recorded in the file, but ExifTool shortens this for the family 1 group name. (see <http://www.iptc.org/IPTC4XMP/>)

These tags belong to the ExifTool XMP-iptcCore family 1 group.

Tag Name	Writable
AltTextAccessibility	lang-alt
CountryCode	string
CreatorContactInfo	ContactInfo Struct
CreatorCity	string_
CreatorCountry	string_
CreatorAddress	string_
CreatorPostalCode	string_
CreatorRegion	string_
CreatorWorkEmail	string_
CreatorWorkTelephone	string_
CreatorWorkURL	string_
ExtDescrAccessibility	lang-alt
IntellectualGenre	string
Location	string
Scene	string+
SubjectCode	string+

## XMP ContactInfo Struct

Field Name	Writable
CiAdrCity	string
CiAdrCtry	string
CiAdrExtadr	string
CiAdrPcode	string
CiAdrRegion	string
CiEmailWork	string
CiTelWork	string
CiUrlWork	string

#### XMP iptcExt Tags

This table contains tags defined by the IPTC Extension schema version 1.7 and IPTC Video Metadata version 1.3. The actual namespace prefix is "Iptc4xmpExt", but ExifTool shortens this for the family 1 group name. (See <a href="http://www.iptc.org/standards/photo-metadata/iptc-standard/">https://iptc.org/standards/video-metadata-hub/</a>.)

These tags belong to the ExifTool XMP-iptcExt family 1 group.

```
Tag Name
                                               Writable
AboutCvTerm
                                               CVTermDetails Struct+
AboutCvTermCvId
                                               string_+
AboutCvTermId
                                               string +
AboutCvTermName
                                               lang-alt_+
AboutCvTermRefinedAbout
                                               string_+
AdditionalModelInformation
                                               string
ArtworkOrObject
                                               ArtworkOrObjectDetails Struct+
ArtworkCircaDateCreated
                                               string! +
ArtworkContentDescription
                                               lang-alt +
ArtworkContributionDescription
                                               lang-alt +
ArtworkCopyrightNotice
                                               string_+
ArtworkCreator
                                               string +
ArtworkCreatorID
                                               string +
ArtworkCopyrightOwnerID
                                               string_+
ArtworkCopyrightOwnerName
                                               string +
ArtworkLicensorID
                                               string +
ArtworkLicensorName
                                               string_+
ArtworkDateCreated
                                               date +
ArtworkPhysicalDescription
                                               lang-alt +
ArtworkSource
                                               string +
ArtworkSourceInventoryNo
                                               string +
ArtworkSourceInvURL
                                               string +
ArtworkStylePeriod
                                               string_+
ArtworkTitle
                                               lang-alt +
AudioBitrate
                                               integer
AudioBitrateMode
                                               string
AudioBitsPerSample
                                               integer
AudioChannelCount
                                               integer
CircaDateCreated
                                               string
ContainerFormat
                                               Entity Struct
ContainerFormatIdentifier
                                               string +
ContainerFormatName
                                               lang-alt
Contributor
                                               EntityWithRole Struct+
ContributorIdentifier
                                               string +
ContributorName
                                               lang-alt_+
ContributorRole
                                               string_+
CopyrightYear
                                               integer
                                               EntityWithRole Struct+
Creator
CreatorIdentifier
                                               string_+
CreatorName
                                               lang-alt_+
CreatorRole
                                               string_+
{\tt Controlled Vocabulary Term}
                                               string+
                                               TextRegion Struct+
DataOnScreen
DataOnScreenRegion
                                               Area Struct_+
                                               real_+
DataOnScreenRegionD
DataOnScreenRegionH
                                               real +
DataOnScreenRegionText
                                               string_+
```

DataOnScreenRegionUnit string\_+ DataOnScreenRegionW real\_+ DataOnScreenRegionX real + DataOnScreenRegionY real + DigitalImageGUID string DigitalSourceFileType string DigitalSourceType string Dopesheet lang-alt DopesheetLink QualifiedLink Struct+ DopesheetLinkLink string\_+ DopesheetLinkLinkQualifier string\_+ EmbdEncRightsExpr EEREDetails Struct+ EmbeddedEncodedRightsExpr string\_+ EmbeddedEncodedRightsExprType string\_+  ${\tt EmbeddedEncodedRightsExprLangID}$ string\_+ Episode EpisodeOrSeason Struct EpisodeIdentifier string EpisodeName string\_ EpisodeNumber string\_ Event lang-alt ShownEvent Entity Struct+ string\_+ ShownEventIdentifier ShownEventName lang-alt + EventID string+ ExternalMetadataLink string+ FeedIdentifier string Genre CVTermDetails Struct+ GenreCvId string + GenreCvTermId string + lang-alt\_+ GenreCvTermName GenreCvTermRefinedAbout string + Headline lang-alt/ ImageRegion ImageRegion Struct+ ImageRegionName lang-alt\_+ ImageRegionCtype Entity Struct + ImageRegionCtypeIdentifier string + ImageRegionCtypeName lang-alt\_+ ImageRegionBoundary RegionBoundary Struct\_+ real\_+ ImageRegionBoundaryH ImageRegionBoundaryRx real\_+ ImageRegionBoundaryShape string + ImageRegionBoundaryUnit string + ImageRegionBoundaryVertices BoundaryPoint Struct\_+ ImageRegionBoundaryVerticesX real + real + ImageRegionBoundaryVerticesY ImageRegionBoundaryW real + ImageRegionBoundaryX real + ImageRegionBoundaryY real + ImageRegionID string\_+ ImageRegionRole Entity Struct\_+ ImageRegionRoleIdentifier string + ImageRegionRoleName lang-alt\_+ **IPTCLastEdited** date LinkedEncRightsExpr LEREDetails Struct+ LinkedEncodedRightsExpr string + LinkedEncodedRightsExprType string + LinkedEncodedRightsExprLangID string + LocationCreated LocationDetails Struct+ LocationCreatedCity string + LocationCreatedCountryCode string + LocationCreatedCountryName string\_+ LocationCreatedGPSAltitude rational\_+ LocationCreatedGPSAltitudeRef integer + LocationCreatedGPSLatitude string\_+ LocationCreatedGPSLongitude string + LocationCreatedIdentifier string + LocationCreatedLocationId string + LocationCreatedLocationName lang-alt + LocationCreatedProvinceState string +

string\_+

LocationCreatedSublocation

EXILIOOI 13.24 Tag Names -	_
LocationCreatedWorldRegion	string_+
LocationShown	LocationDetails Struct+
LocationShownCity	string_+
LocationShownCountryCode	string_+
LocationShownCountryName	string_+
LocationShownGPSAltitude	rational_+
LocationShownGPSAltitudeRef	integer_+
LocationShownGPSLatitude	string_+
LocationShownGPSLongitude	string_+
LocationShownIdentifier	string_+
LocationShownLocationId	string_+
LocationShownLocationName	lang-alt_+
LocationShownProvinceState	string_+
LocationShownSublocation	string_+
LocationShownWorldRegion	string_+
MaxAvailHeight MaxAvailWidth	integer
MetadataAuthority	integer
1	Entity Struct
MetadataAuthorityIdentifier	string_+
MetadataAuthorityName MetadataLastEdited	lang-alt_ date
MetadataLastEditor	Entity Struct
MetadataLastEditorIdentifier	string_+
MetadataLastEditorName	
ModelAge	<pre>lang-alt_ integer+</pre>
OrganisationInImageCode	string+
OrganisationInImageCode OrganisationInImageName	string+
ParentID	string
PersonHeard	Entity Struct+
PersonHeardIdentifier	string_+
PersonHeardName	lang-alt_+
PersonInImage	string+
PersonInImageWDetails	PersonDetails Struct+
PersonInImageCharacteristic	CVTermDetails Struct_+
PersonInImageCvTermCvId	string_+
PersonInImageCvTermId	string_+
PersonInImageCvTermName	lang-alt_+
PersonInImageCvTermRefinedAbout	string_+
PersonInImageDescription	lang-alt_+
PersonInImageId	string_+
PersonInImageName	lang-alt_+
PlanningRef	EntityWithRole Struct+
PlanningRefIdentifier	string_+
PlanningRefName	lang-alt_+
PlanningRefRole	string_+
ProductInImage	ProductDetails Struct+
ProductInImageDescription	lang-alt_+
ProductInImageGTIN	string_+
ProductInImageProductId	string_+
ProductInImageName	lang-alt_+
PublicationEvent	PublicationEvent Struct+
PublicationEventDate	date_+
PublicationEventIdentifier	string_+
PublicationEventName	string_+
Rating	Rating Struct+
RatingRegion	LocationDetails Struct_+
RatingRegionCity	string_+
RatingRegionCountryCode	string_+
RatingRegionCountryName	string_+
RatingRegionGPSAltitude	rational_+
RatingRegionGPSAltitudeRef	integer_+
RatingRegionGPSLatitude	string_+
RatingRegionGPSLongitude	string_+
RatingRegionIdentifier	string_+
RatingRegionLocationId	string_+
RatingRegionLocationName	lang-alt_+
RatingRegionProvinceState	string_+
RatingRegionSublocation	string_+
RatingRegionWorldRegion RatingScaleMaxValue	string_+ string_+
Nactingscatemaxvatue	oct titā _⊥

RatingScaleMinValue	string_+
RatingSourceLink	string_+
RatingValue	string_+
RatingValueLogoLink	string_+
RecDevice	Device Struct
RecDeviceAttLensDescription	string_
RecDeviceManufacturer	string_
RecDeviceModelName	string_
RecDeviceOwnersDeviceId	string_
RecDeviceSerialNumber	string_ string
RegistryID	RegistryEntryDetails Struct+
RegistryEntryRole	string +
RegistryItemID	string_+
RegistryOrganisationID	string_+ string_+
ReleaseReady	boolean
Season	EpisodeOrSeason Struct
SeasonIdentifier	string
SeasonName	string_
SeasonNumber	string_ string
Series	Series Struct
SeriesIdentifier	string_
SeriesName	string_ string
Snapshot	LinkedImage Struct+
SnapshotFormat	string_+
SnapshotHeightPixels	integer_+
SnapshotImageRole	string_+
Snapshotlink	string_+ string_+
Snapshotlink SnapshotLinkQualifier	string_+ string_+
SnapshotUsedVideoFrame	Timecode Struct_+
SnapshotUsedVideoFrameTimeFormat	string_+
SnapshotUsedVideoFrameTimeValue	string_+
SnapshotUsedVideoFrameValue SnapshotUsedVideoFrameValue	integer_+
SnapshotUsedvideoFramevarue	integer_+
StorylineIdentifier	string+
StreamReady	string
StylePeriod	string
SupplyChainSource	Entity Struct+
SupplyChainSourceIdentifier	string_+
SupplyChainSourceName	lang-alt_+
TemporalCoverage	TemporalCoverage Struct
TemporalCoverageFrom	date_
TemporalCoverageTo	date_
Transcript	lang-alt
TranscriptLink	QualifiedLink Struct+
TranscriptLinkLink	string_+
TranscriptLinkLinkQualifier	string_+
VideoBitrate	integer
VideoBitrateMode	string
VideoDisplayAspectRatio	rational
VideoEncodingProfile	string
VideoShotType	Entity Struct+
VideoShotTypeIdentifier	string_+
VideoShotTypeName	lang-alt_+
VideoStreamsCount	integer
VisualColor	string
WorkflowTag	CVTermDetails Struct
WorkflowTagCvId	string_
WorkflowTagCvTermId	string
WorkflowTagCvTermName	lang-alt_
WorkflowTagCvTermRefinedAbout	string_
<u>J</u>	<u></u>
XMP CVTermDetails Struct	
Field Name	Writable

CvId

CvTermId

CvTermName

 ${\tt CvTermRefinedAbout}$ 

-----

lang-alt

string

string

string

## XMP ArtworkOrObjectDetails Struct

Field Name	Writable
AOCircaDateCreated	string
AOContentDescription	lang-alt
AOContributionDescription	lang-alt
AOCopyrightNotice	string
AOCreator	string+
AOCreatorId	string+
AOCurrentCopyrightOwnerId	string
AOCurrentCopyrightOwnerName	string
AOCurrentLicensorId	string
AOCurrentLicensorName	string
AODateCreated	date
AOPhysicalDescription	lang-alt
AOSource	string
AOSourceInvNo	string
AOSourceInvURL	string
AOStylePeriod	string+
AOTitle	lang-alt

## XMP Entity Struct

Field Name	Writable
Identifier	string+
Name	lang-alt

## XMP EntityWithRole Struct

Field Name	Writable
Identifier Name Role	string+ lang-alt string+

# XMP TextRegion Struct

Field Name	Writable
Region RegionText	Area Struct string

## XMP Area Struct

Field Name	Writable
D	real
H	real
Unit	string
W	real
X	real
Y	real

## XMP QualifiedLink Struct

Field Name	Writable
Link	string
LinkQualifier	string

## XMP EEREDetails Struct

Writable
string
string
string

#### XMP EpisodeOrSeason Struct

Field Name	Writable	
Identifier	string	
Name	string	
Number	string	

## XMP ImageRegion Struct

This structure is new in the IPTC Extension version 1.5 specification. As well as the fields defined below, this structure may contain any top-level XMP tags, but since they aren't pre-defined the only way to add these tags is to write ImageRegion as a structure with these tags as new fields.

Field Name	Writable
Name	lang-alt
RegionBoundary	RegionBoundary Struct
RCtype	Entity Struct+
RId	string
RRole	Entity Struct+

#### XMP RegionBoundary Struct

Field Name	Writable
RbH	real
RbRx	real
RbShape	string
RbUnit	string
RbVertices	BoundaryPoint Struct+
RbW	real
RbX	real
RbY	real

## XMP BoundaryPoint Struct

Field Name	Writable
RbX	real
RbY	real

## XMP LEREDetails Struct

Field Name	Writable
LinkedRightsExpr	string
RightsExprEncType	string
RightsExprLangId	string

## XMP LocationDetails Struct

Note that the GPS elements of this structure are in the "exif" namespace.

Field Name	Writable
City	string
CountryCode	string
CountryName	string
GPSAltitude	rational
GPSAltitudeRef	integer
GPSLatitude	string
GPSLongitude	string
Identifier	string+
LocationId	string+
LocationName	lang-alt
ProvinceState	string

Sublocation string WorldRegion string

## XMP PersonDetails Struct

Field Name Writable

PersonCharacteristic CVTermDetails Struct+

PersonDescription lang-alt
PersonId string+
PersonName lang-alt

#### XMP ProductDetails Struct

Field Name Writable
-----ProductDescription lang-alt
ProductGTIN string
ProductId string
ProductName lang-alt

#### XMP PublicationEvent Struct

Field Name Writable
----Date date
Identifier string
Name string

# XMP Rating Struct

Field Name Writable

RatingRegion LocationDetails Struct+

RatingScaleMaxValue string
RatingScaleMinValue string
RatingSourceLink string
RatingValue string
RatingValueLogoLink string

## XMP Device Struct

Field Name Writable
-----AttLensDescription string
Manufacturer string
ModelName string
OwnersDeviceId string
SerialNumber string

#### XMP RegistryEntryDetails Struct

Field Name Writable
-----RegEntryRole string
RegItemId string
RegOrgId string

#### XMP Series Struct

Field Name Writable
----Identifier string
Name string

#### XMP LinkedImage Struct

Field Name Writable
----HeightPixels integer

ImageRolestringLinkstringLinkQualifierstring+

UsedVideoFrame Timecode Struct

WidthPixels integer Format string

#### XMP Timecode Struct

Field Name Writable
----TimeFormat string
TimeValue string
Value integer

#### XMP TemporalCoverage Struct

Field Name Writable
----TempCoverageFrom date
TempCoverageTo date

#### XMP LImage Tags

Tags written by RED smartphones.

These tags belong to the ExifTool XMP-LImage family 1 group.

Tag Name Writable
----MajorVersion string
MinorVersion string
RightAlbedo string

## XMP Lightroom Tags

Adobe Lightroom "lr" namespace tags.

These tags belong to the ExifTool XMP-lr family 1 group.

Tag Name Writable
----HierarchicalSubject string+
PrivateRTKInfo string
WeightedFlatSubject string+

#### XMP MediaPro Tags

iView MediaPro namespace tags.

These tags belong to the ExifTool XMP-mediapro family 1 group.

Tag Name Writable
-----CatalogSets string+
Event string/
Location string/
People string+
Status string
UserFields string+

#### XMP panorama Tags

Adobe Photoshop Panorama-profile tags.

These tags belong to the ExifTool XMP-panorama family 1 group.

Tag Name Writable
----Transformation string

VirtualFocalLength real
VirtualImageXCenter real
VirtualImageYCenter real

## XMP pdf Tags

Adobe PDF namespace tags. The official XMP specification defines only Keywords, PDFVersion, Producer and Trapped. The other tags are included because they have been observed in PDF files, but some are avoided when writing due to name conflicts with other XMP namespaces.

These tags belong to the ExifTool XMP-pdf family 1 group.

Tag Name Writable Author string Copyright string/ CreationDate date Creator string/ Keywords string Marked boolean/ ModDate date PDFVersion string Producer string Subject string/ Title string/ string Trapped

#### XMP pdfx Tags

PDF extension tags. This namespace is used to store application-defined PDF information, so there are few pre-defined tags. User-defined tags must be created to enable writing of other XMP-pdfx information.

These tags belong to the ExifTool XMP-pdfx family 1 group.

Tag Name Writable
----SourceModified string

## XMP photoshop Tags

Adobe Photoshop namespace tags.

These tags belong to the ExifTool XMP-photoshop family 1 group.

Tag Name	Writable
AuthorsPosition CameraProfiles CameraProfilesApertureValue CameraProfilesAuthor CameraProfilesAutoScale CameraProfilesCameraPrettyName CameraProfilesCameraRawProfile CameraProfilesFocalLength CameraProfilesFocusDistance	string Camera Struct+ real_+ string_+ boolean_+ string_+ boolean_+ real_+ real_+
CameraProfilesLens CameraProfilesLensPrettyName CameraProfilesMake CameraProfilesModel CameraProfilesPerspectiveModel CameraProfilesPerspectiveModelImageXCenter CameraProfilesPerspectiveModelImageYCenter CameraProfilesPerspectiveModelRadialDistortPa	ram1 real_+
CameraProfilesPerspectiveModelRadialDistortPa CameraProfilesPerspectiveModelRadialDistortPa CameraProfilesPerspectiveModelScaleFactor CameraProfilesPerspectiveModelVersion	ram3 real_+

CameraProfilesProfileName string\_+ CameraProfilesSensorFormatFactor real\_+ CameraProfilesUniqueCameraModel string\_+ CaptionWriter string Category string City string ColorMode integer Country string Credit string DateCreated date DocumentAncestors string+ EmbeddedXMPDigest string Headline string History string ICCProfileName string Instructions string LegacyIPTCDigest string SidecarForExtension string Source string State string SupplementalCategories string+ TextLayers Layer Struct+ TextLayerName string + TextLayerText string + TransmissionReference string Urgency integer

#### XMP Camera Struct

Field Name Writable ApertureValue real Author string AutoScale boolean CameraPrettyName string CameraRawProfile boolean FocalLength real FocusDistance real Lens string LensPrettyName string Make string Model string PerspectiveModel PerspectiveModel Struct ProfileName string SensorFormatFactor real

string

#### XMP PerspectiveModel Struct

UniqueCameraModel

Field Name Writable ImageXCenter real ImageYCenter real RadialDistortParam1 real RadialDistortParam2 real RadialDistortParam3 real ScaleFactor real Version string

#### XMP Layer Struct

Field Name Writable
----LayerName string
LayerText string

## XMP PixelLive Tags

PixelLive namespace tags. These tags are not writable because they are very uncommon and I haven't been able to locate a reference which gives

the namespace URI.

These tags belong to the ExifTool XMP-PixelLive family 1 group.

Tag Name	Writable
Author	no
Comments	no
Copyright	no
Date	no
Genre	no
Title	no

## XMP pmi Tags

```
PRISM Metadata for Images 3.0 namespace tags. (see <a href="http://www.prismstandard.org/">http://www.prismstandard.org/</a>)
```

These tags belong to the ExifTool XMP-pmi family 1 group.

Tag Name	Writable
Tag Name	writable string/
1	

## XMP prism Tags

```
Publishing Requirements for Industry Standard Metadata 3.0 namespace
tags. (see
<https://www.w3.org/Submission/2020/SUBM-prism-20200910/prism-basic.html>)
```

These tags belong to the ExifTool XMP-prism family 1 group.

Tag Name	Writable
AcademicField	string/
AggregateIssueNumber	integer/
AggregationType	string/+

AlternateTitle	<pre>prismAlternateTitle Struct+</pre>
AlternateTitleA-lang	string/_+
AlternateTitleA-platform	string/_+
AlternateTitleText	string/ +
BlogTitle	string/
BlogURL	string/
BookEdition	
	string/
ByteCount	integer/
Channel	prismChannel Struct+
ChannelA-lang	string/_+
ChannelChannel	string/ +
ChannelSubchannel1	string/_+
ChannelSubchannel2	
	string/_+
ChannelSubchannel3	string/_+
ChannelSubchannel4	string/_+
ComplianceProfile	string/
ContentType	string/
CopyrightYear	string/
	string/+
CorporateEntity	_
CoverDate	date/
CoverDisplayDate	string/
CreationDate	date/
DateRecieved	date/
Device	string/
Distributor	_
	string/
DOI	string/
Edition	string/
EIssn	string/
EndingPage	string/
Event	string/+
	_
Genre	string/+
HasAlternative	string/+
HasCorrection	prismHasCorrection Struct
HasCorrectionA-lang	string/_
HasCorrectionA-platform	string/_
HasCorrectionText	string/_
HasTranslation	string/+
Industry	string/+
IsAlternativeOf	string/+
ISBN	string/+
IsCorrectionOf	string/+
ISSN	string/
IssueIdentifier	string/
	_
IssueName	string/
IssueTeaser	string/
IssueType	string/
IsTranslationOf	string/
Keyword	string/+
KillDate	prismKillDate Struct
KillDateA-platform	string/_
<del>-</del>	
KillDateDate	date/_
Link	string/+
Location	string/+
ModificationDate	date/
NationalCatalogNumber	string/
Number	string/
	_
Object	string/+
OffSaleDate	prismOffSaleDate Struct+
OffSaleDateA-platform	string/_+
OffSaleDateDate	date/ +
OnSaleDate	prismOnSaleDate Struct+
OnSaleDateA-platform	string/_+
OnSaleDateDate	date/_+
OnSaleDay	prismOnSaleDay Struct+
OnSaleDayA-platform	string/_+
OnSaleDayDay	string/_+
Organization	string/+
OriginPlatform	string/+
PageCount	integer/
PageProgressionDirection	string/

```
PageRange
                                                  string/+
  Person
                                                  string/
  Platform
                                                 string/
  ProductCode
                                                 string/
  Profession
                                                 string/
  PublicationDate
                                                 prismPublicationDate Struct+
  PublicationDateA-platform
                                                 string/_+
  PublicationDateDate
                                                 date/_+
                                                 prismPublicationDate Struct+
  PublicationDisplayDate
  PublicationDisplayDateA-platform
                                                 string/_+
  PublicationDisplayDateDate
                                                 date/_+
  PublicationName
                                                 string/
  PublishingFrequency
                                                 string/
  Rating
                                                 string/
  SamplePageRange
                                                 string/
  Section
                                                 string/
  SellingAgency
                                                  string/
  SeriesNumber
                                                 integer/
  SeriesTitle
                                                  string/
  Sport
                                                  string/
  StartingPage
                                                  string/
  Subsection1
                                                  string/
  Subsection2
                                                  string/
  Subsection3
                                                  string/
  Subsection4
                                                 string/
  Subtitle
                                                 string/
  SupplementDisplayID
                                                 string/
  SupplementStartingPage
                                                 string/
  SupplementTitle
                                                 string/
  Teaser
                                                  string/+
  Ticker
                                                 string/+
  TimePeriod
                                                  string/
  URL
                                                 prismUrl Struct+
  URLA-platform
                                                  string/_+
  URLUrl
                                                  string/_+
  UspsNumber
                                                  string/
  VersionIdentifier
                                                 string/
  Volume
                                                 string/
  WordCount
                                                  integer/
XMP prismAlternateTitle Struct
  Field Name
                                                  Writable
  ______
                                                  _____
  A-lang
                                                  string
  A-platform
                                                  string
  Text
                                                  string
XMP prismChannel Struct
  Field Name
                                                  Writable
  A-lang
                                                  string
  Channel
                                                  string
  Subchannel1
                                                 string
  Subchannel2
                                                 string
  Subchannel3
                                                  string
  Subchannel4
                                                  string
XMP prismHasCorrection Struct
                                                  Writable
  Field Name
  A-lang
                                                  string
  A-platform
                                                  string
  Text
                                                  string
```

XMP prismKillDate Struct
Field Name

Writable

A-platform string Date date

## XMP prismOffSaleDate Struct

Field Name Writable
-----A-platform string
Date date

### XMP prismOnSaleDate Struct

Field Name Writable
----A-platform string
Date date

### XMP prismOnSaleDay Struct

Field Name Writable
----A-platform string
Day string

## XMP prismPublicationDate Struct

Field Name Writable
-----A-platform string
Date date

#### XMP prismUrl Struct

Field Name Writable
----A-platform string
Url string

## XMP prl Tags

PRISM Rights Language 2.1 namespace tags. These tags have been deprecated since the release of the PRISM Usage Rights 3.0. (see <a href="https://www.w3.org/submissions/2020/SUBM-prism-20200910/prism-image.html">https://www.w3.org/submissions/2020/SUBM-prism-20200910/prism-image.html</a>)

These tags belong to the ExifTool XMP-prl family 1 group.

Tag Name Writable
----Geography string/+
Industry string/+
Usage string/+

## XMP prm Tags

PRISM Recipe Metadata 3.0 namespace tags. (see
<http://www.prismstandard.org/>)

These tags belong to the ExifTool XMP-prm family 1 group.

Tag Name	Writable
CookingEquipment	string/
CookingMethod	string/
Course	string/
Cuisine	string/
DietaryNeeds	string/
DishType	string/
Duration	string/
IngredientExclusion	string/

MainIngredient string/ Meal string/ RecipeEndingPage string/ RecipePageRange string/ RecipeSource string/ RecipeStartingPage string/ RecipeTitle string/ ServingSize string/ SkillLevel string/ SpecialOccasion string/ Yield string/

#### XMP pur Tags

PRISM Usage Rights 3.0 namespace tags. (see <a href="http://www.prismstandard.org/">http://www.prismstandard.org/</a>)

These tags belong to the ExifTool XMP-pur family 1 group.

Tag Name Writable AdultContentWarning string/+ Agreement string/+ Copyright lang-alt/ string/+ CreditLine EmbargoDate date/+ ExclusivityEndDate date/+ date/+ ExpirationDate ImageSizeRestriction string/ OptionEndDate date/+ Permissions string/+ Restrictions string/+ ReuseProhibited boolean/ RightsAgent string/ RightsOwner string/

# XMP rdf Tags

Most RDF attributes are handled internally, but the "about" attribute is treated specially to allow it to be set to a specific value if required.

These tags belong to the ExifTool XMP-rdf family 1 group.

Tag Name Writable
----About string!

## XMP seal Tags

SEAL embedded in XMP.

These tags belong to the ExifTool XMP-seal family 1 group.

Tag Name Writable
----Seal XMP SEAL

#### XMP SEAL Tags

These tags are used in SEAL (Secure Evidence Attribution Label) content authentification, which is actually XML format, not XMP. ExifTool has read/delete support for SEAL information in JPG, TIFF, XMP, PNG, WEBP, HEIC, PPM, MOV and MP4 files, and read-only support in PDF, MKV and WAV. Use "-seal:all=" on the command line to delete SEAL information in supported formats. See <a href="https://github.com/hackerfactor/SEAL">https://github.com/hackerfactor/SEAL</a> for the specification.

Tag ID Tag Name Writable

'b'	ByteRange	no
'copyright'	Copyright	no
'd'	Domain	no
'da'	DigestAlgorithm	no
'id'	Identifier	no
'info'	SEALComment	no
'ka'	KeyAlgorithm	no
'kv'	KeyVersion	no
'S'	Signature	no
'seal'	SEALVersion	no
'sf'	SignatureFormat	no
'sl'	SignatureLength	no
'uid'	UniqueIdentifier	no

## XMP swf Tags

Adobe SWF namespace tags.

These tags belong to the ExifTool XMP-swf family 1 group.

Tag Name	Writable
BackgroundAlpha	integer
ForwardLock	boolean
MaxStorage	integer
Type	string/

## XMP tiff Tags

EXIF namespace for TIFF tags. See <a href="https://web.archive.org/web/20180921145139if\_/http://www.cipa.jp:80/std/documents/e/DC-010-2017">https://www.cipa.jp:80/std/documents/e/DC-010-2017</a> E.pdf>

for the specification.

These tags belong to the ExifTool XMP-tiff family 1 group.

Tag Name	Writable
Artist BitsPerSample	string integer+
Compression	integer
Copyright	lang-alt
DateTime	date
ImageDescription	lang-alt
ImageHeight	integer
ImageWidth	integer
Make	string
Model	string
NativeDigest	string/
Orientation	integer
PhotometricInterpretation	integer
PlanarConfiguration	integer
PrimaryChromaticities	rational+
ReferenceBlackWhite	rational+
ResolutionUnit	integer
SamplesPerPixel	integer
Software	string
TransferFunction	integer+
WhitePoint	rational+
XResolution	rational
YCbCrCoefficients	rational+
YCbCrPositioning	integer
YCbCrSubSampling	integer+
YResolution	rational

# $\underline{\text{XMP}}$ $\underline{\text{x}}$ $\underline{\text{Tags}}$

The "x" namespace is used for the "xmpmeta" wrapper, and may contain an "xmptk" attribute that is extracted as the XMPToolkit tag. When writing, the XMPToolkit tag is generated automatically by ExifTool

unless specifically set to another value.

These tags belong to the ExifTool XMP-x family 1 group.

Tag Name Writable
----XMPToolkit string!

#### XMP xmp Tags

XMP namespace tags. If the older "xap", "xapBJ", "xapMM" or "xapRights" namespace prefixes are found, they are translated to the newer "xmp", "xmpBJ", "xmpMM" and "xmpRights" prefixes for use in family 1 group names.

These tags belong to the ExifTool XMP-xmp family 1 group.

Tag Name Writable Advisory string+ Author string/ BaseURL string CreateDate date CreatorTool string Description lang-alt/ Format string/ Identifier string/+ Keywords string/ Label string MetadataDate date ModifyDate date Nickname string PageInfo PageInfo Struct+ PageImageFormat string\_+ PageImageHeight integer\_+ PageImage string\_+ PageImagePageNumber integer\_+ PageImageWidth integer\_+ Rating real RatingPercent real/ Thumbnail Struct+ Thumbnails ThumbnailFormat string\_+ ThumbnailHeight integer\_+ string/\_+ ThumbnailImage ThumbnailWidth integer + Title lang-alt/

#### XMP PageInfo Struct

Field Name Writable
-----PageNumber integer
Format string
Height integer
Image string
Width integer

### XMP Thumbnail Struct

Field Name Writable
----Format string
Height integer
Image string
Width integer

## XMP xmpBJ Tags

XMP Basic Job Ticket namespace tags.

These tags belong to the ExifTool XMP-xmpBJ family 1 group.

Tag Name Writable \_\_\_\_\_ JobRef Struct+ JobRef JobRefid string\_+ JobRefName string\_+ JobRefUrl string\_+

#### XMP JobRef Struct

Writable Field Name Тđ string Name string Url string

#### XMP xmpDM Tags

XMP Dynamic Media namespace tags.

These tags belong to the ExifTool XMP-xmpDM family 1 group.

Tag Name Writable \_\_\_\_\_ AbsPeakAudioFilePath string Album string AltTapeName string AltTimecode Timecode Struct AltTimecodeTimeFormat string\_ AltTimecodeTimeValue string AltTimecodeValue integer Artist string/ AudioChannelType string AudioCompressor string AudioModDate date AudioSampleRate integer AudioSampleType string BeatSpliceParams BeatSpliceStretch Struct real\_ BeatSpliceParamsRiseInDecibel BeatSpliceParamsRiseInTimeDuration Time Struct BeatSpliceParamsRiseInTimeDurationScale rational integer\_ BeatSpliceParamsRiseInTimeDurationValue BeatSpliceParamsUseFileBeatsMarker boolean CameraAngle string CameraLabel string CameraModel string CameraMove string Client string DMComment string Composer string ContributedMedia Media Struct+ ContributedMediaDuration Time Struct + ContributedMediaDurationScale rational + ContributedMediaDurationValue integer\_+ ContributedMediaManaged boolean + ContributedMediaPath string + ContributedMediaStartTime Time Struct\_+ ContributedMediaStartTimeScale rational\_+ ContributedMediaStartTimeValue integer +

ContributedMediaTrack string\_+  ${\tt Contributed Media Web Statement}$ string\_+ Copyright string/ Director string DirectorPhotography string DiscNumber string Duration Time Struct rational\_ DurationScale DurationValue integer\_ Engineer string

FileDataRate rational Genre string Good boolean Instrument string IntroTime Time Struct IntroTimeScale rational\_ IntroTimeValue integer\_ Key string LogComment string Loop boolean Lyrics string Markers Marker Struct+ MarkersComment string\_+ MarkersCuePointParams CuePointParam Struct\_+ MarkersCuePointParamsKey string\_+ MarkersCuePointParamsValue string\_+ MarkersCuePointType string\_+ MarkersDuration string + MarkersLocation string\_+ MarkersName string\_+ MarkersProbability real + MarkersSpeaker string\_+ MarkersStartTime string + MarkersTarget string + string\_+ MarkersType MetadataModDate date NumberOfBeats real OutCue Time Struct OutCueScale rational OutCueValue integer PartOfCompilation boolean Pick integer ProjectName string ProjectRef ProjectLink Struct ProjectRefPath string ProjectRefType string PullDown string RelativePeakAudioFilePath string RelativeTimestamp Time Struct RelativeTimestampScale rational\_ RelativeTimestampValue integer ReleaseDate date ResampleParams ResampleStretch Struct ResampleParamsQuality string ScaleType string Scene string/ ShotDate date ShotDay string ShotLocation string ShotName string ShotNumber string ShotSize string SpeakerPlacement string StartTimecode Timecode Struct StartTimecodeTimeFormat string StartTimecodeTimeValue string StartTimecodeValue integer StartTimeSampleSize integer StartTimeScale string StretchMode string TakeNumber integer TapeName string Tempo real TimeScaleParams TimeScaleStretch Struct TimeScaleParamsFrameOverlappingPercentage real\_ real\_ TimeScaleParamsFrameSize string\_ TimeScaleParamsQuality TimeSignature string TrackNumber integer

Track Struct+

Tracks

TracksFrameRate	string_+
TracksMarkers	Marker Struct_+
TracksMarkersComment	string_+
TracksMarkersCuePointParams	CuePointParam Struct_+
TracksMarkersCuePointParamsKey	string_+
TracksMarkersCuePointParamsValue	string_+
TracksMarkersCuePointType	string +
TracksMarkersDuration	string_+
TracksMarkersLocation	string +
	3—
TracksMarkersName	string_+
TracksMarkersProbability	real_+
TracksMarkersSpeaker	string_+
TracksMarkersStartTime	string_+
TracksMarkersTarget	string_+
TracksMarkersType	string_+
TracksTrackName	string_+
TracksTrackType	string_+
VideoAlphaMode	string
VideoAlphaPremultipleColor	Colorant Struct
VideoAlphaPremultipleColorA	integer_
VideoAlphaPremultipleColorB	integer
VideoAlphaPremultipleColorBlack	real
VideoAlphaPremultipleColorBlue	integer
	-
VideoAlphaPremultipleColorCyan	real_
VideoAlphaPremultipleColorGray	integer_
VideoAlphaPremultipleColorGreen	integer_
VideoAlphaPremultipleColorL	real_
VideoAlphaPremultipleColorMagenta	real
VideoAlphaPremultipleColorMode	string_
VideoAlphaPremultipleColorRed	integer
VideoAlphaPremultipleColorSwatchName	string_
VideoAlphaPremultipleColorTint	integer_
VideoAlphaPremultipleColorType	string_
VideoAlphaPremultipleColorYellow	real_
VideoAlphaUnityIsTransparent	boolean
VideoColorSpace	string
VideoCompressor	string
VideoFieldOrder	
	string
VideoFrameRate	real
VideoFrameSize	Dimensions Struct
VideoFrameSizeH	real_
VideoFrameSizeUnit	string_
VideoFrameSizeW	real
VideoModDate	date
VideoPixelAspectRatio	rational
VideoPixelDepth	string
XMP <u>BeatSpliceStretch</u> <u>Struct</u>	
m' 11 m	
Field Name	Writable
Field Name	Writable
 RiseInDecibel	real
RiseInDecibel RiseInTimeDuration	real Time Struct
 RiseInDecibel	real
RiseInDecibel RiseInTimeDuration	real Time Struct
RiseInDecibel RiseInTimeDuration	real Time Struct
RiseInDecibel RiseInTimeDuration UseFileBeatsMarker	real Time Struct
RiseInDecibel RiseInTimeDuration UseFileBeatsMarker	real Time Struct boolean
RiseInDecibel RiseInTimeDuration UseFileBeatsMarker  XMP Time Struct Field Name	real Time Struct boolean Writable
RiseInDecibel RiseInTimeDuration UseFileBeatsMarker  XMP Time Struct  Field Name	real Time Struct boolean  Writable
RiseInDecibel RiseInTimeDuration UseFileBeatsMarker  XMP Time Struct  Field Name	real Time Struct boolean  Writable rational
RiseInDecibel RiseInTimeDuration UseFileBeatsMarker  XMP Time Struct  Field Name	real Time Struct boolean  Writable
RiseInDecibel RiseInTimeDuration UseFileBeatsMarker  XMP Time Struct  Field Name	real Time Struct boolean  Writable rational
RiseInDecibel RiseInTimeDuration UseFileBeatsMarker  XMP Time Struct  Field Name	real Time Struct boolean  Writable rational
RiseInDecibel RiseInTimeDuration UseFileBeatsMarker  XMP Time Struct  Field Name	real Time Struct boolean  Writable rational integer
RiseInDecibel RiseInTimeDuration UseFileBeatsMarker  XMP Time Struct  Field Name	real Time Struct boolean  Writable rational integer
RiseInDecibel RiseInTimeDuration UseFileBeatsMarker  XMP Time Struct  Field Name	real Time Struct boolean  Writable rational integer  Writable
RiseInDecibel RiseInTimeDuration UseFileBeatsMarker  XMP Time Struct  Field Name	real Time Struct boolean  Writable rational integer  Writable Time Struct
RiseInDecibel RiseInTimeDuration UseFileBeatsMarker  XMP Time Struct  Field Name	real Time Struct boolean  Writable rational integer  Writable
RiseInDecibel RiseInTimeDuration UseFileBeatsMarker  XMP Time Struct  Field Name	real Time Struct boolean  Writable rational integer  Writable Time Struct
RiseInDecibel RiseInTimeDuration UseFileBeatsMarker  XMP Time Struct  Field Name	real Time Struct boolean  Writable rational integer  Writable Time Struct boolean

Track string WebStatement string

## XMP Marker Struct

Field Name Writable
----Comment string

CuePointParams CuePointParam Struct+ CuePointType string Duration string Location string Name string Probability real Speaker string StartTime string Target string

#### XMP CuePointParam Struct

Type

Field Name Writable
----Key string
Value string

string

## XMP ProjectLink Struct

Field Name Writable
----Path string
Type string

#### XMP ResampleStretch Struct

Field Name Writable
----Quality string

## XMP TimeScaleStretch Struct

Field Name Writable
----FrameOverlappingPercentage real
FrameSize real
Quality string

#### XMP Track Struct

Field Name Writable -----FrameRate String

Markers Marker Struct+

TrackName string
TrackType string

#### XMP Colorant Struct

Field Name Writable Α integer В integer real Black real Blue integer Cyan real Gray integer Green integer Magenta real Mode string

Red integer
SwatchName string
Tint integer
Type string
Yellow real

#### XMP Dimensions Struct

Field Name Writable
-----H real
Unit string
W real

#### XMP xmpMM Tags

XMP Media Management namespace tags.

IngredientsOriginalDocumentID

These tags belong to the ExifTool XMP-xmpMM family 1 group.

Tag Name Writable \_\_\_\_\_ \_\_\_\_\_ DerivedFrom ResourceRef Struct DerivedFromAlternatePaths string + DerivedFromDocumentID string\_ DerivedFromFilePath string DerivedFromFromPart string DerivedFromInstanceID string DerivedFromLastModifyDate date DerivedFromLastURL string DerivedFromLinkCategory string DerivedFromLinkForm string DerivedFromManager string DerivedFromManagerVariant string\_ DerivedFromManageTo string DerivedFromManageUI string DerivedFromMaskMarkers string\_ DerivedFromOriginalDocumentID string\_ DerivedFromPartMapping string\_ DerivedFromPlacedResolutionUnit string\_ DerivedFromPlacedXResolution string DerivedFromPlacedYResolution string\_ DerivedFromRenditionClass string\_ DerivedFromRenditionParams string DerivedFromToPart string DerivedFromVersionID string\_ DocumentID string ResourceEvent Struct+ History HistoryAction string\_+ HistoryChanged string\_+ HistoryInstanceID string + HistoryParameters string\_+ HistorySoftwareAgent string + HistoryWhen date + Ingredients ResourceRef Struct+ IngredientsAlternatePaths string + IngredientsDocumentID string + IngredientsFilePath string\_+ IngredientsFromPart string + IngredientsInstanceID string + IngredientsLastModifyDate date\_+ IngredientsLastURL string\_+ IngredientsLinkCategory string + IngredientsLinkForm string\_+ IngredientsManager string + IngredientsManagerVariant string + IngredientsManageTo string\_+ string\_+ IngredientsManageUI IngredientsMaskMarkers string +

string\_+

IngredientsPartMapping string\_+ IngredientsPlacedResolutionUnit string + IngredientsPlacedXResolution string + IngredientsPlacedYResolution string + IngredientsRenditionClass string + IngredientsRenditionParams string\_+ IngredientsToPart string\_+ IngredientsVersionID string + InstanceID string LastURL string ManagedFrom ResourceRef Struct  ${\tt ManagedFromAlternatePaths}$ string\_+  ${\tt ManagedFromDocumentID}$ string\_ ManagedFromFilePath string\_ ManagedFromFromPart string\_ ManagedFromInstanceID string\_ ManagedFromLastModifyDate date ManagedFromLastURL string ManagedFromLinkCategory string\_ ManagedFromLinkForm string ManagedFromManager string ManagedFromManagerVariant string\_ ManagedFromManageTo string ManagedFromManageUI string ManagedFromMaskMarkers string ManagedFromOriginalDocumentID string ManagedFromPartMapping string ManagedFromPlacedResolutionUnit string ManagedFromPlacedXResolution string ManagedFromPlacedYResolution string ManagedFromRenditionClass string ManagedFromRenditionParams strina ManagedFromToPart strina ManagedFromVersionID string Manager string ManagerVariant string ManageTo string ManageUI string Manifest. ManifestItem Struct+ ManifestLinkForm string\_+ ManifestPlacedResolutionUnit string\_+ ManifestPlacedXResolution real + ManifestPlacedYResolution real + ManifestReference ResourceRef Struct + ManifestReferenceAlternatePaths string + ManifestReferenceDocumentID string\_+ ManifestReferenceFilePath string + ManifestReferenceFromPart string + ManifestReferenceInstanceID string\_+ ManifestReferenceLastModifyDate date + ManifestReferenceLastURL string + ManifestReferenceLinkCategory string + ManifestReferenceLinkForm string + ManifestReferenceManager string + ManifestReferenceManagerVariant string + ManifestReferenceManageTo string + ManifestReferenceManageUI string + ManifestReferenceMaskMarkers string + ManifestReferenceOriginalDocumentID string + ManifestReferencePartMapping string + ManifestReferencePlacedResolutionUnit string\_+ ManifestReferencePlacedXResolution string\_+ ManifestReferencePlacedYResolution string + ManifestReferenceRenditionClass string\_+ ManifestReferenceRenditionParams string + ManifestReferenceToPart string + string\_+ ManifestReferenceVersionID OriginalDocumentID string PantryItem Struct+ Pantry PantryInstanceID string\_

PreservedFileName string RenditionClass string

RenditionOf ResourceRef Struct

RenditionOfAlternatePaths string + RenditionOfDocumentID string RenditionOfFilePath string\_ RenditionOfFromPart string\_ RenditionOfInstanceID string RenditionOfLastModifyDate date\_ RenditionOfLastURL string\_ RenditionOfLinkCategory string\_ RenditionOfLinkForm string\_ RenditionOfManager string\_ RenditionOfManagerVariant string\_ RenditionOfManageTo string\_ RenditionOfManageUI string\_ RenditionOfMaskMarkers string\_ RenditionOfOriginalDocumentID string\_ RenditionOfPartMapping string\_ RenditionOfPlacedResolutionUnit string\_ RenditionOfPlacedXResolution string RenditionOfPlacedYResolution string\_ RenditionOfRenditionClass string RenditionOfRenditionParams string RenditionOfToPart RenditionOfVersionID RenditionParams SaveID

string string string integer Subject string/+ VersionID string

Versions Version Struct+

VersionsComments string +

VersionsEvent ResourceEvent Struct +

VersionsEventAction string\_+ VersionsEventChanged string + VersionsEventInstanceID string + VersionsEventParameters string\_+ VersionsEventSoftwareAgent string + VersionsEventWhen date + VersionsModifier string + date\_+ VersionsModifyDate string\_+ VersionsVersion

## XMP ResourceRef Struct

RenditionClass

ToPart

VersionID

RenditionParams

Field Name Writable \_\_\_\_\_ \_\_\_\_\_ AlternatePaths string+ Document ID string FilePath string FromPart string InstanceID string LastModifyDate date LastURL string LinkCategory string LinkForm string ManageTo string ManageUI string Manager string ManagerVariant string MaskMarkers string OriginalDocumentID string PartMapping string PlacedResolutionUnit string PlacedXResolution string string PlacedYResolution

string

string

string

string

## XMP ResourceEvent Struct

Field Name Writable
-----Action string
Changed string
InstanceID string
Parameters string
SoftwareAgent string
When date

#### XMP ManifestItem Struct

Field Name Writable
----LinkForm string
PlacedResolutionUnit string
PlacedXResolution real
PlacedYResolution real

Reference ResourceRef Struct

#### XMP PantryItem Struct

This structure must have an InstanceID field, but may also contain any other XMP properties.

Field Name Writable
----InstanceID string

#### XMP Version Struct

Field Name Writable
----Comments string

Event ResourceEvent Struct

Modifier string
ModifyDate date
Version string

#### XMP xmpNote Tags

XMP Note namespace tags.

These tags belong to the ExifTool XMP-xmpNote family 1 group.

Tag Name Writable
----HasExtendedXMP string\*

## XMP xmpPLUS Tags

XMP Picture Licensing Universal System (PLUS) tags as written by some older Adobe applications. See PLUS XMP Tags for the current PLUS tags.

These tags belong to the ExifTool XMP-xmpPLUS family 1 group.

Tag Name Writable
----CreditLineReq boolean/
ReuseAllowed boolean/

## XMP xmpRights Tags

XMP Rights Management namespace tags.

These tags belong to the ExifTool XMP-xmpRights family 1 group.

Tag Name Writable

Certificate string
Marked boolean
Owner string+
UsageTerms lang-alt
WebStatement string

#### XMP xmpTPg Tags

XMP Paged-Text namespace tags.

These tags belong to the ExifTool XMP-xmpTPg family 1 group.

Tag Name Writable Colorants Colorant Struct+ ColorantA integer\_+ ColorantB integer + ColorantBlack real\_+ ColorantBlue integer\_+ ColorantCyan real + integer\_+ ColorantGray ColorantGreen integer + ColorantL real + ColorantMagenta real + ColorantMode string + ColorantRed integer + ColorantSwatchName string + ColorantTint integer + string\_+ ColorantType ColorantYellow real + Fonts Font Struct+ ChildFontFiles string + FontComposite boolean + FontFace string + FontFamily string + FontFileName string\_+ FontName string + FontType string + FontVersion string\_+ HasVisibleOverprint boolean HasVisibleTransparency boolean Dimensions Struct MaxPageSize MaxPageSizeH real MaxPageSizeUnit string MaxPageSizeW real\_ **NPages** integer PlateNames string+ SwatchGroup Struct+ SwatchGroups SwatchGroupsColorants Colorant Struct\_+ SwatchColorantA integer\_+ SwatchColorantB integer\_+ real + SwatchColorantBlack integer\_+ SwatchColorantBlue SwatchColorantCyan real + SwatchColorantGray integer + SwatchColorantGreen integer + SwatchColorantL real\_+ SwatchColorantMagenta real\_+ string\_+ SwatchColorantMode SwatchColorantRed integer\_+ SwatchColorantSwatchName string\_+ SwatchColorantTint integer\_+ SwatchColorantType string\_+ SwatchColorantYellow real\_+ SwatchGroupName string\_+ SwatchGroupType integer\_+

Writable
string+
boolean
string

#### XMP SwatchGroup Struct

Field Name	Writable
Colorants	Colorant Struct+
GroupName	string
GroupType	integer

#### XMP XML Tags

Tag ID	Tag Name	Writable
'dc'	dc	XMP dc
'lastUpdate'	LastUpdate	no

#### XMP SVG Tags

SVG (Scalable Vector Graphics) image tags. By default, only the top-level SVG and Metadata tags are extracted from these images, but all graphics tags may be extracted by setting the Unknown option to 2 (-U on the command line). The SVG tags are not part of XMP as such, but are included with the XMP module for convenience. (see <a href="http://www.w3.org/TR/SVG11/">http://www.w3.org/TR/SVG11/</a>)

These tags belong to the ExifTool XMP-svg family 1 group.

Tag ID	Tag Name	Writable
'height'	ImageHeight	no
'id'	ID	no
'metadataId'	MetadataID	no
'version'	SVGVersion	no
'width'	ImageWidth	no

#### GPS Tags

These GPS tags are part of the EXIF standard, and are stored in a separate IFD within the EXIF information.

ExifTool is very flexible about the input format when writing lat/long coordinates, and will accept from 1 to 3 floating point numbers (for decimal degrees, degrees and minutes, or degrees, minutes and seconds) separated by just about anything, and will format them properly according to the EXIF specification.

Some GPS tags have values which are fixed-length strings. For these, the indicated string lengths include a null terminator which is added automatically by ExifTool. Remember that the descriptive values are used when writing (eg. 'Above Sea Level', not '0') unless the print conversion is disabled (with '-n' on the command line or the PrintConv option in the API, or by suffixing the tag name with a "#" character).

When adding GPS information to an image, it is important to set all of the following tags: GPSLatitude, GPSLatitudeRef, GPSLongitude, GPSLongitudeRef, and GPSAltitude and GPSAltitudeRef if the altitude is known. ExifTool will write the required GPSVersionID tag automatically if new a GPS IFD is added to an image.

Tag ID	Tag Name	Writable

0x0000	GPSVersionID	int8u[4]:
$0 \times 0001$	GPSLatitudeRef	string[2]
$0 \times 0002$	GPSLatitude	rational64u[3]
0x0003	GPSLongitudeRef	string[2]
$0 \times 0004$	GPSLongitude	rational64u[3]
$0 \times 0005$	GPSAltitudeRef	int8u
0x0006	GPSAltitude	rational64u
0x0007	GPSTimeStamp	rational64u[3]
0x0008	GPSSatellites	string
0x0009	GPSStatus	string[2]
0x000a	GPSMeasureMode	string[2]
0x000b	GPSDOP	rational64u
0x000c	GPSSpeedRef	string[2]
0x000d	GPSSpeed	rational64u
0x000e	GPSTrackRef	string[2]
0x000f	GPSTrack	rational64u
$0 \times 0010$	GPSImgDirectionRef	string[2]
$0 \times 0011$	GPSImgDirection	rational64u
$0 \times 0012$	GPSMapDatum	string
$0 \times 0013$	GPSDestLatitudeRef	string[2]
$0 \times 0014$	GPSDestLatitude	rational64u[3]
$0 \times 0015$	GPSDestLongitudeRef	string[2]
$0 \times 0016$	GPSDestLongitude	rational64u[3]
$0 \times 0017$	GPSDestBearingRef	string[2]
$0 \times 0018$	GPSDestBearing	rational64u
$0 \times 0019$	GPSDestDistanceRef	string[2]
0x001a	GPSDestDistance	rational64u
$0 \times 001 b$	GPSProcessingMethod	undef
$0 \times 001c$	GPSAreaInformation	undef
0x001d	GPSDateStamp	string[11]
0x001e	GPSDifferential	int16u
0x001f	GPSHPositioningError	rational64u

#### GeoTiff Tags

ExifTool extracts the following tags from GeoTIFF images. See

<https://web.archive.org/web/20070820121549/http://www.remotesensing.org/geotiff/s
pec/geotiffhome.html>

for the complete  ${\tt GeoTIFF}$  specification. Also included in the table below are  ${\tt ChartTIFF}$  tags (see

<https://web.archive.org/web/20020828193928/http://www.charttiff.com/whitepapers.s
html>).

GeoTIFF tags are not writable individually, but they may be copied en mass via the block tags GeoTiffDirectory, GeoTiffDoubleParams and GeoTiffAsciiParams.

Tag ID	Tag Name	Writable
$0 \times 0001$	GeoTiffVersion	no
$0 \times 0400$	GTModelType	no
$0 \times 0401$	GTRasterType	no
$0 \times 0402$	GTCitation	no
0x0800	GeographicType	no
0x0801	GeogCitation	no
$0 \times 0802$	GeogGeodeticDatum	no
0x0803	GeogPrimeMeridian	no
$0 \times 0804$	GeogLinearUnits	no
$0 \times 0805$	GeogLinearUnitSize	no
0x0806	GeogAngularUnits	no
$0 \times 0807$	GeogAngularUnitSize	no
0x0808	GeogEllipsoid	no
0x0809	GeogSemiMajorAxis	no
0x080a	GeogSemiMinorAxis	no
0x080b	GeogInvFlattening	no
0x080c	GeogAzimuthUnits	no
0x080d	GeogPrimeMeridianLong	no
0x080e	GeogToWGS84	no
0x0c00	ProjectedCSType	no
0x0c01	PCSCitation	no
0x0c02	Projection	no
0x0c03	ProjCoordTrans	no

0x0c04	ProjLinearUnits	no
0x0c05	ProjLinearUnitSize	no
0x0c06	ProjStdParallel1	no
0x0c07	ProjStdParallel2	no
0x0c08	ProjNatOriginLong	no
0x0c09	ProjNatOriginLat	no
0x0c0a	ProjFalseEasting	no
0x0c0b	ProjFalseNorthing	no
0x0c0c	ProjFalseOriginLong	no
0x0c0d	ProjFalseOriginLat	no
0x0c0e	ProjFalseOriginEasting	no
0x0c0f	ProjFalseOriginNorthing	no
0x0c10	ProjCenterLong	no
0x0c11	ProjCenterLat	no
0x0c12	ProjCenterEasting	no
0x0c13	ProjCenterNorthing	no
0x0c14	ProjScaleAtNatOrigin	no
0x0c15	ProjScaleAtCenter	no
0x0c16	ProjAzimuthAngle	no
0x0c17	ProjStraightVertPoleLong	no
0x0c18	ProjRectifiedGridAngle	no
0x1000	VerticalCSType	no
0x1001	VerticalCitation	no
0x1002	VerticalDatum	no
0x1003	VerticalUnits	no
0xb799	ChartFormat	no
0xb79a	ChartSource	no
0xb79b	ChartSourceEdition	no
0xb79c	ChartSourceDate	no
0xb79d	ChartCorrDate	no
0xb79e	ChartCountryOrigin	no
0xb79f	ChartRasterEdition	no
0xb7a0	ChartSoundingDatum	no
0xb7a1	ChartDepthUnits	no
0xb7a2	ChartMagVar	no
0xb7a3	ChartMagVarYear	no
0xb7a4	ChartMagVarAnnChange	no
0xb7a5	ChartWGSNSShift	no
0xb7a7	InsetNWPixelX	no
0xb7a8	InsetNWPixelY	no
0xb7a9	ChartContourInterval	no

#### PLUS Tags

## PLUS XMP Tags

PLUS (Picture Licensing Universal System) License Data Format 2.0.1 XMP tags. Note that all controlled-vocabulary tags in this table (ie. tags with a fixed set of values) have raw values which begin with "http://ns.useplus.org/ldf/vocab/", but to reduce clutter this prefix has been removed from the values shown below, and from the values read and written with the -n option. See <a href="http://ns.useplus.org/">http://ns.useplus.org/</a> for the complete specification.

These tags belong to the ExifTool XMP-plus family 1 group.

Tag Name	Writable
AdultContentWarning	string
CopyrightOwner	CopyrightOwner Struct+
CopyrightOwnerID	string_+
CopyrightOwnerName	string_+
CopyrightOwnerImageID	string
CopyrightRegistrationNumber	string
CopyrightStatus	string
CreditLineRequired	string
Custom1	lang-alt+
Custom10	lang-alt+
Custom2	lang-alt+
Custom3	lang-alt+
Custom4	lang-alt+

Custom5 lang-alt+ Custom6 lang-alt+ Custom7 lang-alt+ Custom8 lang-alt+ Custom9 lang-alt+ DataMining string EndUser EndUser Struct+ EndUserID string\_+ EndUserName string\_+ FileNameAsDelivered string FirstPublicationDate date string+ ImageAlterationConstraints ImageCreator ImageCreator Struct+ string\_+ ImageCreatorID ImageCreatorName string\_+ ImageCreatorImageID string ImageDuplicationConstraints string ImageFileConstraints string+ ImageFileFormatAsDelivered string ImageFileSizeAsDelivered string ImageSupplier ImageSupplier Struct+ ImageSupplierImageID string ImageSupplierID string + ImageSupplierName string + ImageType string Licensee Licensee Struct+ LicenseeImageID string LicenseeImageNotes lang-alt LicenseeID string + LicenseeName string + LicenseEndDate date LicenseeProjectReference string+ LicenseeTransactionID string+ LicenseID string LicenseStartDate date LicenseTransactionDate date Licensor Struct+ Licensor LicensorImageID string LicensorCity string + LicensorCountry string\_+ LicensorEmail string + LicensorExtendedAddress string + LicensorID string + LicensorName string + LicensorPostalCode string + LicensorRegion string + LicensorStreetAddress string + LicensorTelephone1 string + LicensorTelephone2 string\_+ LicensorTelephoneType1 string + LicensorTelephoneType2 string + LicensorURL string + LicensorNotes lang-alt LicensorTransactionID string+ MediaConstraints lang-alt MediaSummaryCode string MinorModelAgeDisclosure string ModelReleaseID string+ ModelReleaseStatus string OtherConditions lang-alt OtherConstraints lang-alt OtherImageInfo lang-alt OtherLicenseDocuments string+ OtherLicenseInfo lang-alt OtherLicenseRequirements lang-alt ProductOrServiceConstraints lang-alt PropertyReleaseID string+ PropertyReleaseStatus string RegionConstraints lang-alt Reuse string

TermsAndConditionsText	lang-alt
TermsAndConditionsURL	string
PLUSVersion	string

## XMP CopyrightOwner Struct

Field Name	Writable
CopyrightOwnerID	string
CopyrightOwnerName	string

#### XMP EndUser Struct

Field Name	Writable
EndUserID	string
EndUserName	string

#### XMP ImageCreator Struct

Field Name	Writable
ImageCreatorID	string
ImageCreatorName	string

## XMP ImageSupplier Struct

Field Name	Writable
ImageSupplierID	string
ImageSupplierName	string

#### XMP Licensee Struct

Field Name	Writable
LicenseeID LicenseeName	string string
	5

## XMP Licensor Struct

Field Name	Writable
LicensorCity	string
LicensorCountry	string
LicensorEmail	string
LicensorExtendedAddress	string
LicensorID	string
LicensorName	string
LicensorPostalCode	string
LicensorRegion	string
LicensorStreetAddress	string
LicensorTelephone1	string
LicensorTelephone2	string
LicensorTelephoneTypel	string
LicensorTelephoneType2	string
LicensorURL	string

#### ICC\_Profile Tags

ICC profile information is used in many different file types including JPEG, TIFF, PDF, PostScript, Photoshop, PNG, MIFF, PICT, QuickTime, XCF and some RAW formats. While the tags listed below are not individually writable, the entire profile itself can be accessed via the extra 'ICC\_Profile' tag, but this tag is neither extracted nor written unless specified explicitly. See <a href="http://www.color.org/icc\_specs2.xalter">http://www.color.org/icc\_specs2.xalter</a> for the official ICC specification.

Tag ID	Tag Name	Writable
'A2B0'	AToB0	no

```
'A2B1'
         AToB1
                                                 no
'A2B2'
         ATOB2
                                                 no
'A2B3'
        AToB3
                                                 no
'A2M0'
        AToM0
                                                 no
'B2A0'
         BToA0
                                                 no
'B2A1'
         BToA1
                                                 no
'B2A2'
         BToA2
                                                 no
'B2A3'
         BToA3
                                                 no
'B2D0'
         BToD0
'B2D1'
         BToD1
'B2D2'
         BToD2
                                                 no
'B2D3'
         BToD3
                                                 no
'CxF '
         CXF
                                                 no
'D2B0'
         DToB0
                                                 no
'D2B1'
         DToB1
                                                 no
'D2B2'
         DToB2
                                                 no
'D2B3'
         DToB3
                                                 no
'Header' ProfileHeader
                                                 ICC Profile Header
'M2A0'
         MToA0
                                                 no
'M2B0'
         MToB0
'M2B1'
         MToB1
'M2B2'
         MToB2
'M2B3'
         MToB3
                                                 no
'M2S0'
         MToS0
                                                 no
'M2S1'
         MToS1
                                                 no
'M2S2'
         MToS2
                                                 no
'M2S3'
         MToS3
                                                 no
'MS00'
         WCSProfiles
                                                 no
'bAB0'
         BRDFAToB0
                                                 no
'bAB1'
         BRDFAToB1
                                                 no
'bAB2'
         BRDFAToB2
                                                 no
'bAB3'
         BRDFAToB3
                                                 no
'bBA0'
         BRDFBToA0
                                                 no
'bBA1'
         BRDFBToA1
'bBA2'
         BRDFBToA2
                                                 no
'bBA3'
         BRDFBToA3
                                                 no
'bBD0'
         BRDFBToD0
                                                 no
'bBD1'
         BRDFBToD1
                                                 no
'bBD2'
         BRDFBToD2
                                                 no
'bBD3'
         BRDFBToD3
                                                 no
'bDB0'
         BRDFDToB0
                                                 no
'bDB1'
         BRDFDToB1
                                                 nο
'bDB2'
         BRDFDToB2
                                                 no
'bDB3'
         BRDFDToB3
                                                 no
'bMB0'
         BRDFMToB0
                                                 no
'bMB1'
         BRDFMToB1
'bMB2'
         BRDFMToB2
                                                 no
'bMB3'
         BRDFMToB3
                                                 no
'bMS0'
         BRDFMToS0
                                                 no
'bMS1'
         BRDFMToS1
                                                 no
'bMS2'
         BRDFMToS2
                                                 no
'bMS3'
         BRDFMToS3
                                                 no
'bTRC'
         BlueTRC
                                                 no
'bxyz'
         BlueMatrixColumn
                                                 no
'bcp0'
         BRDFColorimetricParam0
                                                 no
'bcp1'
         BRDFColorimetricParam1
                                                 no
'bcp2'
         BRDFColorimetricParam2
                                                 nο
'bcp3'
         BRDFColorimetricParam3
'bfd '
         UCRBG
                                                 no
'bkpt'
         MediaBlackPoint
                                                 no
'bsp0'
         BRDFSpectralParam0
                                                 no
'bsp1'
         BRDFSpectralParam1
                                                 no
'bsp2'
         BRDFSpectralParam2
                                                 no
'bsp3'
         BRDFSpectralParam3
                                                 no
'c2sp'
         CustomToStandardPcc
                                                 no
'calt'
         CalibrationDateTime
                                                 no
'cept'
         ColorEncodingParams
                                                 no
'chad'
         ChromaticAdaptation
                                                 no
         Chromaticity
                                                 ICC Profile Chromaticity
'chrm'
'cicp'
         ColorRepresentation
                                                 ICC_Profile ColorRep
```

	ExilTool 13.24 Tag Names	
'ciis'	ColorimetricIntentImageState	no
'clio'	ColorantInfoOut	no
'cloo'	ColorantOrderOut	no
'clot'	ColorantTableOut	no
'clro'	ColorantOrder	no
'clrt'	ColorantTable	<pre>ICC_Profile ColorantTable</pre>
'cprt'	ProfileCopyright	no
'crdi'	CRDInfo	no
'csnm'	ColorSpaceName	no
'dAB0'	DirectionalAToB0	no
'dAB1'	DirectionalAToB1	no
'dAB2'	DirectionalAToB2	no
'dAB3'	DirectionalAToB3	no
'dBA0'	DirectionalBToA0	no
'dBA1'	DirectionalBToA1	no
'dBA2'	DirectionalBToA2	no
'dBA3'	DirectionalBToA3	no
'dBD0'	DirectionalBToD0	no
'dBD1'	DirectionalBToD1	no
'dBD2'	DirectionalBToD2	no
'dBD3'	DirectionalBToD3	no
'dDB0'	DirectionalDToB0	no
'dDB1'	DirectionalDToB1	no
'dDB2'	DirectionalDToB2	no
'dDB3'	DirectionalDToB3	no
'desc'	ProfileDescription	no
'devs'	DeviceSettings	no
'dmdd'	DeviceModelDesc	no
'dmnd'	DeviceMfgDesc	no
'dscm'	ProfileDescriptionML	no
'fpce'	FocalPlaneColorimetryEstimates	no
'gTRC'	GreenTRC	no
'gXYZ'	GreenMatrixColumn	no
'gamt'	Gamut	no
'gdb0'	GamutBoundaryDescription0	no
'gdb1'	GamutBoundaryDescription1	no
'gdb2' 'gdb3'	GamutBoundaryDescription2 GamutBoundaryDescription3	no
'hdgm'	HDGainMapInfo	no
'kTRC'	GrayTRC	no
'lumi'	Luminance	no no
'mcta'	MultiplexTypeArray	no
'mdv '	MultiplexDefaultValues	no
'meas'	Measurement	ICC Profile Measurement
'meta'	Metadata	ICC_Profile Metadata
'miin'	MeasurementInputInfo	no
'minf'	MeasurementInfo	no
'mmod'	MakeAndModel	no
'ncl2'	NamedColor2	no
'ncol'	NamedColor	no
'ndin'	NativeDisplayInfo	no
'nmcl'	NamedColor	no
'pre0'	Preview0	no
'pre1'	Preview1	no
'pre2'	Preview2	no
'ps2i'	PS2RenderingIntent	no
'ps2s'	PostScript2CSA	no
'psd0'	PostScript2CRD0	no
'psd1'	PostScript2CRD1	no
'psd2'	PostScript2CRD2	no
'psd3'	PostScript2CRD3	no
'pseq'	ProfileSequenceDesc	no
'psid'	ProfileSequenceIdentifier	no
'psin'	ProfileSequenceInfo	no
'psvm'	PS2CRDVMSize	no
'rTRC'	RedTRC	no
'rXYZ'	RedMatrixColumn	no
'resp'	OutputResponse	no
'rfnm'	ReferenceName	no
'rhoc'	ReflectionHardcopyOrigColorimetry	no

'rig0'	PerceptualRenderingIntentGamut	no
'rig2'	SaturationRenderingIntentGamut	no
'rpoc'	ReflectionPrintOutputColorimetry	no
's2cp'	StandardToCustomPcc	no
'sape'	SceneAppearanceEstimates	no
'scoe'	SceneColorimetryEstimates	no
'scrd'	ScreeningDesc	no
'scrn'	Screening	no
'smap'	SurfaceMap	no
'svcn'	SpectralViewingConditions	no
'swpt'	SpectralWhitePoint	no
'targ'	CharTarget	no
'tech'	Technology	no
'vcgt'	VideoCardGamma	no
'view'	ViewingConditions	ICC_Profile ViewingConditions
'vued'	ViewingCondDesc	no
'wtpt'	MediaWhitePoint	no

# ICC Profile Header Tags

Index1	Tag Name	Writable
4	ProfileCMMType	no
8	ProfileVersion	no
12	ProfileClass	no
16	ColorSpaceData	no
20	ProfileConnectionSpace	no
24	ProfileDateTime	no
36	ProfileFileSignature	no
40	PrimaryPlatform	no
44	CMMFlags	no
48	DeviceManufacturer	no
52	DeviceModel	no
56	DeviceAttributes	no
64	RenderingIntent	no
68	ConnectionSpaceIlluminant	no
80	ProfileCreator	no
84	ProfileID	no

# ICC Profile Chromaticity Tags

Index1	Tag Name	Writable
8	ChromaticityChannels	no
10	ChromaticityColorant	no
12	ChromaticityChannel1	no
20	ChromaticityChannel2	no
28	ChromaticityChannel3	no
36	ChromaticityChannel4	no

# ICC Profile ColorRep Tags

Index1	Tag Name	Writable
8	ColorPrimaries	no
9	TransferCharacteristics	no
10	MatrixCoefficients	no
11	VideoFullRangeFlag	no

# ICC Profile ColorantTable Tags

Index1	Tag Name	Writable
8	ColorantCount	no
12	Colorant1Name	no
44	Colorant1Coordinates	no
50	Colorant2Name	no
82	Colorant2Coordinates	no
88	Colorant3Name	no
120	Colorant3Coordinates	no

# ICC Profile Measurement Tags

Index1	Tag Name	Writable
8	MeasurementObserver	no
12	MeasurementBacking	no
24	MeasurementGeometry	no
28	MeasurementFlare	no
32	MeasurementIlluminant	no

### ICC Profile Metadata Tags

Only these few tags have been pre-defined, but ExifTool will extract any Metadata tags that exist.

Tag Name	Writable
CreatorApp	no
ManufacturerName	no
MediaColor	no
MediaWeight	no

#### ICC Profile ViewingConditions Tags

Index1	Tag Name	Writable
8	ViewingCondIlluminant	no
20	ViewingCondSurround	no
32	ViewingCondIlluminantType	no

#### PrintIM Tags

The format of the PrintIM information is known, however no PrintIM tags have been decoded. Use the Unknown (-u) option to extract PrintIM information.

Tag ID	Tag Name	Writable
'PrintIMVersion'	Print TMVersion	no

### Photoshop Tags

Photoshop tags are found in PSD and PSB files, as well as inside embedded Photoshop information in many other file types (JPEG, TIFF, PDF, PNG to name a few).

Many Photoshop tags are marked as Unknown (indicated by a question mark after the tag name) because the information they provide is not very useful under normal circumstances. These unknown tags are not extracted unless the Unknown (-u) option is used. See <a href="http://www.adobe.com/devnet-apps/photoshop/fileformatashtml/">http://www.adobe.com/devnet-apps/photoshop/fileformatashtml/</a> for the official specification

Photoshop path tags (Tag ID's 0x7d0 to 0xbb5) are not defined by default, but a config file included in the full ExifTool distribution (config\_files/photoshop\_paths.config) contains the tag definitions to allow access to this information.

Tag ID	Tag Name	Writable
0x03e8	Photoshop2Info?	no
0x03e9	MacintoshPrintInfo?	no
0x03ea	XMLData?	no
0x03eb	Photoshop2ColorTable?	no
0x03ed	ResolutionInfo	Photoshop Resolution
0x03ee	AlphaChannelsNames	no
0x03ef	DisplayInfo?	no
0x03f0	PStringCaption?	no
0x03f1	BorderInformation?	no
0x03f2	BackgroundColor?	no
0x03f3	PrintFlags?	no

```
0 \times 03f4
       BW_HalftoningInfo?
                                               no
0x03f5 ColorHalftoningInfo?
                                               nο
0x03f6 DuotoneHalftoningInfo?
                                              no
0x03f7 BW TransferFunc?
                                              no
0x03f8 ColorTransferFuncs?
0x03f9 DuotoneTransferFuncs?
0x03fa DuotoneImageInfo?
0x03fb EffectiveBW?
0x03fc ObsoletePhotoshopTag1?
0x03fd EPSOptions?
                                              no
0x03fe QuickMaskInfo?
                                              no
0x03ff ObsoletePhotoshopTag2?
                                              no
0x0400 TargetLayerID?
                                              no
0x0401 WorkingPath?
                                              no
0x0402 LayersGroupInfo?
                                              no
0 \times 0403
       ObsoletePhotoshopTag3?
                                              no
0 \times 0404
        IPTCData
                                               TPTC
       RawImageMode?
0 \times 0405
                                               no
       JPEG_Quality
0 \times 0406
                                               Photoshop JPEG_Quality
0 \times 0408
        GridGuidesInfo?
0 \times 0409
        PhotoshopBGRThumbnail
                                               undef!
0x040a
        CopyrightFlag
                                              int8u
       URL
0 \times 040 b
                                              string
       PhotoshopThumbnail
0x040c
                                              undef!
0x040d GlobalAngle
                                              int32u
0x040e ColorSamplersResource?
                                              no
0x040f ICC Profile
                                              ICC Profile
0x0410 Watermark?
                                              no
0x0411 ICC Untagged?
0x0412 EffectsVisible?
                                              no
0x0413 SpotHalftone?
0x0414 IDsBaseValue?
0x0415 UnicodeAlphaNames?
no
0x0417 TransparentIndex?
                                              no
0x0419 GlobalAltitude
                                              int32u
0x041a SliceInfo
                                              Photoshop SliceInfo
0x041b WorkflowURL
                                               no
0x041c JumpToXPEP?
                                              nο
0x041d AlphaIdentifiers?
                                              no
0x041e URL_List
                                               no+
0 \times 0421
                                               Photoshop VersionInfo
        VersionInfo
0 \times 0422
        EXIFInfo
                                               EXIF
0 \times 0423
        ExifInfo2?
                                               no
0 \times 0424
        XMP
                                               XMP
0 \times 0425
        IPTCDigest
                                               string!
       PrintScaleInfo
                                               Photoshop PrintScaleInfo
0 \times 0426
0 \times 0428
       PixelInfo
                                              Photoshop PixelInfo
0x0429 LayerComps?
0x042a AlternateDuotoneColors?
                                              no
       AlternateSpotColors?
0 \times 0.42 b
                                              nο
0x042d LayerSelectionIDs?
                                              nο
0x042e HDRToningInfo?
                                              no
0x042f PrintInfo?
                                              no
0x0430 LayerGroupsEnabledID?
0x0431 ColorSamplersResource2?
0x0432 MeasurementScale?
0 \times 0433
       TimelineInfo?
                                              no
0x0434 SheetDisclosure?
0x0435 ChannelOptions
                                              Photoshop ChannelOptions
0x0436 OnionSkins?
                                              no
0x0438 CountInfo?
                                              no
0x043a PrintInfo2?
                                              no
0x043b PrintStyle?
                                              no
0x043c MacintoshNSPrintInfo?
                                              no
       WindowsDEVMODE?
0 \times 043d
                                               no
       AutoSaveFilePath?
0 \times 043e
                                               no
0 \times 043f
        AutoSaveFormat?
                                               no
0 \times 0440
        PathSelectionState?
0x0bb7
        ClippingPathName
```

### -- ExifTool 13.24 Tag Names --

0x0bb8	OriginPathInfo?	no
0x1b58	<pre>ImageReadyVariables?</pre>	no
0x1b59	ImageReadyDataSets?	no
0x1f40	LightroomWorkflow?	no
0x2710	PrintFlagsInfo?	no

### Photoshop Resolution Tags

Index2	Tag Name	Writable
0	XResolution	int32u
2	DisplayedUnitsX	int16u
4	YResolution	int32u
6	DisplayedUnitsY	int16u

### Photoshop JPEG Quality Tags

Index2	Tag Name	Writable
0	PhotoshopQuality	int16s
1	PhotoshopFormat	no
2	ProgressiveScans	no

### Photoshop SliceInfo Tags

Index	1 Tag Name	Writable
20	SlicesGroupName	no
24	NumSlices	no

### Photoshop VersionInfo Tags

Index1	Tag Name	Writable
4	HasRealMergedData	no
5	WriterName	no
9	ReaderName	no

# Photoshop PrintScaleInfo Tags

Index1	Tag Name	Writable
0	PrintStyle	no
2	PrintPosition	no
10	PrintScale	no

### Photoshop PixelInfo Tags

Index1	Tag Name	Writable
4	PixelAspectRatio	no

### Photoshop ChannelOptions Tags

These tags relate only to the appearance of a channel.

Index1	Tag Name	Writable
0	ChannelColorSpace	no
2	ChannelColorData	no
11	ChannelOpacity	no
12	ChannelColorIndicates	no

# Photoshop DocumentData Tags

Tag ID	Tag Name	Writable
'Layr'	Layers	Photoshop Layers
'Lr16'	Layers	Photoshop Layers

### Photoshop Layers Tags

Tags extracted from Photoshop layer information.

Tag ID	Tag Name	Writable
'_xbnd'	LayerBlendModes	no+
'_xcnt'	LayerCount	no
'_xnam'	LayerNames	no+
'_xopc'	LayerOpacities	no+
'_xrct'	LayerRectangles	no+
'_xvis'	LayerVisible	no+
'lclr'	LayerColors	no+
'lsct'	LayerSections	no+
'luni'	LayerUnicodeNames	no+
'lyid'	LayerIDs?	no+
'shmd'	LayerModifyDates	no+

# Photoshop Header Tags

This information is found in the PSD file header.

Index2	Tag Name	Writable
6	NumChannels	no
7	ImageHeight	no
9	ImageWidth	no
11	BitDepth	no
12	ColorMode	no

### Photoshop ImageData Tags

Index1	Tag Name	Writable
0	Compression	no

### Apple Tags

Tags extracted from the maker notes of iPhone images.

Tag ID	Tag Name	Writable
Tag ID 0x0001 0x0002 0x0003 0x0004 0x0005 0x0006 0x0007 0x0008 0x0000 0x0000 0x0001 0x0011 0x0014 0x0015 0x0017 0x0019 0x001d 0x001d 0x001f 0x0020 0x0021 0x0021	 MakerNoteVersion	Writable int32s no Apple RunTime int32s int32s int32s int32s rational64s[3] int32s string rational64s[2] int32s string int32s string int32s string rational64s int32s string rational64s int32s
0x0023 0x0025 0x0026 0x0027 0x002b 0x002d 0x002e	AFPerformance SceneFlags? SignalToNoiseRatioType? SignalToNoiseRatio PhotoIdentifier ColorTemperature CameraType	<pre>int32s[2] int32s int32s rational64s string int32s int32s</pre>

0x002f	FocusPosition	int32s
$0 \times 0030$	HDRGain	rational64s
0x0038	AFMeasuredDepth	int32s
0x003d	AFConfidence	int32s
0x003e	ColorCorrectionMatrix?	no
0x003f	GreenGhostMitigationStatus?	int32s
$0 \times 0040$	SemanticStyle	no
$0 \times 0041$	SemanticStyleRenderingVer	no
$0 \times 0042$	SemanticStylePreset	no
0x004e	Apple_0x004e?	no
0x004f	Apple_0x004f?	no

### Apple RunTime Tags

This PLIST-format information contains the elements of a CMTime structure representing the amount of time the phone has been running since the last boot, not including standby time.

Tag ID	Tag Name	Writable
'epoch'	RunTimeEpoch	no
'flags'	RunTimeFlags	no
'timescale'	RunTimeScale	no
'value'	RunTimeValue	no

### Canon Tags

Tags		
Tag ID	Tag Name	Writable
0x0001	CanonCameraSettings	Canon CameraSettings
$0 \times 0002$	CanonFocalLength	Canon FocalLength
0x0003	CanonFlashInfo?	no
$0 \times 0004$	CanonShotInfo	Canon ShotInfo
$0 \times 0005$	CanonPanorama	Canon Panorama
0x0006	CanonImageType	string
$0 \times 0007$	CanonFirmwareVersion	string
0x0008	FileNumber	int32u
$0 \times 0009$	OwnerName	string
0x000a	UnknownD30	Canon UnknownD30
0x000c	SerialNumber	int32u
0x000d	CanonCameraInfolD	Canon CameraInfolD
	CanonCameraInfo1DmkII	Canon CameraInfolDmkII
	CanonCameraInfo1DmkIIN	Canon CameraInfolDmkIIN
	CanonCameraInfo1DmkIII	Canon CameraInfolDmkIII
	CanonCameraInfolDmkIV	Canon CameraInfo1DmkIV
	CanonCameraInfo1DX	Canon CameraInfo1DX
	CanonCameraInfo5D	Canon CameraInfo5D
	CanonCameraInfo5DmkII	Canon CameraInfo5DmkII
	CanonCameraInfo5DmkIII	Canon CameraInfo5DmkIII
	CanonCameraInfo6D	Canon CameraInfo6D
	CanonCameraInfo7D	Canon CameraInfo7D
	CanonCameraInfo40D	Canon CameraInfo40D
	CanonCameraInfo50D	Canon CameraInfo50D
	CanonCameraInfo60D	Canon CameraInfo60D
	CanonCameraInfo70D	Canon CameraInfo70D
	CanonCameraInfo80D	Canon CameraInfo80D
	CanonCameraInfo450D	Canon CameraInfo450D
	CanonCameraInfo500D	Canon CameraInfo500D
	CanonCameraInfo550D	Canon CameraInfo550D
	CanonCameraInfo600D	Canon CameraInfo600D
	CanonCameraInfo650D	Canon CameraInfo650D
	CanonCameraInfo700D	Canon CameraInfo650D
	CanonCameraInfo750D	Canon CameraInfo750D
	CanonCameraInfo760D	Canon CameraInfo750D
	CanonCameraInfo1000D	Canon CameraInfo1000D
	CanonCameraInfo1100D	Canon CameraInfo600D
	CanonCameraInfo1200D	Canon CameraInfo60D
	CanonCameraInfoR6	Canon CameraInfoR6
	CanonCameraInfoR6m2	Canon CameraInfoR6m2
	CanonCameraInfoG5XII	Canon CameraInfoG5XII
	CanonCameraInfoPowerShot	Canon CameraInfoPowerShot

	ExifTool 13.24 Tag Names -	
	CanonCameraInfoPowerShot2	Canon CameraInfoPowerShot2
	CanonCameraInfoUnknown32	Canon CameraInfoUnknown32
	CanonCameraInfoUnknown16	Canon CameraInfoUnknown16
	CanonCameraInfoUnknown	Canon CameraInfoUnknown
0x000e	CanonFileLength	int32u
0x000f	CustomFunctions1D	CanonCustom Functions1D
	CustomFunctions5D	CanonCustom Functions5D
	CustomFunctions10D CustomFunctions20D	CanonCustom Functions10D CanonCustom Functions20D
	CustomFunctions30D	CanonCustom Functions30D
	CustomFunctions350D	CanonCustom Functions350D
	CustomFunctions400D	CanonCustom Functions400D
	CustomFunctionsD30	CanonCustom FunctionsD30
	CustomFunctionsD60	CanonCustom FunctionsD30
	CustomFunctionsUnknown	CanonCustom FuncsUnknown
$0 \times 0010$	CanonModelID	int32u
0x0011	MovieInfo	Canon MovieInfo
$0 \times 0012$	CanonAFInfo	Canon AFInfo
0x0013 0x0015	ThumbnailImageValidArea SerialNumberFormat	<pre>int16u[4] int32u</pre>
0x0013 0x001a	SuperMacro	int16u
0x001a	DateStampMode	int16u
0x001d	MyColors	Canon MyColors
0x001e	FirmwareRevision	int32u
$0 \times 0023$	Categories	int32u[2]
$0 \times 0024$	FaceDetect1	Canon FaceDetect1
$0 \times 0025$	FaceDetect2	Canon FaceDetect2
0x0026	CanonAFInfo2	Canon AFInfo2
$0 \times 0027$	ContrastInfo	Canon ContrastInfo
0x0028 0x0029	ImageUniqueID WBInfo	int8u Canon WBInfo
0x0029 0x002f	FaceDetect3	Canon FaceDetect3
0x0035	TimeInfo	Canon TimeInfo
0x0038	BatteryType	undef
0x003c	AFInfo3	Canon AFInfo2
0x0081	RawDataOffset	no
$0 \times 0082$	RawDataLength	no
0x0083	OriginalDecisionDataOffset	int32u*
$0 \times 0083$ $0 \times 0090$	CustomFunctions1D	CanonCustom Functions1D
0x0083 0x0090 0x0091	CustomFunctions1D PersonalFunctions	CanonCustom Functions1D CanonCustom PersonalFuncs
0x0083 0x0090 0x0091 0x0092	CustomFunctions1D PersonalFunctions PersonalFunctionValues	CanonCustom Functions1D CanonCustom PersonalFuncs CanonCustom PersonalFuncValues
0x0083 0x0090 0x0091	CustomFunctions1D PersonalFunctions	CanonCustom Functions1D CanonCustom PersonalFuncs
0x0083 0x0090 0x0091 0x0092 0x0093	CustomFunctions1D PersonalFunctions PersonalFunctionValues CanonFileInfo	CanonCustom Functions1D CanonCustom PersonalFuncs CanonCustom PersonalFuncValues Canon FileInfo
0x0083 0x0090 0x0091 0x0092 0x0093 0x0094	CustomFunctions1D PersonalFunctions PersonalFunctionValues CanonFileInfo AFPointsInFocus1D LensModel SerialInfo	CanonCustom Functions1D CanonCustom PersonalFuncs CanonCustom PersonalFuncValues Canon FileInfo no
0x0083 0x0090 0x0091 0x0092 0x0093 0x0094 0x0095 0x0096	CustomFunctions1D PersonalFunctions PersonalFunctionValues CanonFileInfo AFPointsInFocus1D LensModel SerialInfo InternalSerialNumber	CanonCustom Functions1D CanonCustom PersonalFuncs CanonCustom PersonalFuncValues Canon FileInfo no string Canon SerialInfo string
0x0083 0x0090 0x0091 0x0092 0x0093 0x0094 0x0095 0x0096	CustomFunctions1D PersonalFunctions PersonalFunctionValues CanonFileInfo AFPointsInFocus1D LensModel SerialInfo InternalSerialNumber DustRemovalData	CanonCustom Functions1D CanonCustom PersonalFuncs CanonCustom PersonalFuncValues Canon FileInfo no string Canon SerialInfo string undef!
0x0083 0x0090 0x0091 0x0092 0x0093 0x0094 0x0095 0x0096	CustomFunctions1D PersonalFunctions PersonalFunctionValues CanonFileInfo AFPointsInFocus1D LensModel SerialInfo InternalSerialNumber DustRemovalData CropInfo	CanonCustom Functions1D CanonCustom PersonalFuncs CanonCustom PersonalFuncValues Canon FileInfo no string Canon SerialInfo string undef! Canon CropInfo
0x0083 0x0090 0x0091 0x0092 0x0093 0x0094 0x0095 0x0096	CustomFunctions1D PersonalFunctions PersonalFunctionValues CanonFileInfo AFPointsInFocus1D LensModel SerialInfo InternalSerialNumber DustRemovalData CropInfo CustomFunctions2	CanonCustom Functions1D CanonCustom PersonalFuncs CanonCustom PersonalFuncValues Canon FileInfo no string Canon SerialInfo string undef! Canon CropInfo CanonCustom Functions2
0x0083 0x0090 0x0091 0x0092 0x0093 0x0094 0x0095 0x0096 0x0097 0x0098 0x0099 0x009a	CustomFunctions1D PersonalFunctions PersonalFunctionValues CanonFileInfo AFPointsInFocus1D LensModel SerialInfo InternalSerialNumber DustRemovalData CropInfo CustomFunctions2 AspectInfo	CanonCustom Functions1D CanonCustom PersonalFuncs CanonCustom PersonalFuncValues Canon FileInfo no string Canon SerialInfo string undef! Canon CropInfo CanonCustom Functions2 Canon AspectInfo
0x0083 0x0090 0x0091 0x0092 0x0093 0x0094 0x0095 0x0096	CustomFunctions1D PersonalFunctions PersonalFunctionValues CanonFileInfo AFPointsInFocus1D LensModel SerialInfo InternalSerialNumber DustRemovalData CropInfo CustomFunctions2	CanonCustom Functions1D CanonCustom PersonalFuncs CanonCustom PersonalFuncValues Canon FileInfo no string Canon SerialInfo string undef! Canon CropInfo CanonCustom Functions2
0x0083 0x0090 0x0091 0x0092 0x0093 0x0094 0x0095 0x0096 0x0097 0x0098 0x0099 0x009a 0x00a0	CustomFunctions1D PersonalFunctions PersonalFunctionValues CanonFileInfo AFPointsInFocus1D LensModel SerialInfo InternalSerialNumber DustRemovalData CropInfo CustomFunctions2 AspectInfo ProcessingInfo	CanonCustom Functions1D CanonCustom PersonalFuncs CanonCustom PersonalFuncValues Canon FileInfo no string Canon SerialInfo string undef! Canon CropInfo CanonCustom Functions2 Canon AspectInfo Canon Processing
0x0083 0x0090 0x0091 0x0092 0x0093 0x0094 0x0095 0x0096 0x0097 0x0098 0x0099 0x0099 0x000a0 0x00a1	CustomFunctions1D PersonalFunctions PersonalFunctionValues CanonFileInfo AFPointsInFocus1D LensModel SerialInfo InternalSerialNumber DustRemovalData CropInfo CustomFunctions2 AspectInfo ProcessingInfo ToneCurveTable	CanonCustom Functions1D CanonCustom PersonalFuncs CanonCustom PersonalFuncValues Canon FileInfo no string Canon SerialInfo string undef! Canon CropInfo CanonCustom Functions2 Canon AspectInfo Canon Processing no
0x0083 0x0090 0x0091 0x0092 0x0093 0x0094 0x0095 0x0096 0x0097 0x0098 0x0099 0x0099 0x00a0 0x00a1 0x00a2 0x00a3 0x00a4	CustomFunctions1D PersonalFunctions PersonalFunctionValues CanonFileInfo AFPointsInFocus1D LensModel SerialInfo InternalSerialNumber DustRemovalData CropInfo CustomFunctions2 AspectInfo ProcessingInfo ToneCurveTable SharpnessTable	CanonCustom Functions1D CanonCustom PersonalFuncs CanonCustom PersonalFuncValues Canon FileInfo no string Canon SerialInfo string undef! Canon CropInfo CanonCustom Functions2 Canon AspectInfo Canon Processing no no no
0x0083 0x0090 0x0091 0x0092 0x0093 0x0094 0x0095 0x0096 0x0097 0x0098 0x0099 0x0099 0x00000 0x00a1 0x00a2 0x00a3 0x00a4 0x00a9	CustomFunctions1D PersonalFunctions PersonalFunctionValues CanonFileInfo AFPointsInFocus1D LensModel SerialInfo InternalSerialNumber DustRemovalData CropInfo CustomFunctions2 AspectInfo ProcessingInfo ToneCurveTable SharpnessTable SharpnessFreqTable WhiteBalanceTable ColorBalance	CanonCustom Functions1D CanonCustom PersonalFuncs CanonCustom PersonalFuncValues Canon FileInfo no string Canon SerialInfo string undef! Canon CropInfo CanonCustom Functions2 Canon AspectInfo Canon Processing no no no canon ColorBalance
0x0083 0x0090 0x0091 0x0092 0x0093 0x0094 0x0095 0x0096  0x0097 0x0098 0x0099 0x0090 0x00a0 0x00a1 0x00a2 0x00a3 0x00a4 0x00a9 0x00aa	CustomFunctions1D PersonalFunctions PersonalFunctionValues CanonFileInfo AFPointsInFocus1D LensModel SerialInfo InternalSerialNumber DustRemovalData CropInfo CustomFunctions2 AspectInfo ProcessingInfo ToneCurveTable SharpnessTable SharpnessFreqTable WhiteBalanceTable ColorBalance MeasuredColor	CanonCustom Functions1D CanonCustom PersonalFuncs CanonCustom PersonalFuncValues Canon FileInfo no string Canon SerialInfo string undef! Canon CropInfo CanonCustom Functions2 Canon AspectInfo Canon Processing no no no no Canon ColorBalance Canon MeasuredColor
0x0083 0x0090 0x0091 0x0092 0x0093 0x0094 0x0095 0x0096  0x0097 0x0098 0x0099 0x0090 0x00a0 0x00a1 0x00a2 0x00a3 0x00a4 0x00a9 0x00aa 0x00aa	CustomFunctions1D PersonalFunctions PersonalFunctionValues CanonFileInfo AFPointsInFocus1D LensModel SerialInfo InternalSerialNumber DustRemovalData CropInfo CustomFunctions2 AspectInfo ProcessingInfo ToneCurveTable SharpnessTable SharpnessFreqTable WhiteBalanceTable ColorBalance MeasuredColor ColorTemperature	CanonCustom Functions1D CanonCustom PersonalFuncs CanonCustom PersonalFuncValues Canon FileInfo no string Canon SerialInfo string undef! Canon CropInfo CanonCustom Functions2 Canon AspectInfo Canon Processing no no no canon ColorBalance Canon MeasuredColor int16u
0x0083 0x0090 0x0091 0x0092 0x0093 0x0094 0x0095 0x0096  0x0097 0x0098 0x0099 0x0090 0x00a0 0x00a1 0x00a2 0x00a3 0x00a4 0x00a9 0x00aa 0x00ae 0x00b0	CustomFunctions1D PersonalFunctions PersonalFunctionValues CanonFileInfo AFPointsInFocus1D LensModel SerialInfo InternalSerialNumber DustRemovalData CropInfo CustomFunctions2 AspectInfo ProcessingInfo ToneCurveTable SharpnessTable SharpnessFreqTable WhiteBalanceTable ColorBalance MeasuredColor ColorTemperature CanonFlags	CanonCustom Functions1D CanonCustom PersonalFuncs CanonCustom PersonalFuncValues Canon FileInfo no string Canon SerialInfo string undef! Canon CropInfo CanonCustom Functions2 Canon AspectInfo Canon Processing no no no no canon ColorBalance Canon MeasuredColor int16u Canon Flags
0x0083 0x0090 0x0091 0x0092 0x0093 0x0094 0x0095 0x0096  0x0097 0x0098 0x0099 0x0090 0x00a0 0x00a1 0x00a2 0x00a3 0x00a4 0x00a9 0x00a0 0x00a1 0x00a2 0x00a1 0x00a2	CustomFunctions1D PersonalFunctions PersonalFunctionValues CanonFileInfo AFPointsInFocus1D LensModel SerialInfo InternalSerialNumber DustRemovalData CropInfo CustomFunctions2 AspectInfo ProcessingInfo ToneCurveTable SharpnessTable SharpnessFreqTable WhiteBalanceTable ColorBalance MeasuredColor ColorTemperature CanonFlags ModifiedInfo	CanonCustom Functions1D CanonCustom PersonalFuncs CanonCustom PersonalFuncValues Canon FileInfo no string Canon SerialInfo string undef! Canon CropInfo CanonCustom Functions2 Canon AspectInfo Canon Processing no no no canon ColorBalance Canon MeasuredColor int16u
0x0083 0x0090 0x0091 0x0092 0x0093 0x0094 0x0095 0x0096  0x0097 0x0098 0x0099 0x0090 0x00a0 0x00a1 0x00a2 0x00a3 0x00a4 0x00a9 0x00aa 0x00ae 0x00b0	CustomFunctions1D PersonalFunctions PersonalFunctionValues CanonFileInfo AFPointsInFocus1D LensModel SerialInfo InternalSerialNumber DustRemovalData CropInfo CustomFunctions2 AspectInfo ProcessingInfo ToneCurveTable SharpnessTable SharpnessFreqTable WhiteBalanceTable ColorBalance MeasuredColor ColorTemperature CanonFlags	CanonCustom Functions1D CanonCustom PersonalFuncs CanonCustom PersonalFuncValues Canon FileInfo no string Canon SerialInfo string undef! Canon CropInfo CanonCustom Functions2 Canon AspectInfo Canon Processing no no no canon ColorBalance Canon MeasuredColor int16u Canon Flags Canon ModifiedInfo
0x0083 0x0090 0x0091 0x0092 0x0093 0x0094 0x0095 0x0096  0x0097 0x0098 0x0099 0x0099 0x00a0 0x00a1 0x00a2 0x00a3 0x00a4 0x00a9 0x00aa 0x00ae 0x00b0 0x00b1 0x00b2	CustomFunctions1D PersonalFunctions PersonalFunctionValues CanonFileInfo AFPointsInFocus1D LensModel SerialInfo InternalSerialNumber DustRemovalData CropInfo CustomFunctions2 AspectInfo ProcessingInfo ToneCurveTable SharpnessTable SharpnessFreqTable WhiteBalanceTable ColorBalance MeasuredColor ColorTemperature CanonFlags ModifiedInfo ToneCurveMatching	CanonCustom Functions1D CanonCustom PersonalFuncs CanonCustom PersonalFuncValues Canon FileInfo no string Canon SerialInfo string undef! Canon CropInfo CanonCustom Functions2 Canon AspectInfo Canon Processing no no no canon ColorBalance Canon MeasuredColor int16u Canon Flags Canon ModifiedInfo no
0x0083 0x0090 0x0091 0x0092 0x0093 0x0094 0x0095 0x0096  0x0097 0x0098 0x0099 0x0099 0x000a0 0x00a1 0x00a2 0x00a3 0x00a4 0x00a9 0x00aa 0x00ae 0x00b0 0x00b1 0x00b2 0x00b3	CustomFunctions1D PersonalFunctions PersonalFunctionValues CanonFileInfo AFPointsInFocus1D LensModel SerialInfo InternalSerialNumber DustRemovalData CropInfo CustomFunctions2 AspectInfo ProcessingInfo ToneCurveTable SharpnessTable SharpnessFreqTable WhiteBalanceTable ColorBalance MeasuredColor ColorTemperature CanonFlags ModifiedInfo ToneCurveMatching WhiteBalanceMatching ColorSpace PreviewImageInfo	CanonCustom Functions1D CanonCustom PersonalFuncs CanonCustom PersonalFuncValues Canon FileInfo no string Canon SerialInfo string undef! Canon CropInfo CanonCustom Functions2 Canon AspectInfo Canon Processing no no no canon ColorBalance Canon MeasuredColor int16u Canon Flags Canon ModifiedInfo no ro processing no no no no canon PreviewImageInfo
0x0083 0x0090 0x0091 0x0092 0x0093 0x0094 0x0095 0x0096  0x0097 0x0098 0x0099 0x009a 0x00a0 0x00a1 0x00a2 0x00a3 0x00a4 0x00a9 0x00a0 0x00a1 0x00a2 0x00b0 0x00b1 0x00b2 0x00b6 0x00d0	CustomFunctions1D PersonalFunctions PersonalFunctionValues CanonFileInfo AFPointsInFocus1D LensModel SerialInfo InternalSerialNumber DustRemovalData CropInfo CustomFunctions2 AspectInfo ProcessingInfo ToneCurveTable SharpnessTable SharpnessFreqTable WhiteBalanceTable ColorBalance MeasuredColor ColorTemperature CanonFlags ModifiedInfo ToneCurveMatching WhiteBalanceMatching ColorSpace PreviewImageInfo VRDOffset	CanonCustom Functions1D CanonCustom PersonalFuncs CanonCustom PersonalFuncValues Canon FileInfo no string Canon SerialInfo string undef! Canon CropInfo CanonCustom Functions2 Canon AspectInfo Canon Processing no no no canon ColorBalance Canon MeasuredColor int16u Canon Flags Canon ModifiedInfo no no int16u Canon PreviewImageInfo int32u*
0x0083 0x0090 0x0091 0x0092 0x0093 0x0094 0x0095 0x0096  0x0097 0x0098 0x0099 0x009a 0x00a0 0x00a1 0x00a2 0x00a3 0x00a4 0x00a9 0x00a0 0x00b1 0x00b2 0x00b3 0x00b6 0x00b0 0x00b0 0x00b0 0x00b0 0x00b0	CustomFunctions1D PersonalFunctions PersonalFunctionValues CanonFileInfo AFPointsInFocus1D LensModel SerialInfo InternalSerialNumber DustRemovalData CropInfo CustomFunctions2 AspectInfo ProcessingInfo ToneCurveTable SharpnessTable SharpnessFreqTable WhiteBalanceTable ColorBalance MeasuredColor ColorTemperature CanonFlags ModifiedInfo ToneCurveMatching WhiteBalanceMatching ColorSpace PreviewImageInfo VRDOffset SensorInfo	CanonCustom Functions1D CanonCustom PersonalFuncs CanonCustom PersonalFuncValues Canon FileInfo no string Canon SerialInfo string undef! Canon CropInfo CanonCustom Functions2 Canon AspectInfo Canon Processing no no no canon ColorBalance Canon MeasuredColor int16u Canon Flags Canon ModifiedInfo no no int16u Canon PreviewImageInfo int32u* Canon SensorInfo
0x0083 0x0090 0x0091 0x0092 0x0093 0x0094 0x0095 0x0096  0x0097 0x0098 0x0099 0x009a 0x00a0 0x00a1 0x00a2 0x00a3 0x00a4 0x00a9 0x00a0 0x00a1 0x00a2 0x00b0 0x00b1 0x00b2 0x00b6 0x00d0	CustomFunctions1D PersonalFunctions PersonalFunctionValues CanonFileInfo AFPointsInFocus1D LensModel SerialInfo InternalSerialNumber DustRemovalData CropInfo CustomFunctions2 AspectInfo ProcessingInfo ToneCurveTable SharpnessTable SharpnessFreqTable WhiteBalanceTable ColorBalance MeasuredColor ColorTemperature CanonFlags ModifiedInfo ToneCurveMatching WhiteBalanceMatching ColorSpace PreviewImageInfo VRDOffset SensorInfo ColorData1	CanonCustom Functions1D CanonCustom PersonalFuncs CanonCustom PersonalFuncValues Canon FileInfo no string Canon SerialInfo string undef! Canon CropInfo CanonCustom Functions2 Canon AspectInfo Canon Processing no no no canon ColorBalance Canon MeasuredColor int16u Canon Flags Canon ModifiedInfo no no int16u Canon PreviewImageInfo int32u* Canon SensorInfo Canon ColorDatal
0x0083 0x0090 0x0091 0x0092 0x0093 0x0094 0x0095 0x0096  0x0097 0x0098 0x0099 0x009a 0x00a0 0x00a1 0x00a2 0x00a3 0x00a4 0x00a9 0x00a0 0x00b1 0x00b2 0x00b3 0x00b6 0x00b0 0x00b0 0x00b0 0x00b0 0x00b0	CustomFunctions1D PersonalFunctions PersonalFunctionValues CanonFileInfo AFPointsInFocus1D LensModel SerialInfo InternalSerialNumber DustRemovalData CropInfo CustomFunctions2 AspectInfo ProcessingInfo ToneCurveTable SharpnessTable SharpnessFreqTable WhiteBalanceTable ColorBalance MeasuredColor ColorTemperature CanonFlags ModifiedInfo ToneCurveMatching WhiteBalanceMatching ColorSpace PreviewImageInfo VRDOffset SensorInfo ColorData1 ColorData2	CanonCustom Functions1D CanonCustom PersonalFuncs CanonCustom PersonalFuncValues Canon FileInfo no string Canon SerialInfo string undef! Canon CropInfo CanonCustom Functions2 Canon AspectInfo Canon Processing no no no canon ColorBalance Canon MeasuredColor int16u Canon Flags Canon ModifiedInfo no no int16u Canon PreviewImageInfo int32u* Canon SensorInfo Canon ColorData1 Canon ColorData2
0x0083 0x0090 0x0091 0x0092 0x0093 0x0094 0x0095 0x0096  0x0097 0x0098 0x0099 0x009a 0x00a0 0x00a1 0x00a2 0x00a3 0x00a4 0x00a9 0x00a0 0x00b1 0x00b2 0x00b3 0x00b6 0x00b0 0x00b0 0x00b0 0x00b0 0x00b0	CustomFunctions1D PersonalFunctions PersonalFunctionValues CanonFileInfo AFPointsInFocus1D LensModel SerialInfo InternalSerialNumber DustRemovalData CropInfo CustomFunctions2 AspectInfo ProcessingInfo ToneCurveTable SharpnessTable SharpnessFreqTable WhiteBalanceTable ColorBalance MeasuredColor ColorTemperature CanonFlags ModifiedInfo ToneCurveMatching WhiteBalanceMatching ColorSpace PreviewImageInfo VRDOffset SensorInfo ColorData1	CanonCustom Functions1D CanonCustom PersonalFuncs CanonCustom PersonalFuncValues Canon FileInfo no string Canon SerialInfo string undef! Canon CropInfo CanonCustom Functions2 Canon AspectInfo Canon Processing no no no canon ColorBalance Canon MeasuredColor int16u Canon Flags Canon ModifiedInfo no no int16u Canon PreviewImageInfo int32u* Canon SensorInfo Canon ColorDatal

	ColorData5	Canon ColorData5
	ColorData6	Canon ColorData6
	ColorData7	Canon ColorData7
	ColorData8	Canon ColorData8
	ColorData9	Canon ColorData9
	ColorData10	Canon ColorData10
	ColorData11	Canon ColorData11
	ColorData12	Canon ColorData12
	ColorDataUnknown	Canon ColorDataUnknown
0x4002	CRWParam?	no
0x4003	ColorInfo	Canon ColorInfo
0x4005	Flavor?	no
0x4008	PictureStyleUserDef	[Values 0-2]
		Canon PictureStyle
0x4009	PictureStylePC	[Values 0-2]
		Canon PictureStyle
$0 \times 4010$	CustomPictureStyleFileName	string
0x4010 0x4013	CustomPictureStyleFileName AFMicroAdj	string Canon AFMicroAdj
	AFMicroAdj VignettingCorr	Canon AFMicroAdj Canon VignettingCorr
0x4013	AFMicroAdj VignettingCorr VignettingCorrUnknown1	Canon AFMicroAdj
0x4013 0x4015	AFMicroAdj VignettingCorr VignettingCorrUnknown1 VignettingCorrUnknown2	Canon AFMicroAdj Canon VignettingCorr Canon VignettingCorrUnknown Canon VignettingCorrUnknown
0x4013 0x4015	AFMicroAdj VignettingCorr VignettingCorrUnknownl VignettingCorrUnknown2 VignettingCorr2	Canon AFMicroAdj Canon VignettingCorr Canon VignettingCorrUnknown Canon VignettingCorrUnknown Canon VignettingCorr2
0x4013 0x4015 0x4016 0x4018	AFMicroAdj VignettingCorr VignettingCorrUnknown1 VignettingCorrUnknown2 VignettingCorr2 LightingOpt	Canon AFMicroAdj Canon VignettingCorr Canon VignettingCorrUnknown Canon VignettingCorrUnknown Canon VignettingCorr2 Canon LightingOpt
0x4013 0x4015 0x4016 0x4018 0x4019	AFMicroAdj VignettingCorr VignettingCorrUnknown1 VignettingCorrUnknown2 VignettingCorr2 LightingOpt LensInfo	Canon AFMicroAdj Canon VignettingCorr Canon VignettingCorrUnknown Canon VignettingCorrUnknown Canon VignettingCorr2 Canon LightingOpt Canon LensInfo
0x4013 0x4015 0x4016 0x4018 0x4019 0x4020	AFMicroAdj VignettingCorr VignettingCorrUnknown1 VignettingCorrUnknown2 VignettingCorr2 LightingOpt LensInfo AmbienceInfo	Canon AFMicroAdj Canon VignettingCorr Canon VignettingCorrUnknown Canon VignettingCorrUnknown Canon VignettingCorr2 Canon LightingOpt Canon LensInfo Canon Ambience
0x4013 0x4015 0x4016 0x4018 0x4019 0x4020 0x4021	AFMicroAdj VignettingCorr VignettingCorrUnknown1 VignettingCorrUnknown2 VignettingCorr2 LightingOpt LensInfo AmbienceInfo MultiExp	Canon AFMicroAdj Canon VignettingCorr Canon VignettingCorrUnknown Canon VignettingCorrUnknown Canon VignettingCorr2 Canon LightingOpt Canon LensInfo Canon Ambience Canon MultiExp
0x4013 0x4015 0x4016 0x4018 0x4019 0x4020 0x4021 0x4024	AFMicroAdj VignettingCorr VignettingCorrUnknown1 VignettingCorrUnknown2 VignettingCorr2 LightingOpt LensInfo AmbienceInfo MultiExp FilterInfo	Canon AFMicroAdj Canon VignettingCorr Canon VignettingCorrUnknown Canon VignettingCorrUnknown Canon VignettingCorr2 Canon LightingOpt Canon LensInfo Canon Ambience Canon MultiExp Canon FilterInfo
0x4013 0x4015 0x4016 0x4018 0x4019 0x4020 0x4021 0x4024 0x4025	AFMicroAdj VignettingCorr VignettingCorrUnknown1 VignettingCorrUnknown2 VignettingCorr2 LightingOpt LensInfo AmbienceInfo MultiExp FilterInfo HDRInfo	Canon AFMicroAdj Canon VignettingCorr Canon VignettingCorrUnknown Canon VignettingCorrUnknown Canon VignettingCorr2 Canon LightingOpt Canon LensInfo Canon Ambience Canon MultiExp Canon FilterInfo Canon HDRInfo
0x4013 0x4015 0x4016 0x4018 0x4019 0x4020 0x4021 0x4024 0x4025 0x4026	AFMicroAdj VignettingCorr VignettingCorrUnknown1 VignettingCorrUnknown2 VignettingCorr2 LightingOpt LensInfo AmbienceInfo MultiExp FilterInfo LogInfo	Canon AFMicroAdj Canon VignettingCorr Canon VignettingCorrUnknown Canon VignettingCorrUnknown Canon VignettingCorr2 Canon LightingOpt Canon LensInfo Canon Ambience Canon MultiExp Canon FilterInfo Canon LogInfo
0x4013 0x4015 0x4016 0x4018 0x4019 0x4020 0x4021 0x4024 0x4025 0x4026 0x4028	AFMicroAdj VignettingCorr VignettingCorrUnknown1 VignettingCorrUnknown2 VignettingCorr2 LightingOpt LensInfo AmbienceInfo MultiExp FilterInfo HDRInfo LogInfo AFConfig	Canon AFMicroAdj Canon VignettingCorr Canon VignettingCorrUnknown Canon VignettingCorrUnknown Canon VignettingCorr2 Canon LightingOpt Canon LensInfo Canon Ambience Canon MultiExp Canon FilterInfo Canon HDRInfo Canon LogInfo Canon AFConfig
0x4013 0x4015 0x4016 0x4018 0x4019 0x4020 0x4021 0x4024 0x4025 0x4026	AFMicroAdj VignettingCorr VignettingCorrUnknown1 VignettingCorrUnknown2 VignettingCorr2 LightingOpt LensInfo AmbienceInfo MultiExp FilterInfo LogInfo	Canon AFMicroAdj Canon VignettingCorr Canon VignettingCorrUnknown Canon VignettingCorrUnknown Canon VignettingCorr2 Canon LightingOpt Canon LensInfo Canon Ambience Canon MultiExp Canon FilterInfo Canon LogInfo

# Canon CameraSettings Tags

Index2	Tag Name	Writable
1	MacroMode	int16s
2	SelfTimer	int16s
3	Quality	int16s
4	CanonFlashMode	int16s
5	ContinuousDrive	int16s
7	FocusMode	int16s
9	RecordMode	int16s
10	CanonImageSize	int16s
11	EasyMode	int16s
12	DigitalZoom	int16s
13	Contrast	int16s
14	Saturation	int16s
15	Sharpness	int16s
16	CameraISO	int16s
17	MeteringMode	int16s
18	FocusRange	int16s
19	AFPoint	int16s
20	CanonExposureMode	int16s
22	LensType	int16u
23	MaxFocalLength	int16u
24	MinFocalLength	int16u
25	FocalUnits	int16s
26	MaxAperture	int16s
27	MinAperture	int16s
28	FlashActivity	int16s
29	FlashBits	int16s
32	FocusContinuous	int16s
33	AESetting	int16s
34	ImageStabilization	int16s
35	DisplayAperture	int16s
36	ZoomSourceWidth	int16s
37	ZoomTargetWidth	int16s
39	SpotMeteringMode	int16s

#### -- ExifTool 13.24 Tag Names --

PhotoEffect	int16s
ManualFlashOutput	int16s
ColorTone	int16s
SRAWQuality	int16s
Clarity	int16s
	ManualFlashOutput ColorTone SRAWQuality

### Canon FocalLength Tags

Index2	Tag Name	Writable
0	FocalType	int16u
1	FocalLength	int16u
2	FocalPlaneXSize	int16u
	FocalPlaneXUnknown?	int16u
3	FocalPlaneYSize	int16u
	FocalPlaneYUnknown?	int16u

### Canon ShotInfo Tags

Index2	Tag Name	Writable
1	AutoISO	int16s
2	BaseISO	int16s
3	MeasuredEV	int16s
4	TargetAperture	int16s
5	TargetExposureTime	int16s
6	ExposureCompensation	int16s
7	WhiteBalance	int16s
8	SlowShutter	int16s
9	SequenceNumber	int16s
10	OpticalZoomCode	int16s
12	CameraTemperature	int16s
13	FlashGuideNumber	int16s
14	AFPointsInFocus	int16s
15	FlashExposureComp	int16s
16	AutoExposureBracketing	int16s
17	AEBBracketValue	int16s
18	ControlMode	int16s
19	FocusDistanceUpper	int16u
20	FocusDistanceLower	int16u
21	FNumber	int16s
22	ExposureTime	int16s
23	MeasuredEV2	int16s
24	BulbDuration	int16s
26	CameraType	int16s
27	AutoRotate	int16s
28	NDFilter	int16s
29	SelfTimer2	int16s
33	FlashOutput	int16s

### <u>Canon Panorama Tags</u>

Index2	Tag Name	Writable
2	PanoramaFrameNumber	int16s
5	PanoramaDirection	int16s

## Canon UnknownD30 Tags

Index2	Tag Name	Writable
[no tags	known]	

### <u>Canon</u> <u>CameraInfolD</u> <u>Tags</u>

Information in the "CameraInfo" records is tricky to decode because the encodings are very different than in other Canon records (even sometimes switching endianness between values within a single camera), plus there is considerable variation in format from model to model. The first table below lists CameraInfo tags for the 1D and 1DS.

- 1 1		1. 1.7
Index1	Tag Name	Writable
4	ExposureTime	int8u
10	FocalLength	int16u
13	LensType	int16uRev
14	MinFocalLength	int16u
16	MaxFocalLength	int16u
65	SharpnessFrequency	int8u
66	Sharpness	int8s
68	WhiteBalance	int8u
71	SharpnessFrequency	int8u
72	ColorTemperature	int16u
	Sharpness	int8s
74	WhiteBalance	int8u
75	PictureStyle	int8u
78	ColorTemperature	int16u
81	PictureStyle	int8u

### <u>Canon</u> <u>CameraInfolDmkII</u> <u>Tags</u>

CameraInfo tags for the 1DmkII and 1DSmkII.

Index1	Tag Name	Writable
4	ExposureTime	int8u
9	FocalLength	int16uRev
12	LensType	int16uRev
17	MinFocalLength	int16uRev
19	MaxFocalLength	int16uRev
45	FocalType	int8u
54	WhiteBalance	int8u
55	ColorTemperature	int16uRev
57	CanonImageSize	int16u
102	JPEGQuality	int8u
108	PictureStyle	int8u
110	Saturation	int8s
111	ColorTone	int8s
114	Sharpness	int8s
115	Contrast	int8s
117	ISO	string[5]

# $\underline{\texttt{Canon}} \ \underline{\texttt{CameraInfolDmkIIN}} \ \underline{\texttt{Tags}}$

CameraInfo tags for the 1DmkIIN.

Index1	Tag Name	Writable
4	ExposureTime	int8u
9	FocalLength	int16uRev
12	LensType	int16uRev
17	MinFocalLength	int16uRev
19	MaxFocalLength	int16uRev
54	WhiteBalance	int8u
55	ColorTemperature	int16uRev
115	PictureStyle	int8u
116	Sharpness	int8s
117	Contrast	int8s
118	Saturation	int8s
119	ColorTone	int8s
121	ISO	string[5]

### <u>Canon</u> <u>CameraInfolDmkIII</u> <u>Tags</u>

CameraInfo tags for the 1DmkIII and 1DSmkIII.

Index1	Tag Name	Writable
3	FNumber	int8u
4	ExposureTime	int8u

ISO	int8u
CameraTemperature	int8u
MacroMagnification	int8u
FocalLength	int16uRev
CameraOrientation	int8u
FocusDistanceUpper	int16uRev
FocusDistanceLower	int16uRev
WhiteBalance	int16u
ColorTemperature	int16u
PictureStyle	int8u
LensType	int16uRev
MinFocalLength	int16uRev
MaxFocalLength	int16uRev
FirmwareVersion	string[6]
FileIndex	int32u
ShutterCount	int32u
DirectoryIndex	int32u
PictureStyleInfo	Canon PSInfo
TimeStamp1	int32u
TimeStamp	int32u
	CameraTemperature MacroMagnification FocalLength CameraOrientation FocusDistanceUpper FocusDistanceLower WhiteBalance ColorTemperature PictureStyle LensType MinFocalLength MaxFocalLength FirmwareVersion FileIndex ShutterCount DirectoryIndex PictureStyleInfo TimeStamp1

# Canon PSInfo Tags

Custom picture style information for various models.

Index1	Tag Name	Writable
0	ContrastStandard	int32s
4	SharpnessStandard	int32s
8	SaturationStandard	int32s
12	ColorToneStandard	int32s
16	FilterEffectStandard?	int32s
20	ToningEffectStandard?	int32s
24	ContrastPortrait	int32s
28	SharpnessPortrait	int32s
32	SaturationPortrait	int32s
36	ColorTonePortrait	int32s
40	FilterEffectPortrait?	int32s
44	ToningEffectPortrait?	int32s
48	ContrastLandscape	int32s
52	SharpnessLandscape	int32s
56	SaturationLandscape	int32s
60	ColorToneLandscape	int32s
64	FilterEffectLandscape?	int32s
68	ToningEffectLandscape?	int32s
72	ContrastNeutral	int32s
76	SharpnessNeutral	int32s
80	SaturationNeutral	int32s
84	ColorToneNeutral	int32s
88	FilterEffectNeutral?	int32s
92	ToningEffectNeutral?	int32s
96	ContrastFaithful	int32s
100	SharpnessFaithful	int32s
104	SaturationFaithful	int32s
108	ColorToneFaithful	int32s
112	FilterEffectFaithful?	int32s
116	ToningEffectFaithful?	int32s
120	ContrastMonochrome	int32s
124	SharpnessMonochrome	int32s
128	SaturationMonochrome?	int32s
132	ColorToneMonochrome?	int32s
136	FilterEffectMonochrome	int32s
140	ToningEffectMonochrome	int32s
144	ContrastUserDef1	int32s
148	SharpnessUserDef1	int32s
152	SaturationUserDef1	int32s
156	ColorToneUserDef1	int32s
160	FilterEffectUserDef1	int32s
164	ToningEffectUserDef1	int32s
168	ContrastUserDef2	int32s

172	SharpnessUserDef2	int32s
176	SaturationUserDef2	int32s
180	ColorToneUserDef2	int32s
184	FilterEffectUserDef2	int32s
188	ToningEffectUserDef2	int32s
192	ContrastUserDef3	int32s
196	SharpnessUserDef3	int32s
200	SaturationUserDef3	int32s
204	ColorToneUserDef3	int32s
208	FilterEffectUserDef3	int32s
212	ToningEffectUserDef3	int32s
216	UserDef1PictureStyle	int16u
218	UserDef2PictureStyle	int16u
220	UserDef3PictureStyle	int16u

### Canon CameraInfolDmkIV Tags

CameraInfo tags for the EOS 1D Mark IV. Indices shown are for firmware versions 1.0.x, but they may be different for other firmware versions.

Index1	Tag Name	Writable
3	FNumber	int8u
4	ExposureTime	int8u
6	ISO	int8u
7	HighlightTonePriority	int8u
8	MeasuredEV2	int8u
9	MeasuredEV3	int8u
21	FlashMeteringMode	int8u
25	CameraTemperature	int8u
30	FocalLength	int16uRev
53	CameraOrientation	int8u
84	FocusDistanceUpper	int16uRev
86	FocusDistanceLower	int16uRev
120	WhiteBalance	int16u
124	ColorTemperature	int16u
335	LensType	int16uRev
337	MinFocalLength	int16uRev
339	MaxFocalLength	int16uRev
493	FirmwareVersion	no
556	FileIndex	int32u
568	DirectoryIndex	int32u
872	PictureStyleInfo	Canon PSInfo

### Canon CameraInfolDX Tags

CameraInfo tags for the EOS 1D X. Indices shown are for firmware version 1.0.2, but they may be different for other firmware versions.

Index1	Tag Name	Writable
3	FNumber	int8u
4	ExposureTime	int8u
6	ISO	int8u
27	CameraTemperature	int8u
35	FocalLength	int16uRev
125	CameraOrientation	int8u
140	FocusDistanceUpper	int16uRev
142	FocusDistanceLower	int16uRev
188	WhiteBalance	int16u
192	ColorTemperature	int16u
244	PictureStyle	int8u
423	LensType	int16uRev
425	MinFocalLength	int16uRev
427	MaxFocalLength	int16uRev
640	FirmwareVersion	no
720	FileIndex	int32u
732	DirectoryIndex	int32u
1012	PictureStyleInfo	Canon PSInfo2

# Canon PSInfo2 Tags

Custom picture style information for the EOS 5DmkIII, 60D, 600D and 1100D.

Index1	Tag Name	Writable
0	ContrastStandard	int32s
4	SharpnessStandard	int32s
8	SaturationStandard	int32s
12	ColorToneStandard	int32s
16	FilterEffectStandard?	int32s
20	ToningEffectStandard?	int32s
24	ContrastPortrait	int32s
28	SharpnessPortrait	int32s
32	SaturationPortrait	int32s
36	ColorTonePortrait	int32s
40	FilterEffectPortrait?	int32s
44	ToningEffectPortrait?	int32s
48	ContrastLandscape	int32s
52	SharpnessLandscape	int32s
56	SaturationLandscape	int32s
60	ColorToneLandscape	int32s
64	FilterEffectLandscape?	int32s
68 72	ToningEffectLandscape?	int32s
72 76	ContrastNeutral	int32s
76 80	SharpnessNeutral SaturationNeutral	int32s int32s
84	ColorToneNeutral	int32s
88	FilterEffectNeutral?	int32s
92	ToningEffectNeutral?	int32s
96	ContrastFaithful	int32s
100	SharpnessFaithful	int32s
104	SaturationFaithful	int32s
108	ColorToneFaithful	int32s
112	FilterEffectFaithful?	int32s
116	ToningEffectFaithful?	int32s
120	ContrastMonochrome	int32s
124	SharpnessMonochrome	int32s
128	SaturationMonochrome?	int32s
132	ColorToneMonochrome?	int32s
136	FilterEffectMonochrome	int32s
140	ToningEffectMonochrome	int32s
144	ContrastAuto	int32s
148	SharpnessAuto	int32s
152	SaturationAuto	int32s
156	ColorToneAuto	int32s
160	FilterEffectAuto	int32s int32s
164 168	ToningEffectAuto ContrastUserDef1	int32s
172	SharpnessUserDef1	int32s
176	SaturationUserDef1	int32s
180	ColorToneUserDef1	int32s
184	FilterEffectUserDef1	int32s
188	ToningEffectUserDef1	int32s
192	ContrastUserDef2	int32s
196	SharpnessUserDef2	int32s
200	SaturationUserDef2	int32s
204	ColorToneUserDef2	int32s
208	FilterEffectUserDef2	int32s
212	ToningEffectUserDef2	int32s
216	ContrastUserDef3	int32s
220	SharpnessUserDef3	int32s
224	SaturationUserDef3	int32s
228	ColorToneUserDef3	int32s
232	FilterEffectUserDef3	int32s
236	ToningEffectUserDef3	int32s
240	UserDef1PictureStyle	int16u
242	UserDef2PictureStyle	int16u
244	UserDef3PictureStyle	int16u

# <u>Canon CameraInfo5D Tags</u>

CameraInfo tags for the EOS 5D.

Index1	Tag Name	Writable
3	FNumber	 int8u
4	ExposureTime	int8u
6	ISO	int8u
12	LensType	int16uRev
23	CameraTemperature	int8u
27	MacroMagnification	int8s
39	CameraOrientation	int8s
40	FocalLength	int16uRev
56	AFPointsInFocus5D	int16uRev
84	WhiteBalance	int16u
88	ColorTemperature	int16u
108	PictureStyle	int8u
147	MinFocalLength	int16uRev
149	MaxFocalLength	int16uRev
151	LensType	int16uRev
164	FirmwareRevision	string[8]
172	ShortOwnerName	string[16]
204	DirectoryIndex	int32u
208	FileIndex ContrastStandard	int16u
232 233	ContrastStandard	int8s int8s
234	ContrastLandscape	int8s
235	ContrastNeutral	int8s
236	ContrastFaithful	int8s
237	ContrastMonochrome	int8s
238	ContrastUserDef1	int8s
239	ContrastUserDef2	int8s
240	ContrastUserDef3	int8s
241	SharpnessStandard	int8s
242	SharpnessPortrait	int8s
243	SharpnessLandscape	int8s
244	SharpnessNeutral	int8s
245	SharpnessFaithful	int8s
246	SharpnessMonochrome	int8s
247	SharpnessUserDef1	int8s
248	SharpnessUserDef2	int8s
249	SharpnessUserDef3	int8s
250	SaturationStandard	int8s
251	SaturationPortrait	int8s
252	SaturationLandscape	int8s
253	SaturationNeutral SaturationFaithful	int8s
254 255	FilterEffectMonochrome	int8s int8s
256	SaturationUserDef1	int8s
257	SaturationUserDef1	int8s
258	SaturationUserDef3	int8s
259	ColorToneStandard	int8s
260	ColorTonePortrait	int8s
261	ColorToneLandscape	int8s
262	ColorToneNeutral	int8s
263	ColorToneFaithful	int8s
264	ToningEffectMonochrome	int8s
265	ColorToneUserDef1	int8s
266	ColorToneUserDef2	int8s
267	ColorToneUserDef3	int8s
268	UserDef1PictureStyle	int16u
270	UserDef2PictureStyle	int16u
272	UserDef3PictureStyle	int16u
284	TimeStamp	int32u

# Canon CameraInfo5DmkII Tags

CameraInfo tags for the EOS 5D Mark II. Indices shown are for firmware

version 1.0.6, but they may be different for other firmware versions.

Index1	Tag Name	Writable
3	FNumber	 int8u
4	ExposureTime	int8u
6	ISO	int8u
7	HighlightTonePriority	int8u
21	FlashMeteringMode	int8u
25	CameraTemperature	int8u
27	MacroMagnification	int8u
30	FocalLength	int16uRev
49	CameraOrientation	int8u
80	FocusDistanceUpper	int16uRev
82	FocusDistanceLower	int16uRev
111	WhiteBalance	int16u
115	ColorTemperature	int16u
167	PictureStyle	int8u
189	HighISONoiseReduction	int8u
191	AutoLightingOptimizer	int8u
230	LensType	int16uRev
232	MinFocalLength	int16uRev
234	MaxFocalLength	int16uRev
382	FirmwareVersion	no
443	FileIndex	int32u
455	DirectoryIndex	int32u
759	PictureStyleInfo	Canon PSInfo

### Canon CameraInfo5DmkIII Tags

CameraInfo tags for the EOS 5D Mark III. Indices shown are for firmware versions 1.0.x, but they may be different for other firmware versions.

Index1	Tag Name	Writable
3	FNumber	int8u
4	ExposureTime	int8u
6	ISO	int8u
27	CameraTemperature	int8u
35	FocalLength	int16uRev
125	CameraOrientation	int8u
140	FocusDistanceUpper	int16uRev
142	FocusDistanceLower	int16uRev
188	WhiteBalance	int16u
192	ColorTemperature	int16u
244	PictureStyle	int8u
339	LensType	int16uRev
341	MinFocalLength	int16uRev
343	MaxFocalLength	int16uRev
356	LensSerialNumber	undef[5]
572	FirmwareVersion	no
652	FileIndex	int32u
656	FileIndex2	int32u
664	DirectoryIndex	int32u
668	DirectoryIndex2	int32u
944	PictureStyleInfo	Canon PSInfo2

### Canon CameraInfo6D Tags

CameraInfo tags for the EOS 6D.

Index1	Tag Name	Writable
3	FNumber	int8u
4	ExposureTime	int8u
6	ISO	int8u
27	CameraTemperature	int8u
35	FocalLength	int16uRev
131	CameraOrientation	int8u

146	FocusDistanceUpper	int16uRev
148	FocusDistanceLower	int16uRev
194	WhiteBalance	int16u
198	ColorTemperature	int16u
250	PictureStyle	int8u
353	LensType	int16uRev
355	MinFocalLength	int16uRev
357	MaxFocalLength	int16uRev
598	FirmwareVersion	no
682	FileIndex	int32u
694	DirectoryIndex	int32u
966	PictureStyleInfo	Canon PSInfo2

### <u>Canon</u> <u>CameraInfo7D</u> <u>Tags</u>

CameraInfo tags for the EOS 7D. Indices shown are for firmware versions 1.0.x, but they may be different for other firmware versions.

Index1	Tag Name	Writable
3	FNumber	int8u
4	ExposureTime	int8u
6	ISO	int8u
7	HighlightTonePriority	int8u
8	MeasuredEV2	int8u
9	MeasuredEV	int8u
21	FlashMeteringMode	int8u
25	CameraTemperature	int8u
30	FocalLength	int16uRev
53	CameraOrientation	int8u
84	FocusDistanceUpper	int16uRev
86	FocusDistanceLower	int16uRev
119	WhiteBalance	int16u
123	ColorTemperature	int16u
175	CameraPictureStyle	int8u
201	HighISONoiseReduction	int8u
274	LensType	int16uRev
276	MinFocalLength	int16uRev
278	MaxFocalLength	int16uRev
428	FirmwareVersion	no
491	FileIndex	int32u
503	DirectoryIndex	int32u
807	PictureStyleInfo	Canon PSInfo

### Canon CameraInfo40D Tags

CameraInfo tags for the EOS 40D.

Index1	Tag Name	Writable
3	FNumber	int8u
4	ExposureTime	int8u
6	ISO	int8u
21	FlashMeteringMode	int8u
24	CameraTemperature	int8u
27	MacroMagnification	int8u
29	FocalLength	int16uRev
48	CameraOrientation	int8u
67	FocusDistanceUpper	int16uRev
69	FocusDistanceLower	int16uRev
111	WhiteBalance	int16u
115	ColorTemperature	int16u
214	LensType	int16uRev
216	MinFocalLength	int16uRev
218	MaxFocalLength	int16uRev
255	FirmwareVersion	string[6]
307	FileIndex	int32u
319	DirectoryIndex	int32u
603	PictureStyleInfo	Canon PSInfo
2347	LensModel	string[64]

# Canon CameraInfo50D Tags

CameraInfo tags for the EOS 50D. Indices shown are for firmware versions 1.0.x, but they may be different for other firmware versions.

Index1	Tag Name	Writable
3	FNumber	int8u
4	ExposureTime	int8u
6	ISO	int8u
7	$ exttt{HighlightTonePriority}$	int8u
21	FlashMeteringMode	int8u
25	CameraTemperature	int8u
30	FocalLength	int16uRev
49	CameraOrientation	int8u
80	FocusDistanceUpper	int16uRev
82	FocusDistanceLower	int16uRev
111	WhiteBalance	int16u
115	ColorTemperature	int16u
167	PictureStyle	int8u
189	HighISONoiseReduction	int8u
191	AutoLightingOptimizer	int8u
234	LensType	int16uRev
236	MinFocalLength	int16uRev
238	MaxFocalLength	int16uRev
350	FirmwareVersion	no
411	FileIndex	int32u
423	DirectoryIndex	int32u
727	PictureStyleInfo	Canon PSInfo

### Canon CameraInfo60D Tags

CameraInfo tags for the EOS 60D and 1200D.

Index1	Tag Name	Writable
3	FNumber	int8u
4	ExposureTime	int8u
6	ISO	int8u
25	CameraTemperature	int8u
30	FocalLength	int16uRev
54	CameraOrientation	int8u
58	CameraOrientation	int8u
85	FocusDistanceUpper	int16uRev
87	FocusDistanceLower	int16uRev
125	ColorTemperature	int16u
232	LensType	int16uRev
234	MinFocalLength	int16uRev
236	MaxFocalLength	int16uRev
409	FirmwareVersion	no
473	FileIndex	int32u
485	DirectoryIndex	int32u
761	PictureStyleInfo	Canon PSInfo2
801	PictureStyleInfo	Canon PSInfo2

### Canon CameraInfo70D Tags

CameraInfo tags for the EOS 70D.

Index1	Tag Name	Writable
3	FNumber	int8u
4	ExposureTime	int8u
6	ISO	int8u
27	CameraTemperature	int8u
35	FocalLength	int16uRev
132	CameraOrientation	int8u
147	FocusDistanceUpper	int16uRev
149	FocusDistanceLower	int16uRev

199	ColorTemperature	int16u
358	LensType	int16uRev
360	MinFocalLength	int16uRev
362	MaxFocalLength	int16uRev
606	FirmwareVersion	no
691	FileIndex	int32u
703	DirectoryIndex	int32u
975	PictureStyleInfo	Canon PSInfo2

### Canon CameraInfo80D Tags

CameraInfo tags for the EOS 80D.

Index1	Tag Name	Writable
3	FNumber	int8u
4	ExposureTime	int8u
6	ISO	int8u
27	CameraTemperature	int8u
35	FocalLength	int16uRev
150	CameraOrientation	int8u
165	FocusDistanceUpper	int16uRev
167	FocusDistanceLower	int16uRev
314	ColorTemperature	int16u
393	LensType	int16uRev
395	MinFocalLength	int16uRev
397	MaxFocalLength	int16uRev
1114	FirmwareVersion	no
1198	FileIndex	int32u
1210	DirectoryIndex	int32u

# Canon CameraInfo450D Tags

CameraInfo tags for the EOS 450D.

Index1	Tag Name	Writable
3	FNumber	int8u
4	ExposureTime	int8u
6	ISO	int8u
21	FlashMeteringMode	int8u
24	CameraTemperature	int8u
27	MacroMagnification	int8u
29	FocalLength	int16uRev
48	CameraOrientation	int8u
67	FocusDistanceUpper	int16uRev
69	FocusDistanceLower	int16uRev
111	WhiteBalance	int16u
115	ColorTemperature	int16u
222	LensType	int16uRev
263	FirmwareVersion	string[6]
271	OwnerName	string[32]
307	DirectoryIndex	int32u
319	FileIndex	int32u
611	PictureStyleInfo	Canon PSInfo
2355	LensModel	string[64]

# Canon CameraInfo500D Tags

CameraInfo tags for the EOS 500D.

Index1	Tag Name	Writable
3	FNumber	int8u
4	ExposureTime	int8u
6	ISO	int8u
7	HighlightTonePriority	int8u
21	FlashMeteringMode	int8u
25	CameraTemperature	int8u
30	FocalLength	int16uRev

# -- ExifTool 13.24 Tag Names --

49	CameraOrientation	int8u
80	FocusDistanceUpper	int16uRev
82	FocusDistanceLower	int16uRev
115	WhiteBalance	int16u
119	ColorTemperature	int16u
171	PictureStyle	int8u
188	HighISONoiseReduction	int8u
190	AutoLightingOptimizer	int8u
246	LensType	int16uRev
248	MinFocalLength	int16uRev
250	MaxFocalLength	int16uRev
400	FirmwareVersion	no
467	FileIndex	int32u
479	DirectoryIndex	int32u
779	PictureStyleInfo	Canon PSInfo

# Canon CameraInfo550D Tags

CameraInfo tags for the EOS 550D.

Index1	Tag Name	Writable
3	FNumber	int8u
4	ExposureTime	int8u
6	ISO	int8u
7	HighlightTonePriority	int8u
21	FlashMeteringMode	int8u
25	CameraTemperature	int8u
30	FocalLength	int16uRev
53	CameraOrientation	int8u
84	FocusDistanceUpper	int16uRev
86	FocusDistanceLower	int16uRev
120	WhiteBalance	int16u
124	ColorTemperature	int16u
176	PictureStyle	int8u
255	LensType	int16uRev
257	MinFocalLength	int16uRev
259	MaxFocalLength	int16uRev
420	FirmwareVersion	no
484	FileIndex	int32u
496	DirectoryIndex	int32u
796	PictureStyleInfo	Canon PSInfo

# Canon CameraInfo600D Tags

CameraInfo tags for the EOS 600D and 1100D.

Index1	Tag Name	Writable
3	FNumber	int8u
4	ExposureTime	int8u
6	ISO	int8u
7	HighlightTonePriority	int8u
21	FlashMeteringMode	int8u
25	CameraTemperature	int8u
30	FocalLength	int16uRev
56	CameraOrientation	int8u
87	FocusDistanceUpper	int16uRev
89	FocusDistanceLower	int16uRev
123	WhiteBalance	int16u
127	ColorTemperature	int16u
179	PictureStyle	int8u
234	LensType	int16uRev
236	MinFocalLength	int16uRev
238	MaxFocalLength	int16uRev
411	FirmwareVersion	no
475	FileIndex	int32u
487	DirectoryIndex	int32u
763	PictureStyleInfo	Canon PSInfo2

# Canon CameraInfo650D Tags

CameraInfo tags for the EOS 650D and 700D.

Index1	Tag Name	Writable
3	FNumber	int8u
4	ExposureTime	int8u
6	ISO	int8u
27	CameraTemperature	int8u
35	FocalLength	int16uRev
125	CameraOrientation	int8u
140	FocusDistanceUpper	int16uRev
142	FocusDistanceLower	int16uRev
188	WhiteBalance	int16u
192	ColorTemperature	int16u
244	PictureStyle	int8u
295	LensType	int16uRev
297	MinFocalLength	int16uRev
299	MaxFocalLength	int16uRev
539	FirmwareVersion	no
544	FirmwareVersion	no
624	FileIndex	int32u
628	FileIndex	int32u
636	DirectoryIndex	int32u
640	DirectoryIndex	int32u
912	PictureStyleInfo	Canon PSInfo2

# Canon CameraInfo750D Tags

CameraInfo tags for the EOS 750D and 760D.

Index1	Tag Name	Writable
3	FNumber	int8u
4	ExposureTime	int8u
6	ISO	int8u
27	CameraTemperature	int8u
35	FocalLength	int16uRev
150	CameraOrientation	int8u
165	FocusDistanceUpper	int16uRev
167	FocusDistanceLower	int16uRev
305	WhiteBalance	int16u
309	ColorTemperature	int16u
361	PictureStyle	int8u
388	LensType	int16uRev
390	MinFocalLength	int16uRev
392	MaxFocalLength	int16uRev
1085	FirmwareVersion	no
1097	FirmwareVersion	no

# Canon CameraInfo1000D Tags

CameraInfo tags for the EOS 1000D.

Index1	Tag Name	Writable
3	FNumber	int8u
4	ExposureTime	int8u
6	ISO	int8u
21	FlashMeteringMode	int8u
24	CameraTemperature	int8u
27	MacroMagnification	int8u
29	FocalLength	int16uRev
48	CameraOrientation	int8u
67	FocusDistanceUpper	int16uRev
69	FocusDistanceLower	int16uRev
111	WhiteBalance	int16u
115	ColorTemperature	int16u
226	LensType	int16uRev

128

#### -- ExifTool 13.24 Tag Names --

228	MinFocalLength	int16uRev
230	MaxFocalLength	int16uRev
267	FirmwareVersion	string[6]
311	DirectoryIndex	int32u
323	FileIndex	int32u
615	PictureStyleInfo	Canon PSInfo
2359	LensModel	string[64]

#### Canon CameraInfoR6 Tags

CameraInfo tags for the EOS R5 and R6.

Index1	Tag Name	Writable
2801	ShutterCount	int32u

#### Canon CameraInfoR6m2 Tags

CameraInfo tags for the EOS R6 Mark II.

Index1	Tag Name	Writable
3369	ShutterCount	int32u

#### <u>Canon</u> <u>CameraInfoG5XII</u> <u>Tags</u>

CameraInfo tags for the PowerShot G5 X Mark II.

Index1	Tag Name	Writable
659	ShutterCount	int32u
2709	ShutterCount	int32u
2849	DirectoryIndex	int32u
2861	FileIndex	int32u

#### Canon CameraInfoPowerShot Tags

CameraInfo tags for PowerShot models such as the A450, A460, A550, A560, A570, A630, A640, A650, A710, A720, G7, G9, S5, SD40, SD750, SD800, SD850, SD870, SD900, SD950, SD1000, SX100 and TX1.

Index4	Tag Name	Writable
0	ISO	int32s
5	FNumber	int32s
6	ExposureTime	int32s
23	Rotation	int32s
135 145	CameraTemperature CameraTemperature	int32s int32s

#### <u>Canon CameraInfoPowerShot2 Tags</u>

CameraInfo tags for PowerShot models such as the A470, A480, A490, A495, A580, A590, A1000, A1100, A2000, A2100, A3000, A3100, D10, E1, G10, G11, S90, S95, SD770, SD780, SD790, SD880, SD890, SD940, SD960, SD970, SD980, SD990, SD1100, SD1200, SD1300, SD1400, SD3500, SD4000, SD4500, SX1, SX10, SX20, SX110, SX120, SX130, SX200 and SX210.

Index4	Tag Name	Writable
1	ISO	int32s
6	FNumber	int32s
7	ExposureTime	int32s
24	Rotation	int32s
153	CameraTemperature	int32s
159	CameraTemperature	int32s
164	CameraTemperature	int32s
168	CameraTemperature	int32s
261	CameraTemperature	int32s

### <u>Canon</u> <u>CameraInfoUnknown32</u> <u>Tags</u>

Unknown CameraInfo tags are divided into 3 tables based on format size.

Index4	Tag Name	Writable
71	CameraTemperature	int32s
83	CameraTemperature	int32s
91	CameraTemperature	int32s
92	CameraTemperature	int32s
100	CameraTemperature	int32s
-3	CameraTemperature	int32s

#### Canon CameraInfoUnknown16 Tags

Index2	Tag Name	Writable
[no tags	known]	

#### Canon CameraInfoUnknown Tags

Index1	Tag Name	Writable
363	LensSerialNumber	undef[5]
1473	FirmwareVersion	no

### <u>Canon MovieInfo Tags</u>

Tags written by some Canon cameras when recording video.

Tag Name	Writable
FrameRate	int16u
FrameCount	int16u
FrameCount	int32u
FrameRate	rational32u
Duration	int32u
AudioBitrate	int32u
AudioSampleRate	int32u
AudioChannels	int32u
VideoCodec	undef[4]
	FrameRate FrameCount FrameCount FrameRate Duration AudioBitrate AudioSampleRate AudioChannels

### Canon AFInfo Tags

Auto-focus information used by many older Canon models. The values in this record are sequential, and some have variable sizes based on the value of NumAFPoints (which may be 1,5,7,9,15,45 or 53). The AFArea coordinates are given in a system where the image has dimensions given by AFImageWidth and AFImageHeight, and 0,0 is the image center. The direction of the Y axis depends on the camera model, with positive Y upwards for EOS models, but apparently downwards for PowerShot models.

Sequence	Tag Name	Writable
0	NumAFPoints	no
1	ValidAFPoints	no
2	CanonImageWidth	no
3	CanonImageHeight	no
4	AFImageWidth	no
5	AFImageHeight	no
6	AFAreaWidth	no
7	AFAreaHeight	no
8	AFAreaXPositions	no
9	AFAreaYPositions	no
10	AFPointsInFocus	no
11	PrimaryAFPoint	no
	Canon_AFInfo_0x000b?	no
12	PrimaryAFPoint	no

### Canon MyColors Tags

Index2	Tag Name	Writable
2	MyColorMode	int16u

### <u>Canon FaceDetect1 Tags</u>

Index2	Tag Name	Writable
2	FacesDetected	int16u
3	FaceDetectFrameSize	int16u[2]
8	FacelPosition	int16s[2]
10	Face2Position	int16s[2]
12	Face3Position	int16s[2]
14	Face4Position	int16s[2]
16	Face5Position	int16s[2]
18	Face6Position	int16s[2]
20	Face7Position	int16s[2]
22	Face8Position	int16s[2]
24	Face9Position	int16s[2]

#### Canon FaceDetect2 Tags

Index1	Tag Name	Writable
1	FaceWidth	int8u
2	FacesDetected	int8u

### Canon AFInfo2 Tags

Newer version of the AFInfo record containing much of the same information (and coordinate confusion) as the older version. In this record, NumAFPoints may be 7, 9, 11, 19, 31, 45 or 61, depending on the camera model.

Sequence	Tag Name	Writable
0	AFInfoSize?	no
1	AFAreaMode	no
2	NumAFPoints	no
3	ValidAFPoints	no
4	CanonImageWidth	no
5	CanonImageHeight	no
6	AFImageWidth	no
7	AFImageHeight	no
8	AFAreaWidths	no
9	AFAreaHeights	no
10	AFAreaXPositions	no
11	AFAreaYPositions	no
12	AFPointsInFocus	no
13	AFPointsSelected	no
	Canon_AFInfo2_0x000d?	no
14	PrimaryAFPoint	no

# <u>Canon ContrastInfo Tags</u>

Index2	Tag Name	Writable
4	IntelligentContrast	int16u

# <u>Canon WBInfo Tags</u>

WB tags for the Canon G9.

Index4	Tag Name	Writable
2	WB_GRBGLevelsAuto	int32s[4]
10	WB_GRBGLevelsDaylight	int32s[4]
18	WB_GRBGLevelsCloudy	int32s[4]
26	WB_GRBGLevelsTungsten	int32s[4]

### -- ExifTool 13.24 Tag Names --

34	WB_GRBGLevelsFluorescent	int32s[4]
42	WB_GRBGLevelsFluorHigh	int32s[4]
50	WB_GRBGLevelsFlash	int32s[4]
58	WB_GRBGLevelsUnderwater	int32s[4]
66	WB_GRBGLevelsCustom1	int32s[4]
74	WB_GRBGLevelsCustom2	int32s[4]

### Canon FaceDetect3 Tags

Index2	Tag Name	Writable
3	FacesDetected	int16u

# Canon TimeInfo Tags

Tag Name	Writable
TimeZone	int32s
TimeZoneCity	int32s
DaylightSavings	int32s
	TimeZone TimeZoneCity

### Canon FileInfo Tags

Index2	Tag Name	Writable
1	FileNumber	int32u
	ShutterCount	int32u
3	BracketMode	int16s
4	BracketValue	int16s
5	BracketShotNumber	int16s
6	RawJpgQuality	int16s
7	RawJpgSize	int16s
8	LongExposureNoiseReduction2	int16s
9	WBBracketMode	int16s
12	WBBracketValueAB	int16s
13	WBBracketValueGM	int16s
14	FilterEffect	int16s
15	ToningEffect	int16s
16	MacroMagnification	int16s
19	LiveViewShooting	int16s
20	FocusDistanceUpper	int16u
21	FocusDistanceLower	int16u
23	ShutterMode	int16s
25	FlashExposureLock	int16s
32	AntiFlicker	int16s
61	RFLensType	int16u

# Canon SerialInfo Tags

Index1	Tag Name	Writable
9	InternalSerialNumber	string

# <u>Canon CropInfo Tags</u>

Index2	Tag Name	Writable
0	CropLeftMargin	int16u
1	CropRightMargin	int16u
2	CropTopMargin	int16u
3	CropBottomMargin	int16u

# Canon AspectInfo Tags

Index4	Tag Name	Writable
0	AspectRatio	int32u
1	CroppedImageWidth	int32u
2	CroppedImageHeight	int32u
3	CroppedImageLeft	int32u

int32u

### 4 CroppedImageTop

Canon Processing Tags

Index2	Tag Name	Writable
1	ToneCurve	int16s
2	Sharpness	int16s
3	SharpnessFrequency	int16s
4	SensorRedLevel	int16s
5	SensorBlueLevel	int16s
6	WhiteBalanceRed	int16s
7	WhiteBalanceBlue	int16s
8	WhiteBalance	int16s
9	ColorTemperature	int16s
10	PictureStyle	int16s
11	DigitalGain	int16s
12	WBShiftAB	int16s
13	WBShiftGM	int16s
14	UnsharpMaskFineness	int16s
15	UnsharpMaskThreshold	int16s

### <u>Canon</u> <u>ColorBalance</u> <u>Tags</u>

These tags are used by the 10D and 300D.

Tag Name	Writable
WB_RGGBLevelsAuto	int16s[4]
WB_RGGBLevelsDaylight	int16s[4]
WB_RGGBLevelsShade	int16s[4]
WB_RGGBLevelsCloudy	int16s[4]
WB_RGGBLevelsTungsten	int16s[4]
WB_RGGBLevelsFluorescent	int16s[4]
WB_RGGBLevelsFlash	int16s[4]
WB_RGGBLevelsCustom	int16s[4]
BlackLevels	int16s[4]
WB_RGGBLevelsKelvin	int16s[4]
WB_RGGBBlackLevels	int16s[4]
	WB_RGGBLevelsAuto WB_RGGBLevelsDaylight WB_RGGBLevelsShade WB_RGGBLevelsCloudy WB_RGGBLevelsTungsten WB_RGGBLevelsFluorescent WB_RGGBLevelsFlash WB_RGGBLevelsCustom BlackLevels WB_RGGBLevelsKelvin

# Canon MeasuredColor Tags

Index2	Tag Name	Writable
1	MeasuredRGGB	int16u[4]

# Canon Flags Tags

Index2	Tag Name	Writable
1	ModifiedParamFlag	int16s

### Canon ModifiedInfo Tags

Index2	Tag Name	Writable
1	ModifiedToneCurve	int16s
2	ModifiedSharpness	int16s
3	ModifiedSharpnessFreq	int16s
4	ModifiedSensorRedLevel	int16s
5	ModifiedSensorBlueLevel	int16s
6	ModifiedWhiteBalanceRed	int16s
7	ModifiedWhiteBalanceBlue	int16s
8	ModifiedWhiteBalance	int16s
9	ModifiedColorTemp	int16s
10	ModifiedPictureStyle	int16s
11	ModifiedDigitalGain	int16s

### <u>Canon PreviewImageInfo Tags</u>

Index4	Tag Name	Writable
1	PreviewQuality	int32u
2	PreviewImageLength	int32u*
3	PreviewImageWidth	int32u
4	PreviewImageHeight	int32u
5	PreviewImageStart	int32u*

### Canon SensorInfo Tags

Index2	Tag Name	Writable
1	SensorWidth	no
2	SensorHeight	no
5	SensorLeftBorder	no
6	SensorTopBorder	no
7	SensorRightBorder	no
8	SensorBottomBorder	no
9	BlackMaskLeftBorder	no
10	BlackMaskTopBorder	no
11	BlackMaskRightBorder	no
12	BlackMaskBottomBorder	no

### Canon ColorDatal Tags

These tags are used by the 20D and 350D.

Index2	Tag Name	Writable
25	WB_RGGBLevelsAsShot	int16s[4]
29	ColorTempAsShot	int16s
30	WB_RGGBLevelsAuto	int16s[4]
34	ColorTempAuto	int16s
35	WB_RGGBLevelsDaylight	int16s[4]
39	ColorTempDaylight	int16s
40	WB_RGGBLevelsShade	int16s[4]
44	ColorTempShade	int16s
45	WB_RGGBLevelsCloudy	int16s[4]
49	ColorTempCloudy	int16s
50	WB_RGGBLevelsTungsten	int16s[4]
54	ColorTempTungsten	int16s
55	WB_RGGBLevelsFluorescent	int16s[4]
59	ColorTempFluorescent	int16s
60	WB_RGGBLevelsFlash	int16s[4]
64	ColorTempFlash	int16s
65	WB_RGGBLevelsCustom1	int16s[4]
69	ColorTempCustom1	int16s
70	WB_RGGBLevelsCustom2	int16s[4]
74	ColorTempCustom2	int16s
75	ColorCalib?	Canon ColorCalib

# Canon ColorCalib Tags

Camera color calibration data. For the 20D, 350D, 1DmkII and 1DSmkII the order of the coefficients is A, B, C, Temperature, but for newer models it is B, C, A, Temperature. These tags are extracted only when the Unknown option is used.

Index2	Tag Name	Writable
0	CameraColorCalibration01?	int16s[4]
4	CameraColorCalibration02?	int16s[4]
8	CameraColorCalibration03?	int16s[4]
12	CameraColorCalibration04?	int16s[4]
16	CameraColorCalibration05?	int16s[4]
20	CameraColorCalibration06?	int16s[4]
24	CameraColorCalibration07?	int16s[4]
28	CameraColorCalibration08?	int16s[4]
32	CameraColorCalibration09?	int16s[4]
36	CameraColorCalibration10?	int16s[4]

40	CameraColorCalibration11?	int16s[4]
44	CameraColorCalibration12?	int16s[4]
48	CameraColorCalibration13?	int16s[4]
52	CameraColorCalibration14?	int16s[4]
56	CameraColorCalibration15?	int16s[4]

# Canon ColorData2 Tags

These tags are used by the 1DmkII and 1DSmkII.

Index2	Tag Name	Writable
24	WB_RGGBLevelsAuto	int16s[4]
28	ColorTempAuto	int16s
29	WB_RGGBLevelsUnknown?	int16s[4]
33	ColorTempUnknown?	int16s
34	WB_RGGBLevelsAsShot	int16s[4]
38	ColorTempAsShot	int16s
39	WB_RGGBLevelsDaylight	int16s[4]
43	ColorTempDaylight	int16s
44	WB_RGGBLevelsShade	int16s[4]
48	ColorTempShade	int16s
49	WB_RGGBLevelsCloudy	int16s[4]
53 54	ColorTempCloudy	int16s
5 <del>4</del> 58	WB_RGGBLevelsTungsten	int16s[4] int16s
56 59	ColorTempTungsten WB_RGGBLevelsFluorescent	int16s
63	ColorTempFluorescent	int16s[4]
64	WB RGGBLevelsKelvin	int16s[4]
68	ColorTempKelvin	int16s
69	WB_RGGBLevelsFlash	int16s[4]
73	ColorTempFlash	int16s
74	WB_RGGBLevelsUnknown2?	int16s[4]
78	ColorTempUnknown2?	int16s
79	WB_RGGBLevelsUnknown3?	int16s[4]
83	ColorTempUnknown3?	int16s
84	WB_RGGBLevelsUnknown4?	int16s[4]
88	ColorTempUnknown4?	int16s
89	WB_RGGBLevelsUnknown5?	int16s[4]
93	ColorTempUnknown5?	int16s
94	WB_RGGBLevelsUnknown6?	int16s[4]
98	ColorTempUnknown6?	int16s
99	WB_RGGBLevelsUnknown7?	int16s[4]
103	ColorTempUnknown7?	int16s
104	WB_RGGBLevelsUnknown8?	int16s[4]
108	ColorTempUnknown8?	int16s
109	WB_RGGBLevelsUnknown9?	int16s[4]
113	ColorTempUnknown9?	int16s int16s[4]
114 118	WB_RGGBLevelsUnknown10? ColorTempUnknown10?	int16s(4)
119	WB_RGGBLevelsUnknown11?	int16s[4]
123	ColorTempUnknown11?	int16s
124	WB_RGGBLevelsUnknown12?	int16s[4]
128	ColorTempUnknown12?	int16s
129	WB_RGGBLevelsUnknown13?	int16s[4]
133	ColorTempUnknown13?	int16s
134	WB RGGBLevelsUnknown14?	int16s[4]
138	ColorTempUnknown14?	int16s
139	WB_RGGBLevelsUnknown15?	int16s[4]
143	ColorTempUnknown15?	int16s
144	WB_RGGBLevelsPC1	int16s[4]
148	ColorTempPC1	int16s
149	WB_RGGBLevelsPC2	int16s[4]
153	ColorTempPC2	int16s
154	WB_RGGBLevelsPC3	int16s[4]
158	ColorTempPC3	int16s
159	WB_RGGBLevelsUnknown16?	int16s[4]
163 164	ColorTempUnknown16? ColorCalib?	int16s Canon ColorCalib
164 618	RawMeasuredRGGB	int32u[4]
010	rawricabat carcob	πιοσαίτ]

# <u>Canon</u> <u>ColorData3</u> <u>Tags</u>

These tags are used by the 1DmkIIN, 5D, 30D and 400D.

Index2	Tag Name	Writable
0	 ColorDataVersion	 int16s
63	WB RGGBLevelsAsShot	int16s[4]
67	ColorTempAsShot	int16s
68	WB RGGBLevelsAuto	int16s[4]
72	ColorTempAuto	int16s
73	WB_RGGBLevelsMeasured	int16s[4]
77	ColorTempMeasured	int16s
78	WB_RGGBLevelsDaylight	int16s[4]
82	ColorTempDaylight	int16s
83	WB_RGGBLevelsShade	int16s[4]
87	ColorTempShade	int16s
88	WB_RGGBLevelsCloudy	int16s[4]
92	ColorTempCloudy	int16s
93	WB_RGGBLevelsTungsten	int16s[4]
97	ColorTempTungsten	int16s
98	WB_RGGBLevelsFluorescent	int16s[4]
102	ColorTempFluorescent	int16s
103	WB_RGGBLevelsKelvin	int16s[4]
107	ColorTempKelvin	int16s
108	WB_RGGBLevelsFlash	int16s[4]
112	ColorTempFlash	int16s
113	WB_RGGBLevelsPC1	int16s[4]
117	ColorTempPC1	int16s
118	WB_RGGBLevelsPC2	int16s[4]
122	ColorTempPC2	int16s
123	WB_RGGBLevelsPC3	int16s[4]
127	ColorTempPC3	int16s
128	WB_RGGBLevelsCustom	int16s[4]
132	ColorTempCustom	int16s
133	ColorCalib?	Canon ColorCalib
196	PerChannelBlackLevel	int16u[4]
584	FlashOutput	int16s
585	FlashBatteryLevel	int16s
586	ColorTempFlashData	int16s
647	MeasuredRGGBData	int32u[4]

# Canon ColorData4 Tags

These tags are used by the 1DmkIII, 1DSmkIII, 1DmkIV, 5DmkII, 7D, 40D, 50D, 60D, 450D, 500D, 550D, 1000D and 1100D.

Index2	Tag Name	Writable
0	ColorDataVersion	int16s
63	ColorCoefs	Canon ColorCoefs
168	ColorCalib?	Canon ColorCalib
231	AverageBlackLevel	int16u[4]
640	RawMeasuredRGGB	int32u[4]
692	PerChannelBlackLevel	int16u[4]
696	NormalWhiteLevel	int16u
697	SpecularWhiteLevel	int16u
698	LinearityUpperMargin	int16u
715	PerChannelBlackLevel	int16u[4]
719	NormalWhiteLevel	int16u
	PerChannelBlackLevel	int16u[4]
720	SpecularWhiteLevel	int16u
721	LinearityUpperMargin	int16u
723	NormalWhiteLevel	int16u
724	SpecularWhiteLevel	int16u
725	LinearityUpperMargin	int16u

### <u>Canon</u> <u>ColorCoefs</u> <u>Tags</u>

Index2	Tag Name	Writable
0	 WB RGGBLevelsAsShot	 int16s[4]
4	ColorTempAsShot	int16s
5	WB RGGBLevelsAuto	int16s[4]
9	ColorTempAuto	int16s
10	WB_RGGBLevelsMeasured	int16s[4]
14	ColorTempMeasured	int16s
15	WB_RGGBLevelsUnknown?	int16s[4]
19	ColorTempUnknown?	int16s
20	WB RGGBLevelsDaylight	int16s[4]
24	ColorTempDaylight	int16s
25	WB_RGGBLevelsShade	int16s[4]
29	_ ColorTempShade	int16s
30	WB_RGGBLevelsCloudy	int16s[4]
34	ColorTempCloudy	int16s
35	WB_RGGBLevelsTungsten	int16s[4]
39	ColorTempTungsten	int16s
40	WB_RGGBLevelsFluorescent	int16s[4]
44	ColorTempFluorescent	int16s
45	WB_RGGBLevelsKelvin	int16s[4]
49	ColorTempKelvin	int16s
50	WB_RGGBLevelsFlash	int16s[4]
54	ColorTempFlash	int16s
55	WB_RGGBLevelsUnknown2?	int16s[4]
59	ColorTempUnknown2?	int16s
60	WB_RGGBLevelsUnknown3?	int16s[4]
64	ColorTempUnknown3?	int16s
65	WB_RGGBLevelsUnknown4?	int16s[4]
69	ColorTempUnknown4?	int16s
70	WB_RGGBLevelsUnknown5?	int16s[4]
74	ColorTempUnknown5?	int16s
75	WB_RGGBLevelsUnknown6?	int16s[4]
79	ColorTempUnknown6?	int16s
80	WB_RGGBLevelsUnknown7?	int16s[4]
84	ColorTempUnknown7?	int16s
85	WB_RGGBLevelsUnknown8?	int16s[4]
89	ColorTempUnknown8?	int16s
90	WB_RGGBLevelsUnknown9?	int16s[4]
94	ColorTempUnknown9?	int16s
95	WB_RGGBLevelsUnknown10?	int16s[4]
99	ColorTempUnknown10?	int16s
100	WB_RGGBLevelsUnknown11?	int16s[4]
104	ColorTempUnknown11?	int16s
105	WB_RGGBLevelsUnknown12?	int16s[4]
109	ColorTempUnknown12?	int16s
110	WB_RGGBLevelsUnknown13?	int16s[4]
114	ColorTempUnknown13?	int16s

# <u>Canon</u> <u>ColorData5</u> <u>Tags</u>

These tags are used by many EOS  $\ensuremath{\mathrm{M}}$  and PowerShot models.

Index2	Tag Name	Writable
0	ColorDataVersion	int16s
71	ColorCoefs	Canon ColorCoefs
	ColorCoefs2	Canon ColorCoefs2
186	ColorCalib2?	Canon ColorCalib2
255	ColorCalib2?	Canon ColorCalib2
264	PerChannelBlackLevel	int16s[4]
333	PerChannelBlackLevel	int16s[4]
662	SpecularWhiteLevel	int16u
1385	NormalWhiteLevel	int16u
1386	SpecularWhiteLevel	int16u

# <u>Canon</u> <u>ColorCoefs2</u> <u>Tags</u>

Index2	Tag Name	Writa	ble

•		
0	WB_RGGBLevelsAsShot	int16s[4]
7	ColorTempAsShot	int16s
8	WB_RGGBLevelsAuto	int16s[4]
15	ColorTempAuto	int16s
16	WB_RGGBLevelsMeasured	int16s[4]
23	ColorTempMeasured	int16s
24	WB_RGGBLevelsUnknown?	int16s[4]
31	ColorTempUnknown?	int16s
32	WB_RGGBLevelsDaylight	int16s[4]
39	ColorTempDaylight	int16s
40	WB_RGGBLevelsShade	int16s[4]
47	ColorTempShade	int16s
48	WB RGGBLevelsCloudy	int16s[4]
55	ColorTempCloudy	int16s
56	WB_RGGBLevelsTungsten	int16s[4]
63	ColorTempTungsten	int16s
64	WB RGGBLevelsFluorescent	int16s[4]
71	ColorTempFluorescent	int16s
72	WB RGGBLevelsKelvin	int16s[4]
79	ColorTempKelvin	int16s
80	WB_RGGBLevelsFlash	int16s[4]
87	ColorTempFlash	int16s
88	WB_RGGBLevelsUnknown2?	int16s[4]
95	ColorTempUnknown2?	int16s[4]
95 96	WB_RGGBLevelsUnknown3?	int16s[4]
103	ColorTempUnknown3?	int16s[4]
103	WB RGGBLevelsUnknown4?	int16s[4]
111	ColorTempUnknown4?	int16s[4]
112	WB_RGGBLevelsUnknown5?	
		int16s[4]
119	ColorTempUnknown5?	int16s
120	WB_RGGBLevelsUnknown6?	int16s[4]
127	ColorTempUnknown6?	int16s
128	WB_RGGBLevelsUnknown7?	int16s[4]
135	ColorTempUnknown7?	int16s
136	WB_RGGBLevelsUnknown8?	int16s[4]
143	ColorTempUnknown8?	int16s
144	WB_RGGBLevelsUnknown9?	int16s[4]
151	ColorTempUnknown9?	int16s
152	WB_RGGBLevelsUnknown10?	int16s[4]
159	ColorTempUnknown10?	int16s
160	WB_RGGBLevelsUnknown11?	int16s[4]
167	ColorTempUnknown11?	int16s
168	WB_RGGBLevelsUnknown12?	int16s[4]
175	ColorTempUnknown12?	int16s
176	WB_RGGBLevelsUnknown13?	int16s[4]
183	ColorTempUnknown13?	int16s

# Canon ColorCalib2 Tags

# B, C, A, D, Temperature.

Index2	Tag Name	Writable
0	CameraColorCalibration01?	int16s[5]
5	CameraColorCalibration02?	int16s[5]
10	CameraColorCalibration03?	int16s[5]
15	CameraColorCalibration04?	int16s[5]
20	CameraColorCalibration05?	int16s[5]
25	CameraColorCalibration06?	int16s[5]
30	CameraColorCalibration07?	int16s[5]
35	CameraColorCalibration08?	int16s[5]
40	CameraColorCalibration09?	int16s[5]
45	CameraColorCalibration10?	int16s[5]
50	CameraColorCalibration11?	int16s[5]
55	CameraColorCalibration12?	int16s[5]
60	CameraColorCalibration13?	int16s[5]
65	CameraColorCalibration14?	int16s[5]
70	CameraColorCalibration15?	int16s[5]

These tags are used by the EOS 600D and 1200D.

Index2	Tag Name	Writable
0	ColorDataVersion	int16s
63	WB RGGBLevelsAsShot	int16s[4]
67	ColorTempAsShot	int16s
68	WB_RGGBLevelsAuto	int16s[4]
72	ColorTempAuto	int16s
73	WB_RGGBLevelsMeasured	int16s[4]
77	ColorTempMeasured	int16s
78	WB_RGGBLevelsUnknown?	int16s[4]
82	ColorTempUnknown?	int16s
83	WB_RGGBLevelsUnknown2?	int16s[4]
87	ColorTempUnknown2?	int16s
88	WB_RGGBLevelsUnknown3?	int16s[4]
92	ColorTempUnknown3?	int16s
93	WB_RGGBLevelsUnknown4?	int16s[4]
97	ColorTempUnknown4?	int16s
98	WB_RGGBLevelsUnknown5?	int16s[4]
102	ColorTempUnknown5?	int16s
103	WB_RGGBLevelsDaylight	int16s[4]
107	ColorTempDaylight	int16s
108	WB_RGGBLevelsShade	int16s[4]
112	ColorTempShade	int16s
113	WB_RGGBLevelsCloudy	int16s[4]
117	ColorTempCloudy	int16s
118	WB_RGGBLevelsTungsten	int16s[4]
122	ColorTempTungsten	int16s
123	WB_RGGBLevelsFluorescent	int16s[4]
127	ColorTempFluorescent	int16s
128	WB_RGGBLevelsKelvin	int16s[4]
132	ColorTempKelvin	int16s
133	WB_RGGBLevelsFlash	int16s[4]
137	ColorTempFlash	int16s
138	WB_RGGBLevelsUnknown6?	int16s[4]
142 143	ColorTempUnknown6? WB RGGBLevelsUnknown7?	int16s int16s[4]
143	<pre>ColorTempUnknown7?</pre>	int16s[4]
148	WB_RGGBLevelsUnknown8?	int16s[4]
152	ColorTempUnknown8?	int16s
152	WB_RGGBLevelsUnknown9?	int16s[4]
157	ColorTempUnknown9?	int16s
158	WB RGGBLevelsUnknown10?	int16s[4]
162	ColorTempUnknown10?	int16s
163	WB_RGGBLevelsUnknown11?	int16s[4]
167	ColorTempUnknown11?	int16s
168	WB_RGGBLevelsUnknown12?	int16s[4]
172	ColorTempUnknown12?	int16s
173	WB RGGBLevelsUnknown13?	int16s[4]
177	ColorTempUnknown13?	int16s
178	WB_RGGBLevelsUnknown14?	int16s[4]
182	ColorTempUnknown14?	int16s
183	WB_RGGBLevelsUnknown15?	int16s[4]
187	ColorTempUnknown15?	int16s
188	ColorCalib?	Canon ColorCalib
251	AverageBlackLevel	int16u[4]
404	RawMeasuredRGGB	int32u[4]
479	PerChannelBlackLevel	int16u[4]
483	NormalWhiteLevel	int16u
484	SpecularWhiteLevel	int16u
485	LinearityUpperMargin	int16u

# Canon ColorData7 Tags

These tags are used by the EOS 1DX, 5DmkIII, 6D, 7DmkII, 100D, 650D, 700D, 8000D, M and M2.

0	ColorDataVersion	int16s
63	WB_RGGBLevelsAsShot	int16s[4]
67	ColorTempAsShot	int16s
68	WB_RGGBLevelsAuto	int16s[4]
72	ColorTempAuto	int16s
73	WB_RGGBLevelsMeasured	int16s[4]
77	ColorTempMeasured	int16s
78	WB_RGGBLevelsUnknown?	int16s[4]
82	ColorTempUnknown?	int16s
83	WB_RGGBLevelsUnknown2?	int16s[4]
87	ColorTempUnknown2?	int16s
88	WB_RGGBLevelsUnknown3?	int16s[4]
92	ColorTempUnknown3?	int16s
93	WB_RGGBLevelsUnknown4?	int16s[4]
97	ColorTempUnknown4?	int16s
98	WB_RGGBLevelsUnknown5?	int16s[4]
102	ColorTempUnknown5?	int16s int16s[4]
103	WB_RGGBLevelsUnknown6?	
107	ColorTempUnknown6?	int16s
108	WB_RGGBLevelsUnknown7?	int16s[4]
112	ColorTempUnknown7?	int16s
113	WB_RGGBLevelsUnknown8?	int16s[4] int16s
117	ColorTempUnknown8?	
118	WB_RGGBLevelsUnknown9?	int16s[4]
122	ColorTempUnknown9?	int16s
123	WB_RGGBLevelsUnknown10?	int16s[4]
127	ColorTempUnknown10?	int16s
128	WB_RGGBLevelsDaylight	int16s[4] int16s
132 133	ColorTempDaylight WB RGGBLevelsShade	int16s int16s[4]
137	WB_RGGBLevelsShade ColorTempShade	int16s[4]
137	WB_RGGBLevelsCloudy	int16s[4]
142	WB_RGGBLEVEISCIOUDY ColorTempCloudy	int16s[4]
142	WB_RGGBLevelsTungsten	int16s[4]
143	ColorTempTungsten	int16s[4]
148	WB_RGGBLevelsFluorescent	int16s[4]
152	ColorTempFluorescent	int16s
153	WB RGGBLevelsKelvin	int16s[4]
157	ColorTempKelvin	int16s
158	WB_RGGBLevelsFlash	int16s[4]
162	ColorTempFlash	int16s
163	WB RGGBLevelsUnknown11?	int16s[4]
167	ColorTempUnknown11?	int16s
168	WB RGGBLevelsUnknown12?	int16s[4]
172	ColorTempUnknown12?	int16s
173	WB RGGBLevelsUnknown13?	int16s[4]
177	ColorTempUnknown13?	int16s
178	WB RGGBLevelsUnknown14?	int16s[4]
182	ColorTempUnknown14?	int16s
183	WB_RGGBLevelsUnknown15?	int16s[4]
187	ColorTempUnknown15?	int16s
188	WB_RGGBLevelsUnknown16?	int16s[4]
192	ColorTempUnknown16?	int16s
193	WB RGGBLevelsUnknown17?	int16s[4]
197	ColorTempUnknown17?	int16s
198	WB_RGGBLevelsUnknown18?	int16s[4]
202	ColorTempUnknown18?	int16s
203	WB_RGGBLevelsUnknown19?	int16s[4]
207	ColorTempUnknown19?	int16s
208	WB_RGGBLevelsUnknown20?	int16s[4]
212	ColorTempUnknown20?	int16s
213	ColorCalib?	Canon ColorCalib
276	AverageBlackLevel	int16u[4]
429	RawMeasuredRGGB	int32u[4]
504	PerChannelBlackLevel	int16u[4]
508	NormalWhiteLevel	int16u
509	SpecularWhiteLevel	int16u
510	LinearityUpperMargin	int16u
619	RawMeasuredRGGB	int32u[4]

728	PerChannelBlackLevel	int16u[4]
732	NormalWhiteLevel	int16u
733	SpecularWhiteLevel	int16u
734	LinearityUpperMargin	int16u

### Canon ColorData8 Tags

These tags are used by the EOS 1DXmkII, 5DS, 5DSR, 5DmkIV, 6DmkII, 77D, 80D, 200D, 800D, 1300D, 2000D, 4000D and 9000D.

	, , , , , , , , , , , , , , , , , , , ,	
Index2	Tag Name	Writable
0	ColorDataVersion	int16s
63	WB_RGGBLevelsAsShot	int16s[4]
67		int16s
68	WB_RGGBLevelsAuto	int16s[4]
72	ColorTempAuto	int16s
73	WB_RGGBLevelsMeasured	int16s[4]
77	ColorTempMeasured	int16s
78	WB_RGGBLevelsUnknown?	int16s[4]
82	ColorTempUnknown?	int16s
83	WB_RGGBLevelsUnknown2?	int16s[4]
87	ColorTempUnknown2?	int16s
88	WB_RGGBLevelsUnknown3?	int16s[4]
92	ColorTempUnknown3?	int16s
93	WB_RGGBLevelsUnknown4?	int16s[4]
97	ColorTempUnknown4?	int16s
98 102	WB_RGGBLevelsUnknown5?	int16s[4] int16s
102	ColorTempUnknown5? WB_RGGBLevelsUnknown6?	int16s[4]
103	ColorTempUnknown6?	int16s[4]
107	WB RGGBLevelsUnknown7?	int16s[4]
112	ColorTempUnknown7?	int16s
113	WB_RGGBLevelsUnknown8?	int16s[4]
117	ColorTempUnknown8?	int16s
118	WB_RGGBLevelsUnknown9?	int16s[4]
122	ColorTempUnknown9?	int16s
123	WB_RGGBLevelsUnknown10?	int16s[4]
127	ColorTempUnknown10?	int16s
128	WB_RGGBLevelsUnknown11?	int16s[4]
132	ColorTempUnknown11?	int16s
133	WB_RGGBLevelsDaylight	int16s[4]
137	ColorTempDaylight	int16s
138	WB_RGGBLevelsShade	int16s[4]
142	ColorTempShade	int16s
143	WB_RGGBLevelsCloudy	int16s[4]
147	ColorTempCloudy	int16s
148 152	WB_RGGBLevelsTungsten ColorTempTungsten	int16s[4] int16s
152	WB_RGGBLevelsFluorescent	int16s[4]
157	ColorTempFluorescent	int16s
158	WB_RGGBLevelsKelvin	int16s[4]
162	ColorTempKelvin	int16s
163	WB_RGGBLevelsFlash	int16s[4]
167	ColorTempFlash	int16s
168	WB_RGGBLevelsUnknown12?	int16s[4]
172	ColorTempUnknown12?	int16s
173	WB_RGGBLevelsUnknown13?	int16s[4]
177	ColorTempUnknown13?	int16s
178	WB_RGGBLevelsUnknown14?	int16s[4]
182	ColorTempUnknown14?	int16s
183	WB_RGGBLevelsUnknown15?	int16s[4]
187	ColorTempUnknown15?	int16s
188	WB_RGGBLevelsUnknown16?	int16s[4]
192	ColorTempUnknown16?	int16s
193 197	WB_RGGBLevelsUnknown17?	int16s[4]
197	ColorTempUnknown17?	int16s
198 202	WB_RGGBLevelsUnknown18? ColorTempUnknown18?	int16s[4] int16s
202	WB_RGGBLevelsUnknown19?	int16s[4]
203	"D_IOODDICACTOOMITTA:	THUTUS[4]

207	ColorTempUnknown19?	int16s
207	WB RGGBLevelsUnknown20?	int16s[4]
212	ColorTempUnknown20?	int16s
213	WB RGGBLevelsUnknown21?	int16s[4]
217	ColorTempUnknown21?	int16s
218	WB RGGBLevelsUnknown22?	int16s[4]
222	ColorTempUnknown22?	int16s
223	WB RGGBLevelsUnknown23?	int16s[4]
227	ColorTempUnknown23?	int16s
228	WB RGGBLevelsUnknown24?	int16s[4]
232	ColorTempUnknown24?	int16s
233	WB_RGGBLevelsUnknown25?	int16s[4]
237	ColorTempUnknown25?	int16s
238	WB RGGBLevelsUnknown26?	int16s[4]
242	ColorTempUnknown26?	int16s
243	WB RGGBLevelsUnknown27?	int16s[4]
247	ColorTempUnknown27?	int16s
248	WB_RGGBLevelsUnknown28?	int16s[4]
252	ColorTempUnknown28?	int16s
253	WB_RGGBLevelsUnknown29?	int16s[4]
257	ColorTempUnknown29?	int16s
258	WB_RGGBLevelsUnknown30?	int16s[4]
262	ColorTempUnknown30?	int16s
263	ColorCalib?	Canon ColorCalib
326	AverageBlackLevel	int16u[4]
556	PerChannelBlackLevel	int16u[4]
560	NormalWhiteLevel	int16u
561	SpecularWhiteLevel	int16u
562	LinearityUpperMargin	int16u
778	PerChannelBlackLevel	int16u[4]
782	NormalWhiteLevel	int16u
783	SpecularWhiteLevel	int16u
784	LinearityUpperMargin	int16u

# Canon ColorData9 Tags

These tags are used by the M6mkII, M50, M200, EOS R, RP, 90D, 250D and 850D

Index2	Tag Name	Writable
0	ColorDataVersion	int16s
71	WB RGGBLevelsAsShot	int16s[4]
75	ColorTempAsShot	int16s
76	WB RGGBLevelsAuto	int16s[4]
80	 ColorTempAuto	int16s
81	WB_RGGBLevelsMeasured	int16s[4]
85	ColorTempMeasured	int16s
86	WB_RGGBLevelsUnknown?	int16s[4]
90	ColorTempUnknown?	int16s
91	WB_RGGBLevelsUnknown2?	int16s[4]
95	ColorTempUnknown2?	int16s
96	WB_RGGBLevelsUnknown3?	int16s[4]
100	ColorTempUnknown3?	int16s
101	WB_RGGBLevelsUnknown4?	int16s[4]
105	ColorTempUnknown4?	int16s
106	WB_RGGBLevelsUnknown5?	int16s[4]
110	ColorTempUnknown5?	int16s
111	WB_RGGBLevelsUnknown6?	int16s[4]
115	ColorTempUnknown6?	int16s
116	WB_RGGBLevelsUnknown7?	int16s[4]
120	ColorTempUnknown7?	int16s
121	WB_RGGBLevelsUnknown8?	int16s[4]
125	ColorTempUnknown8?	int16s
126	WB_RGGBLevelsUnknown9?	int16s[4]
130	ColorTempUnknown9?	int16s
131	WB_RGGBLevelsUnknown10?	int16s[4]
135	ColorTempUnknown10?	int16s
136	WB_RGGBLevelsDaylight	int16s[4]
140	ColorTempDaylight	int16s

141	WB_RGGBLevelsShade	int16s[4]
145	_ ColorTempShade	int16s
146	WB RGGBLevelsCloudy	int16s[4]
150	ColorTempCloudy	int16s
151	WB_RGGBLevelsTungsten	int16s[4]
155	ColorTempTungsten	int16s
156	WB_RGGBLevelsFluorescent	int16s[4]
160	ColorTempFluorescent	int16s
161	WB_RGGBLevelsKelvin	int16s[4]
165	ColorTempKelvin	int16s
166	WB RGGBLevelsFlash	int16s[4]
170	 ColorTempFlash	int16s
171	WB RGGBLevelsUnknown11?	int16s[4]
175	ColorTempUnknown11?	int16s
176	WB_RGGBLevelsUnknown12?	int16s[4]
180	ColorTempUnknown12?	int16s
181	WB_RGGBLevelsUnknown13?	int16s[4]
185	ColorTempUnknown13?	int16s
186	WB RGGBLevelsUnknown14?	int16s[4]
190	ColorTempUnknown14?	int16s
191	WB RGGBLevelsUnknown15?	int16s[4]
195	ColorTempUnknown15?	int16s
196	WB_RGGBLevelsUnknown16?	int16s[4]
200	ColorTempUnknown16?	int16s
201	WB_RGGBLevelsUnknown17?	int16s[4]
205	ColorTempUnknown17?	int16s
206	WB RGGBLevelsUnknown18?	int16s[4]
210	ColorTempUnknown18?	int16s
211	WB_RGGBLevelsUnknown19?	int16s[4]
215	ColorTempUnknown19?	int16s
216	WB_RGGBLevelsUnknown20?	int16s[4]
220	ColorTempUnknown20?	int16s
221	WB RGGBLevelsUnknown21?	int16s[4]
225	ColorTempUnknown21?	int16s
226	WB_RGGBLevelsUnknown22?	int16s[4]
230	ColorTempUnknown22?	int16s
231	WB_RGGBLevelsUnknown23?	int16s[4]
235	ColorTempUnknown23?	int16s
236	WB RGGBLevelsUnknown24?	int16s[4]
240	ColorTempUnknown24?	int16s
240	WB_RGGBLevelsUnknown25?	int16s[4]
245	ColorTempUnknown25?	int16s
245	WB_RGGBLevelsUnknown26?	int16s[4]
250	ColorTempUnknown26?	int16s
251	WB RGGBLevelsUnknown27?	int16s[4]
255	ColorTempUnknown27?	int16s[4]
256	WB_RGGBLevelsUnknown28?	int16s[4]
		int16s[4]
260 261	ColorTempUnknown28? WB RGGBLevelsUnknown29?	int16s[4]
	ColorTempUnknown29?	
265	ColorCalib?	int16s
266		Canon ColorCalib
329	PerChannelBlackLevel	int16u[4]
796	NormalWhiteLevel	int16u
797	SpecularWhiteLevel	int16u
798	LinearityUpperMargin	int16u

# $\underline{\texttt{Canon}} \ \underline{\texttt{ColorData10}} \ \underline{\texttt{Tags}}$

These tags are used by the R5, R5 and EOS 1DXmkIII.

Index2	Tag Name	Writable
0	ColorDataVersion	int16s
85	WB_RGGBLevelsAsShot	int16s[4]
89	ColorTempAsShot	int16s
90	WB_RGGBLevelsAuto	int16s[4]
94	ColorTempAuto	int16s
95	WB_RGGBLevelsMeasured	int16s[4]
99	ColorTempMeasured	int16s
100	WB_RGGBLevelsUnknown?	int16s[4]

	ExifTool 13.	24 Tag	Names	
104	ColorTempUnknown?			int16s
105	WB_RGGBLevelsUnknown2?			int16s[4]
109	ColorTempUnknown2?			int16s
110	WB_RGGBLevelsUnknown3?			int16s[4]
114	ColorTempUnknown3?			int16s
115	WB_RGGBLevelsUnknown4?			int16s[4]
119	ColorTempUnknown4?			int16s
120	WB_RGGBLevelsUnknown5?			int16s[4]
124	ColorTempUnknown5?			int16s[4]
	<del>-</del>			int16s[4]
125	WB_RGGBLevelsUnknown6?			
129	ColorTempUnknown6?			int16s
130	WB_RGGBLevelsUnknown7?			int16s[4]
134	ColorTempUnknown7?			int16s
135	WB_RGGBLevelsUnknown8?			int16s[4]
139	ColorTempUnknown8?			int16s
140	WB_RGGBLevelsUnknown9?			int16s[4]
144	ColorTempUnknown9?			int16s
145	WB_RGGBLevelsUnknown10	?		int16s[4]
149	ColorTempUnknown10?			int16s
150	WB_RGGBLevelsDaylight			int16s[4]
154	ColorTempDaylight			int16s
155	WB_RGGBLevelsShade			int16s[4]
159	ColorTempShade			int16s
160	WB_RGGBLevelsCloudy			int16s[4]
164	ColorTempCloudy			int16s
165	WB_RGGBLevelsTungsten			int16s[4]
169	ColorTempTungsten			int16s
170	WB_RGGBLevelsFluoresce	nt		int16s[4]
174	ColorTempFluorescent			int16s
175	WB_RGGBLevelsKelvin			int16s[4]
179	ColorTempKelvin			int16s
180	WB_RGGBLevelsFlash			int16s[4]
184	ColorTempFlash			int16s
185	WB_RGGBLevelsUnknown11	?		int16s[4]
189	ColorTempUnknown11?			int16s
190	WB_RGGBLevelsUnknown12	?		int16s[4]
194	ColorTempUnknown12?			int16s
195	WB_RGGBLevelsUnknown13	?		int16s[4]
199	ColorTempUnknown13?			int16s
200	WB_RGGBLevelsUnknown14	?		int16s[4]
204	ColorTempUnknown14?			int16s
205	WB_RGGBLevelsUnknown15	?		int16s[4]
209	ColorTempUnknown15?			int16s
210	WB_RGGBLevelsUnknown16	?		int16s[4]
214	ColorTempUnknown16?			int16s
215	WB_RGGBLevelsUnknown17	?		int16s[4]
219	ColorTempUnknown17?			int16s
220	WB_RGGBLevelsUnknown18	?		int16s[4]
224	ColorTempUnknown18?			int16s
225	WB_RGGBLevelsUnknown19	?		int16s[4]
229	ColorTempUnknown19?			int16s
230	WB_RGGBLevelsUnknown20	?		int16s[4]
234	ColorTempUnknown20?			int16s
235	WB_RGGBLevelsUnknown21	?		int16s[4]
239	ColorTempUnknown21?			int16s
240	WB_RGGBLevelsUnknown22	?		int16s[4]
244	ColorTempUnknown22?			int16s
245	WB_RGGBLevelsUnknown23	?		int16s[4]
249	ColorTempUnknown23?			int16s
250	WB_RGGBLevelsUnknown24	?		int16s[4]
254	ColorTempUnknown24?			int16s
255	WB_RGGBLevelsUnknown25	?		int16s[4]
259	ColorTempUnknown25?	_		int16s
260	WB_RGGBLevelsUnknown26	?		int16s[4]
264	ColorTempUnknown26?	_		int16s
265	WB_RGGBLevelsUnknown27	?		int16s[4]
269	ColorTempUnknown27?	_		int16s
270	WB_RGGBLevelsUnknown28	<b>:</b>		int16s[4]
274	ColorTempUnknown28?	2		int16s
275	WB_RGGBLevelsUnknown29	•		int16s[4]

279	ColorTempUnknown29?	int16s
280	ColorCalib?	Canon ColorCalib
343	PerChannelBlackLevel	int16u[4]
810	NormalWhiteLevel	int16u
811	SpecularWhiteLevel	int16u
812	LinearityUpperMargin	int16u

# Canon ColorDatall Tags

These tags are used by the EOS R3, R7 and R6mkII

5	,	
Index2	Tag Name	Writable
	Calambata Wanaian	
105	ColorDataVersion	int16s
105	WB_RGGBLevelsAsShot	int16s[4] int16s
109	ColorTempAsShot	
110	WB_RGGBLevelsAuto	int16s[4]
114	ColorTempAuto	int16s
115	WB_RGGBLevelsMeasured	int16s[4]
119	ColorTempMeasured	int16s
120	WB_RGGBLevelsUnknown?	int16s[4]
124	ColorTempUnknown?	int16s
125	WB_RGGBLevelsUnknown2?	int16s[4]
129	ColorTempUnknown2?	int16s
130	WB_RGGBLevelsUnknown3?	int16s[4]
134	ColorTempUnknown3?	int16s
135	WB_RGGBLevelsUnknown4?	int16s[4]
139	ColorTempUnknown4?	int16s
140	WB_RGGBLevelsUnknown5?	int16s[4]
144	ColorTempUnknown5?	int16s
145	WB_RGGBLevelsUnknown6?	int16s[4]
149	ColorTempUnknown6?	int16s
150	WB_RGGBLevelsUnknown7?	int16s[4]
154	ColorTempUnknown7?	int16s
155	WB_RGGBLevelsUnknown8?	int16s[4]
159	ColorTempUnknown8?	int16s
160	WB_RGGBLevelsUnknown9?	int16s[4]
164	ColorTempUnknown9?	int16s
165	WB_RGGBLevelsUnknown10?	int16s[4]
169	ColorTempUnknown10?	int16s
170	WB_RGGBLevelsUnknown11?	int16s[4]
174	ColorTempUnknown11?	int16s
175	WB_RGGBLevelsUnknown11?	int16s[4]
179	ColorTempUnknown11?	int16s
180	WB_RGGBLevelsUnknown12?	int16s[4]
184	ColorTempUnknown12?	int16s
185	WB_RGGBLevelsUnknown13?	int16s[4]
189	ColorTempUnknown13?	int16s
190	WB_RGGBLevelsUnknown14?	int16s[4]
194	ColorTempUnknown14?	int16s
195	WB_RGGBLevelsUnknown15?	int16s[4]
199	ColorTempUnknown15?	int16s
200	WB_RGGBLevelsUnknown16?	int16s[4]
204	ColorTempUnknown16?	int16s
205	WB_RGGBLevelsDaylight	int16s[4]
209	ColorTempDaylight	int16s
210	WB_RGGBLevelsShade	int16s[4]
214	ColorTempShade	int16s
215	WB_RGGBLevelsCloudy	int16s[4]
219	ColorTempCloudy	int16s
220	WB_RGGBLevelsTungsten	int16s[4]
224	ColorTempTungsten	int16s
225	WB_RGGBLevelsFluorescent	int16s[4]
229	ColorTempFluorescent	int16s
230	WB_RGGBLevelsKelvin	int16s[4]
234	ColorTempKelvin	int16s
235	WB_RGGBLevelsFlash	int16s[4]
239	ColorTempFlash	int16s
240	WB_RGGBLevelsUnknown17?	int16s[4]
244	ColorTempUnknown17?	int16s

245	WB_RGGBLevelsUnknown18?	int16s[4]
249	ColorTempUnknown18?	int16s
250	WB_RGGBLevelsUnknown19?	int16s[4]
254	ColorTempUnknown19?	int16s
255	WB_RGGBLevelsUnknown20?	int16s[4]
259	ColorTempUnknown20?	int16s
260	WB_RGGBLevelsUnknown21?	int16s[4]
264	ColorTempUnknown21?	int16s
265	WB_RGGBLevelsUnknown22?	int16s[4]
269	ColorTempUnknown22?	int16s
270	WB_RGGBLevelsUnknown23?	int16s[4]
274	ColorTempUnknown23?	int16s
275	WB_RGGBLevelsUnknown24?	int16s[4]
279	ColorTempUnknown24?	int16s
280	WB_RGGBLevelsUnknown25?	int16s[4]
284	ColorTempUnknown25?	int16s
285	WB_RGGBLevelsUnknown26?	int16s[4]
289	ColorTempUnknown26?	int16s
290	WB_RGGBLevelsUnknown27?	int16s[4]
294	ColorTempUnknown27?	int16s
300	ColorCalib?	Canon ColorCalib
363	PerChannelBlackLevel	int16u[4]
640	NormalWhiteLevel	int16u
641	SpecularWhiteLevel	int16u
642	LinearityUpperMargin	int16u

# <u>Canon</u> <u>ColorData12</u> <u>Tags</u>

These tags are used by the EOS R1 and R5mkII  $\,$ 

Index2	Tag Name	Writable
0	ColorDataVersion	int16s
105	WB_RGGBLevelsAsShot	int16s[4]
109	ColorTempAsShot	int16s
110	WB_RGGBLevelsDaylight	int16s[4]
114	ColorTempDaylight	int16s
115	WB_RGGBLevelsShade	int16s[4]
119	ColorTempShade	int16s
120	WB_RGGBLevelsCloudy	int16s[4]
124	ColorTempCloudy	int16s
125	WB_RGGBLevelsTungsten	int16s[4]
129	ColorTempTungsten	int16s
130	WB_RGGBLevelsFluorescent	int16s[4]
134	ColorTempFluorescent	int16s
135	WB_RGGBLevelsFlash	int16s[4]
139	ColorTempFlash	int16s
140	WB_RGGBLevelsUnknown2?	int16s[4]
144	ColorTempUnknown2?	int16s
145	WB_RGGBLevelsUnknown3?	int16s[4]
149	ColorTempUnknown3?	int16s
150	WB_RGGBLevelsUnknown4?	int16s[4]
154	ColorTempUnknown4?	int16s
155	WB_RGGBLevelsUnknown5?	int16s[4]
159	ColorTempUnknown5?	int16s
160	WB_RGGBLevelsUnknown6?	int16s[4]
164	ColorTempUnknown6?	int16s
165	WB_RGGBLevelsUnknown7?	int16s[4]
169	ColorTempUnknown7?	int16s
170	WB_RGGBLevelsUnknown8?	int16s[4]
174	ColorTempUnknown8?	int16s
175	WB_RGGBLevelsUnknown9?	int16s[4]
179	ColorTempUnknown9?	int16s
180	WB_RGGBLevelsUnknown10?	int16s[4]
184	ColorTempUnknown10?	int16s
185	WB_RGGBLevelsUnknown11?	int16s[4]
189	ColorTempUnknown11?	int16s
190	WB_RGGBLevelsUnknown12?	int16s[4]
194	ColorTempUnknown12?	int16s
195	WB_RGGBLevelsUnknown13?	int16s[4]

199	ColorTempUnknown13?	int16s
200	WB_RGGBLevelsUnknown14?	int16s[4]
204	ColorTempUnknown14?	int16s
205	WB_RGGBLevelsUnknown15?	int16s[4]
209	ColorTempUnknown15?	int16s
210	WB_RGGBLevelsUnknown16?	int16s[4]
214	ColorTempUnknown16?	int16s
215	WB RGGBLevelsUnknown17?	int16s[4]
219	ColorTempUnknown17?	int16s
220	WB RGGBLevelsUnknown18?	int16s[4]
224	ColorTempUnknown18?	int16s
225	WB_RGGBLevelsUnknown19?	int16s[4]
229	ColorTempUnknown19?	int16s
230	WB_RGGBLevelsUnknown20?	int16s[4]
234	ColorTempUnknown20?	int16s
235	WB_RGGBLevelsUnknown21?	int16s[4]
239	ColorTempUnknown21?	int16s
240	WB RGGBLevelsUnknown22?	int16s[4]
244	ColorTempUnknown22?	int16s
245	WB_RGGBLevelsUnknown23?	int16s[4]
249	ColorTempUnknown23?	int16s
250	WB RGGBLevelsUnknown24?	int16s[4]
254		
	ColorTempUnknown24?	int16s
255	WB_RGGBLevelsUnknown25?	int16s[4]
259	ColorTempUnknown25?	int16s
260	WB_RGGBLevelsUnknown26?	int16s[4]
264	ColorTempUnknown26?	int16s
265	WB_RGGBLevelsUnknown27?	int16s[4]
269	ColorTempUnknown27?	int16s
270	WB RGGBLevelsUnknown28?	int16s[4]
274	ColorTempUnknown28?	int16s
275	WB RGGBLevelsUnknown29?	int16s[4]
279	ColorTempUnknown29?	int16s
280	WB RGGBLevelsUnknown30?	int16s[4]
284	<del></del>	int16s
_	ColorTempUnknown30?	
285	WB_RGGBLevelsUnknown31?	int16s[4]
289	ColorTempUnknown31?	int16s
290	WB_RGGBLevelsUnknown32?	int16s[4]
294	ColorTempUnknown32?	int16s
295	WB_RGGBLevelsUnknown33?	int16s[4]
299	ColorTempUnknown33?	int16s
320	ColorCalib?	Canon ColorCalib
383	PerChannelBlackLevel	int16u[4]
660	NormalWhiteLevel	int16u
661	SpecularWhiteLevel	int16u
662	LinearityUpperMargin	int16u
002	ninear rely opportuar arm	111C1 V U

# Canon ColorDataUnknown Tags

Index2	Tag Name	Writable
0	ColorDataVersion	no

# Canon ColorInfo Tags

Index2	Tag Name	Writable
1	Saturation	int16s
2	ColorTone	int16s
3	ColorSpace	int16s

# Canon AFMicroAdj Tags

Tag Name	Writable
AFMicroAdjMode	int32s
AFMicroAdjValue	rational64s
	 AFMicroAdjMode

# Canon VignettingCorr Tags

This information is found in images from newer EOS models.

Index2	Tag Name	Writable
0	VignettingCorrVersion	no
2	PeripheralLighting	int16s
3	DistortionCorrection	int16s
4	ChromaticAberrationCorr	int16s
5	ChromaticAberrationCorr	int16s
6	PeripheralLightingValue	int16s
9	DistortionCorrectionValue	int16s
11	OriginalImageWidth	int16s
12	OriginalImageHeight	int16s

### Canon VignettingCorrUnknown Tags

Vignetting correction from PowerShot models.

Index2	Tag Name	Writable
0	VignettingCorrVersion	no

### Canon VignettingCorr2 Tags

Index4	Tag Name	Writable
5	PeripheralLightingSetting	int32s
6	ChromaticAberrationSetting	int32s
7	DistortionCorrectionSetting	int32s
9	DigitalLensOptimizerSetting	int32s

### Canon LightingOpt Tags

This information is new in images from the EOS 7D.

Index4	Tag Name	Writable
1	PeripheralIlluminationCorr	int32s
2	AutoLightingOptimizer	int32s
3	HighlightTonePriority	int32s
4	LongExposureNoiseReduction	int32s
5	HighISONoiseReduction	int32s
10	DigitalLensOptimizer	int32s
11	DualPixelRaw	int32s

# <u>Canon LensInfo Tags</u>

Index1	Tag Name	Writable
0	LensSerialNumber	undef[5]

# <u>Canon Ambience Tags</u>

Index4	Tag Name	Writable
1	AmbienceSelection	int32s

# Canon MultiExp Tags

Index4	Tag Name	Writable
1	MultiExposure	int32s
2	MultiExposureControl	int32s
3	MultiExposureShots	int32s

# Canon FilterInfo Tags

Information about creative filter settings.

Tag ID Tag Name

Writable

0x0101	GrainyBWFilter	no
0x0201	SoftFocusFilter	no
0x0301	ToyCameraFilter	no
$0 \times 0401$	MiniatureFilter	no
$0 \times 0402$	MiniatureFilterOrientation	no
$0 \times 0403$	MiniatureFilterPosition	no
$0 \times 0404$	MiniatureFilterParameter	no
$0 \times 0501$	FisheyeFilter	no
$0 \times 0601$	PaintingFilter	no
$0 \times 0701$	WatercolorFilter	no

# Canon HDRInfo Tags

Index4	Tag Name	Writable
1	HDR	int32s
2	HDREffect	int32s

# Canon LogInfo Tags

Index4	Tag Name	Writable
4	CompressionFormat	int32s
6	Sharpness	int32s
7	Saturation	int32s
8	ColorTone	int32s
9	ColorSpace2	int32s
10	ColorMatrix	int32s
11	CanonLogVersion	int32s

# Canon AFConfig Tags

Index4	Tag Name	Writable
1	7.ECon 5 : cEo 2	int32s
2	AFConfigTool	
	AFTrackingSensitivity	int32s
3	AFAccelDecelTracking	int32s
4	AFPointSwitching	int32s
5	AIServoFirstImage	int32s
6	AIServoSecondImage	int32s
7	USMLensElectronicMF	int32s
8	AFAssistBeam	int32s
9	OneShotAFRelease	int32s
10	AutoAFPointSelEOSiTRAF	int32s
11	LensDriveWhenAFImpossible	int32s
12	SelectAFAreaSelectionMode	int32s
13	AFAreaSelectionMethod	int32s
14	OrientationLinkedAF	int32s
15	ManualAFPointSelPattern	int32s
16	AFPointDisplayDuringFocus	int32s
17	VFDisplayIllumination	int32s
18	AFStatusViewfinder	int32s
19	InitialAFPointInServo	int32s
20	SubjectToDetect	int32s
24	EyeDetection	int32s

# Canon RawBurstInfo Tags

Index4	Tag Name	Writable
1	RawBurstImageNum	int32u
2	RawBurstImageCount	int32u

# <u>Canon LevelInfo Tags</u>

Index4	Tag Name	Writable
4	RollAngle	int32s
5	PitchAngle	int32s

#### -- ExifTool 13.24 Tag Names --

7	FocalLength	int32s
8	MinFocalLength2	int32s
9	MaxFocalLength2	int32s

# Canon CTMD Tags

Canon Timed MetaData tags found in CR3 images. The ExtractEmbedded option is automatically applied when reading CR3 files to be able to extract this information.

Tag ID	Tag Name	Writable
$0 \times 0001$	TimeStamp	no
$0 \times 0 0 0 4$	FocalInfo	Canon FocalInfo
$0 \times 0005$	ExposureInfo	Canon ExposureInfo
$0 \times 0007$	ExifInfo7	Canon ExifInfo
0x0008	ExifInfo8	Canon ExifInfo
0x0009	ExifInfo9	Canon ExifInfo

#### Canon FocalInfo Tags

Index4	Tag Name	Writable
0	FocalLength	no

# Canon ExposureInfo Tags

Index4	Tag Name	Writable
0	FNumber	no
1	ExposureTime	no
2	ISO	no

### Canon ExifInfo Tags

Tag ID	Tag Name	Writable
0x8769	ExifIFD	EXIF
0x927c	MakerNoteCanon	Canon

# Canon CDI1 Tags

Tag ID	Tag Name	Writak	ole
'IAD1'	IAD1	Canon	IAD1

# Canon IAD1 Tags

Index2	Tag Name	Writable
[no tags	known]	

# Canon CMP1 Tags

Index2	Tag Name	Writable
8	ImageWidth	no
10	ImageHeight	no

### Canon CNOP Tags

Tag ID	Tag Name	Writable
[no tags	known]	

### Canon CNTH Tags

Canon-specific QuickTime tags found in the CNTH atom of  $\ensuremath{\mathsf{MOV/MP4}}$  videos from some cameras.

Tag ID	Tag Name	Writable
'CNDA'	ThumbnailImage	undef

# Canon uuid Tags

Tags extracted from the uuid atom of MP4 videos from cameras such as the SX280, and CR3 images from cameras such as the EOS M50.

	Tag ID	Tag Name	Writable
	'CCTP'	CanonCCTP	Canon CCTP
	'CMT1'	IFD0	EXIF
	'CMT2'	ExifIFD	EXIF
	'CMT3'	MakerNoteCanon	Canon
	'CMT4'	GPSInfo	GPS
	'CNCV'	CompressorVersion	no
	'CNOP'	CanonCNOP	Canon CNOP
	'CNTH'	CanonCNTH	Canon CNTH
	'THMB'	ThumbnailImage	no
7	anon CCTP	<u>Tags</u>	

### Ca

Tag ID	Tag Name	Writable
[no tags	known]	

# Canon Skip Tags

Information found in the "skip" atom of Canon MOV videos.

Tag ID	Tag Name	Writable
'CNDB'	Unknown_CNDB?	no

# Canon uuid2 Tags

Tag ID	Tag Name	Writable
'CNOP'	CanonVRD	CanonVRD

### CanonCustom Tags

# CanonCustom Functions1D Tags

These custom functions are used by all 1D models up to but not including the Mark III.

Tag ID	Tag Name	Writable
0	FocusingScreen	int8u
1	FinderDisplayDuringExposure	int8u
2	ShutterReleaseNoCFCard	int8u
3	ISOSpeedExpansion	int8u
4	ShutterAELButton	int8u
5	ManualTv	int8u
6	ExposureLevelIncrements	int8u
7	USMLensElectronicMF	int8u
8	LCDPanels	int8u
9	AEBSequenceAutoCancel	int8u
10	AFPointIllumination	int8u
11	AFPointSelection	int8u
12	MirrorLockup	int8u
13	AFPointSpotMetering	int8u
14	FillFlashAutoReduction	int8u
15	ShutterCurtainSync	int8u
16	SafetyShiftInAvOrTv	int8u
17	AFPointActivationArea	int8u
18	SwitchToRegisteredAFPoint	int8u
19	LensAFStopButton	int8u
20	${\tt AIServoTrackingSensitivity}$	int8u

# 21 AIServoContinuousShooting int8u

# <u>CanonCustom</u> <u>Functions5D</u> <u>Tags</u>

Tag ID	Tag Name	Writable
0	FocusingScreen	int8u
1	${ t SetFunctionWhenShooting}$	int8u
2	LongExposureNoiseReduction	int8u
3	FlashSyncSpeedAv	int8u
4	Shutter-AELock	int8u
5	AFAssistBeam	int8u
6	ExposureLevelIncrements	int8u
7	FlashFiring	int8u
8	ISOExpansion	int8u
9	AEBSequenceAutoCancel	int8u
10	SuperimposedDisplay	int8u
11	MenuButtonDisplayPosition	int8u
12	MirrorLockup	int8u
13	AFPointSelectionMethod	int8u
14	ETTLII	int8u
15	ShutterCurtainSync	int8u
16	SafetyShiftInAvOrTv	int8u
17	AFPointActivationArea	int8u
18	LCDDisplayReturnToShoot	int8u
19	LensAFStopButton	int8u
20	AddOriginalDecisionData	int8u

# <u>CanonCustom</u> <u>Functions10D</u> <u>Tags</u>

Tag ID	Tag Name	Writable
1	SetButtonWhenShooting	int8u
2	ShutterReleaseNoCFCard	int8u
3	FlashSyncSpeedAv	int8u
4	Shutter-AELock	int8u
5	AFAssist	int8u
6	ExposureLevelIncrements	int8u
7	AFPointRegistration	int8u
8	RawAndJpgRecording	int8u
9	AEBSequenceAutoCancel	int8u
10	SuperimposedDisplay	int8u
11	MenuButtonDisplayPosition	int8u
12	MirrorLockup	int8u
13	AssistButtonFunction	int8u
14	FillFlashAutoReduction	int8u
15	ShutterCurtainSync	int8u
16	SafetyShiftInAvOrTv	int8u
17	LensAFStopButton	int8u

# CanonCustom Functions20D Tags

Tag ID	Tag Name	Writable
0	SetFunctionWhenShooting	int8u
1	LongExposureNoiseReduction	int8u
2	FlashSyncSpeedAv	int8u
3	Shutter-AELock	int8u
4	AFAssistBeam	int8u
5	ExposureLevelIncrements	int8u
6	FlashFiring	int8u
7	ISOExpansion	int8u
8	AEBSequenceAutoCancel	int8u
9	SuperimposedDisplay	int8u
10	MenuButtonDisplayPosition	int8u
11	MirrorLockup	int8u
12	AFPointSelectionMethod	int8u
13	ETTLII	int8u
14	ShutterCurtainSync	int8u
15	SafetyShiftInAvOrTv	int8u

16	LensAFStopButton	int8u
17	AddOriginalDecisionData	int8u

# <u>CanonCustom</u> <u>Functions30D</u> <u>Tags</u>

Tag Name	Writable
SetFunctionWhenShooting	int8u
LongExposureNoiseReduction	int8u
FlashSyncSpeedAv	int8u
Shutter-AELock	int8u
AFAssistBeam	int8u
ExposureLevelIncrements	int8u
FlashFiring	int8u
ISOExpansion	int8u
AEBSequenceAutoCancel	int8u
SuperimposedDisplay	int8u
MenuButtonDisplayPosition	int8u
MirrorLockup	int8u
${\tt AFPointSelectionMethod}$	int8u
ETTLII	int8u
ShutterCurtainSync	int8u
2	int8u
_	int8u
LensAFStopButton	int8u
AddOriginalDecisionData	int8u
	SetFunctionWhenShooting LongExposureNoiseReduction FlashSyncSpeedAv Shutter-AELock AFAssistBeam ExposureLevelIncrements FlashFiring ISOExpansion AEBSequenceAutoCancel SuperimposedDisplay MenuButtonDisplayPosition MirrorLockup AFPointSelectionMethod ETTLII ShutterCurtainSync SafetyShiftInAvOrTv MagnifiedView LensAFStopButton

# <u>CanonCustom</u> <u>Functions350D</u> <u>Tags</u>

Tag ID	Tag Name	Writable
0	SetButtonCrossKeysFunc	int8u
1	LongExposureNoiseReduction	int8u
2	FlashSyncSpeedAv	int8u
3	Shutter-AELock	int8u
4	AFAssistBeam	int8u
5	ExposureLevelIncrements	int8u
6	MirrorLockup	int8u
7	ETTLII	int8u
8	ShutterCurtainSvnc	int8u

# CanonCustom Functions400D Tags

Tag ID	Tag Name	Writable
0	SetButtonCrossKeysFunc	int8u
1	LongExposureNoiseReduction	int8u
2	FlashSyncSpeedAv	int8u
3	Shutter-AELock	int8u
4	AFAssistBeam	int8u
5	ExposureLevelIncrements	int8u
6	MirrorLockup	int8u
7	ETTLII	int8u
8	ShutterCurtainSync	int8u
9	MagnifiedView	int8u
10	LCDDisplayAtPowerOn	int8u

# CanonCustom FunctionsD30 Tags

Custom functions for the EOS D30 and D60.

Tag ID	Tag Name	Writable
1	LongExposureNoiseReduction	int8u
2	Shutter-AELock	int8u
3	MirrorLockup	int8u
4	ExposureLevelIncrements	int8u
5	AFAssist	int8u
6	FlashSyncSpeedAv	int8u
7	AEBSequenceAutoCancel	int8u

8	ShutterCurtainSync	int8u
9	LensAFStopButton	int8u
10	FillFlashAutoReduction	int8u
11	MenuButtonReturn	int8u
12	SetButtonWhenShooting	int8u
13	SensorCleaning	int8u
14	SuperimposedDisplay	int8u
15	ShutterReleaseNoCFCard	int8u

### <u>CanonCustom</u> <u>FuncsUnknown</u> <u>Tags</u>

Tag ID	Tag Name	Writable
[no tags	known]	

# <u>CanonCustom PersonalFuncs Tags</u>

Personal function settings for the EOS-1D.

Index2	Tag Name	Writable
1	PF0CustomFuncRegistration	int16u
2	PF1DisableShootingModes	int16u
3	PF2DisableMeteringModes	int16u
4	PF3ManualExposureMetering	int16u
5	PF4ExposureTimeLimits	int16u
6	PF5ApertureLimits	int16u
7	PF6PresetShootingModes	int16u
8	PF7BracketContinuousShoot	int16u
9	PF8SetBracketShots	int16u
10	PF9ChangeBracketSequence	int16u
11	PF10RetainProgramShift	int16u
14	PF13DrivePriority	int16u
15	PF14DisableFocusSearch	int16u
16	PF15DisableAFAssistBeam	int16u
17	PF16AutoFocusPointShoot	int16u
18	PF17DisableAFPointSel	int16u
19	PF18EnableAutoAFPointSel	int16u
20	PF19ContinuousShootSpeed	int16u
21	PF20LimitContinousShots	int16u
22	PF21EnableQuietOperation	int16u
24	PF23SetTimerLengths	int16u
25	PF24LightLCDDuringBulb	int16u
26	PF25DefaultClearSettings	int16u
27	PF26ShortenReleaseLag	int16u
28	PF27ReverseDialRotation	int16u
29	PF28NoQuickDialExpComp	int16u
30	PF29QuickDialSwitchOff	int16u
31	PF30EnlargementMode	int16u
32	PF310riginalDecisionData	int16u

# <u>CanonCustom</u> <u>PersonalFuncValues</u> <u>Tags</u>

Tag Name	Writable
PF1Value	int16u
PF2Value	int16u
PF3Value	int16u
PF4ExposureTimeMin	int16u
PF4ExposureTimeMax	int16u
PF5ApertureMin	int16u
PF5ApertureMax	int16u
PF8BracketShots	int16u
PF19ShootingSpeedLow	int16u
PF19ShootingSpeedHigh	int16u
PF20MaxContinousShots	int16u
PF23ShutterButtonTime	int16u
PF23FELockTime	int16u
PF23PostReleaseTime	int16u
PF25AEMode	int16u
	PF1Value PF2Value PF3Value PF4ExposureTimeMin PF4ExposureTimeMax PF5ApertureMin PF5ApertureMax PF8BracketShots PF19ShootingSpeedLow PF19ShootingSpeedHigh PF20MaxContinousShots PF23ShutterButtonTime PF23FELockTime PF23PostReleaseTime

16	PF25MeteringMode	int16u
17	PF25DriveMode	int16u
18	PF25AFMode	int16u
19	PF25AFPointSel	int16u
20	PF25ImageSize	int16u
21	PF25WBMode	int16u
22	PF25Parameters	int16u
23	PF25ColorMatrix	int16u
24	PF27Value	int16u

#### <u>CanonCustom Functions2 Tags</u>

Beginning with the EOS 1D Mark III, Canon finally created a set of custom function tags which are (reasonably) consistent across models. The EOS 1D Mark III has 57 custom function tags divided into four main groups: 1. Exposure (0x0101-0x010f), 2. Image (0x0201-0x0203), Flash Exposure (0x0304-0x0306) and Display (0x0407-0x0409), 3. Auto Focus (0x0501-0x050e) and Drive (0x060f-0x0611), and 4. Operation (0x0701-0x070a) and Others (0x080b-0x0810). The table below lists tags used by the EOS 1D Mark III, as well as newer tags and values added by later models.

Tag ID	Tag Name	Writable
0x0101	ExposureLevelIncrements	int32s
0x0102	ISOSpeedIncrements	int32s
0x0103	ISOSpeedRange	int32s[3]
	ISOExpansion	int32s
$0 \times 0104$	AEBAutoCancel	int32s
$0 \times 0105$	AEBSequence	int32s
0x0106	AEBShotCount	int32s
	AEBShotCount	int32s[2]
0x0107	SpotMeterLinkToAFPoint	int32s
0x0108	SafetyShift	int32s
$0 \times 0109$	UsableShootingModes	int32s
	UsableShootingModes	int32s[2]
0x010a	UsableMeteringModes	int32s
	UsableMeteringModes	int32s[2]
0x010b	ExposureModeInManual	int32s
0x010c	ShutterSpeedRange	int32s[3]
	ShutterSpeedRange	int32s[4]
0x010d	ApertureRange	int32s[3]
	ApertureRange	int32s[4]
0x010e	ApplyShootingMeteringMode	int32s[8]
0x010f	FlashSyncSpeedAv	int32s
0x0110	AEMicroadjustment	int32s[3]
0x0111	FEMicroadjustment	int32s[3]
0x0112	SameExposureForNewAperture	int32s
$0 \times 0113$	ExposureCompAutoCancel	int32s
$0 \times 0114$	AELockMeterModeAfterFocus	int32s
$0 \times 0201$	LongExposureNoiseReduction	int32s
$0 \times 0202$ $0 \times 0203$	HighISONoiseReduction	int32s int32s
0x0203 0x0204	HighlightTonePriority	int32s
0x0204 $0x0304$	AutoLightingOptimizer ETTLII	int32s
0x0304 $0x0305$	ShutterCurtainSync	int32s
0x0305	FlashFiring	int32s
0x0300	ViewInfoDuringExposure	int32s
0x0407 0x0408	LCDIlluminationDuringBulb	int32s
0x0400	InfoButtonWhenShooting	int32s
0x040a	ViewfinderWarnings	int32s
$0 \times 040 \text{b}$	LVShootingAreaDisplay	int32s
0x040c	LVShootingAreaDisplay	int32s
0x0501	USMLensElectronicMF	int32s
0x0501	AIServoTrackingSensitivity	int32s
0x0502	AIServoImagePriority	int32s
0x0504	AIServoTrackingMethod	int32s
$0 \times 0505$	LensDriveNoAF	int32s
0x0506	LensAFStopButton	int32s
$0 \times 0507$	AFMicroadjustment	int32s[5]
	-	

0x0508	AFPointAreaExpansion	int32s
0x0509	SelectableAFPoint	int32s
0x050a	SwitchToRegisteredAFPoint	int32s
0x050b	AFPointAutoSelection	int32s
0x050c	AFPointDisplayDuringFocus	int32s
0x050d	AFPointBrightness	int32s
0x050e	AFAssistBeam	int32s
0x050f	AFPointSelectionMethod	int32s
$0 \times 0510$	VFDisplayIllumination	int32s
	SuperimposedDisplay	int32s
0x0511	AFDuringLiveView	int32s
$0 \times 0512$	SelectAFAreaSelectMode	int32s
0x0513	ManualAFPointSelectPattern	int32s
$0 \times 0514$	DisplayAllAFPoints	int32s
0x0515	FocusDisplayAIServoAndMF	int32s
0x0516	OrientationLinkedAFPoint	int32s
$0 \times 0517$	MultiControllerWhileMetering	int32s
$0 \times 0518$	AccelerationTracking	int32s
$0 \times 0519$	AIServoFirstImagePriority	int32s
0x051a	AIServoSecondImagePriority	int32s
$0 \times 051b$	AFAreaSelectMethod	int32s
0x051c	AutoAFPointColorTracking	int32s
0x051d 0x051e	VFDisplayIllumination	int32s
	InitialAFPointAIServoAF	int32s
0x060f 0x0610	MirrorLockup	int32s
0X0010	ContinuousShootingSpeed	int32s[6]
	ContinuousShootingSpeed	int32s[5] int32s[3]
0x0611	ContinuousShootingSpeed ContinuousShotLimit	int32s[3]
0x0611	RestrictDriveModes	int32s[2]
0X0012	RestrictDriveModes	int32s[2]
0x0701	Shutter-AELock	int32s[2]
020701	AFAndMeteringButtons	int32s
	ShutterButtonAFOnButton	int32s
0x0702	AFOnAELockButtonSwitch	int32s
0x0702	QuickControlDialInMeter	int32s
0x0703	SetButtonWhenShooting	int32s
0x0705	ManualTv	int32s
0x0706	DialDirectionTvAv	int32s
0x0707	AvSettingWithoutLens	int32s
$0 \times 0708$	WBMediaImageSizeSetting	int32s
$0 \times 0709$	LockMicrophoneButton	int32s
0x070a	ButtonFunctionControlOff	int32s
$0 \times 070 b$	AssignFuncButton	int32s
0x070c	CustomControls	int32s
0x070d	StartMovieShooting	int32s
0x070e	FlashButtonFunction	int32s
0x070f	MultiFunctionLock	int32s
$0 \times 0710$	TrashButtonFunction	int32s
$0 \times 0711$	ShutterReleaseWithoutLens	int32s
$0 \times 0712$	ControlRingRotation	int32s
$0 \times 0713$	FocusRingRotation	int32s
$0 \times 0714$	RFLensMFFocusRingSensitivity	int32s
$0 \times 0715$	CustomizeDials	int32s
0x080b	FocusingScreen	int32s
0x080c	TimerLength	int32s[3]
	TimerLength	int32s[4]
0x080d	ShortReleaseTimeLag	int32s
0x080e	AddAspectRatioInfo	int32s
0x080f	AddOriginalDecisionData	int32s
0x0810	LiveViewExposureSimulation	int32s
0x0811	LCDDisplayAtPowerOn	int32s
$0 \times 0812$	MemoAudioQuality	int32s
$0 \times 0.813$	DefaultEraseOption	int32s
$0 \times 0814$	RetractLensOnPowerOff	int32s
0x0815	AddIPTCInformation	int32s
$0 \times 0816$	AudioCompression	int32s

CanonVRD Tags
Canon Digital Photo Professional writes VRD (Recipe Data) information

as a trailer record to JPEG, TIFF, CRW and CR2 images, or as standalone VRD or DR4 files. The tags listed below represent information found in these records. The complete VRD/DR4 data record may be accessed as a block using the Extra 'CanonVRD' or 'CanonDR4' tag, but this tag is not extracted or copied unless specified explicitly.

Tag ID	Tag Name	Writable
0xffff00f4	EditData	CanonVRD Edit
0xffff00f5	IHLData	CanonVRD IHL
0xffff00f6	XMP	XMP
0xffff00f7	Edit4Data	CanonVRD Edit4

# <u>CanonVRD</u> <u>Edit</u> <u>Tags</u>

Canon VRD edit information.

Index	Tag Name	Writable	
0	VRD1	CanonVRD	Ver1
1	VRDStampTool	CanonVRD	StampTool
2	VRD2	CanonVRD	Ver2

### CanonVRD Ver1 Tags

allollykb	verr rags	
Index1	Tag Name	Writable
2	VRDVersion	no
6	WBAdjRGGBLevels	int16u[4]
24	WhiteBalanceAdj	int16u
26	WBAdjColorTemp	int16u
36	WBFineTuneActive	int16u
40	WBFineTuneSaturation	int16u
44	WBFineTuneTone	int16u
46	RawColorAdj	int16u
48	RawCustomSaturation	int32s
52	RawCustomTone	int32s
56	RawBrightnessAdj	int32s
60	ToneCurveProperty	int16u
122	DynamicRangeMin	int16u
124	DynamicRangeMax	int16u
272	ToneCurveActive	int16u
275	ToneCurveMode	int8u
276	BrightnessAdj	int8s
277	ContrastAdj	int8s
278	SaturationAdj	int16s
286	ColorToneAdj	int32s
294	LuminanceCurvePoints	int16u[21]
336	LuminanceCurveLimits	int16u[4]
345	ToneCurveInterpolation	int8u
352	RedCurvePoints	int16u[21]
394	RedCurveLimits	int16u[4]
410	GreenCurvePoints	int16u[21]
452	GreenCurveLimits	int16u[4]
468	BlueCurvePoints	int16u[21]
510	BlueCurveLimits	int16u[4]
526	RGBCurvePoints	int16u[21]
568	RGBCurveLimits	int16u[4]
580	CropActive	int16u
582	CropLeft	int16u
584	CropTop	int16u
586	CropWidth	int16u
588	CropHeight	int16u
602	SharpnessAdj	int16u
608	CropAspectRatio	int16u
610	ConstrainedCropWidth	float
614	ConstrainedCropHeight	float
618	CheckMark	int16u
622	Rotation	int16u
624	WorkColorSpace	int16u

# CanonVRD StampTool Tags

Index1	Tag Name	Writable
0	StampToolCount	no

# <u>CanonVRD Ver2 Tags</u>

Tags added in DPP version 2.0 and later.

agb addea	III DII VCIDIOII 2.0 ana lacci.	
Index2	Tag Name	Writable
2	PictureStyle	int16s
3	IsCustomPictureStyle	int16s
13	StandardRawColorTone	int16s
14	StandardRawSaturation	int16s
15	StandardRawContrast	int16s
16	StandardRawLinear	int16s
17	StandardRawSharpness	int16s
18	StandardRawHighlightPoint	int16s
19	StandardRawShadowPoint	int16s
20	StandardOutputHighlightPoint	int16s
21	StandardOutputShadowPoint	int16s
22	PortraitRawColorTone	int16s
23	PortraitRawSaturation	int16s
24	PortraitRawContrast	int16s
25	PortraitRawLinear	int16s
26	PortraitRawSharpness	int16s
27	PortraitRawHighlightPoint	int16s
28	PortraitRawShadowPoint	int16s
29	PortraitOutputHighlightPoint	int16s
30	PortraitOutputShadowPoint	int16s
31	LandscapeRawColorTone	int16s
32	LandscapeRawSaturation	int16s
33	LandscapeRawContrast	int16s
34	LandscapeRawLinear	int16s
35	LandscapeRawSharpness	int16s
36	LandscapeRawHighlightPoint	int16s
37	LandscapeRawShadowPoint	int16s
38	LandscapeOutputHighlightPoint	int16s
39	LandscapeOutputShadowPoint	int16s
40	NeutralRawColorTone	int16s
41	NeutralRawSaturation	int16s
42	NeutralRawContrast	int16s
43	NeutralRawLinear	int16s
44	NeutralRawSharpness	int16s
45	NeutralRawHighlightPoint	int16s
46	NeutralRawShadowPoint	int16s
47	NeutralOutputHighlightPoint	int16s
48	NeutralOutputShadowPoint	int16s
49	FaithfulRawColorTone	int16s
50	FaithfulRawSaturation	int16s
51	FaithfulRawContrast	int16s
52	FaithfulRawLinear	int16s
53	FaithfulRawSharpness	int16s
54	FaithfulRawHighlightPoint	int16s
55	FaithfulRawShadowPoint	int16s
56	FaithfulOutputHighlightPoint	int16s
57	FaithfulOutputShadowPoint	int16s
58	MonochromeFilterEffect	int16s
59	MonochromeToningEffect	int16s
60	MonochromeContrast	int16s
61	MonochromeLinear	int16s
62	MonochromeSharpness	int16s
63	MonochromeRawHighlightPoint	int16s
64	MonochromeRawShadowPoint	int16s
65	MonochromeOutputHighlightPoint	int16s
66	MonochromeOutputShadowPoint	int16s
69	UnknownContrast?	int16s
<b>J</b> J		

	ExifTool 13.24 Tag Names -	-
70	UnknownLinear?	int16s
71	UnknownSharpness?	int16s
72	UnknownRawHighlightPoint?	int16s
73	UnknownRawShadowPoint?	int16s
74	UnknownOutputHighlightPoint?	int16s
75	UnknownOutputShadowPoint?	int16s
76 77	CustomColorTone	int16s
7 <i>7</i> 78	CustomSaturation CustomContrast	int16s int16s
79	CustomLinear	int16s
80	CustomSharpness	int16s
81	CustomRawHighlightPoint	int16s
82	CustomRawShadowPoint	int16s
83	CustomOutputHighlightPoint	int16s
84	CustomOutputShadowPoint	int16s
88	CustomPictureStyleData	no
94	ChrominanceNoiseReduction	int16s
95	LuminanceNoiseReduction	int16s
96 98	ChrominanceNR_TIFF_JPEG ChromaticAberrationOn	int16s int16s
99	DistortionCorrectionOn	int16s
100	PeripheralIlluminationOn	int16s
101	ColorBlur	int16s
102	ChromaticAberration	int16s
103	DistortionCorrection	int16s
104	PeripheralIllumination	int16s
105	AberrationCorrectionDistance	int16s
106	ChromaticAberrationRed	int16s
107	ChromaticAberrationBlue	int16s
109	LuminanceNR_TIFF_JPEG	int16s
110 111	AutoLightingOptimizerOn	int16s int16s
117	AutoLightingOptimizer StandardRawHighlight	int16s
118	PortraitRawHighlight	int16s
119	LandscapeRawHighlight	int16s
120	NeutralRawHighlight	int16s
121	FaithfulRawHighlight	int16s
122	MonochromeRawHighlight	int16s
123	UnknownRawHighlight?	int16s
124	CustomRawHighlight	int16s
126	StandardRawShadow PortraitRawShadow	int16s
127 128	LandscapeRawShadow	int16s int16s
129	NeutralRawShadow	int16s
130	FaithfulRawShadow	int16s
131	MonochromeRawShadow	int16s
132	UnknownRawShadow?	int16s
133	CustomRawShadow	int16s
139	AngleAdj	int32s
142	CheckMark2	int16u
144	UnsharpMask	int16s
146	StandardUnsharpMaskStrength	int16s
148 150	StandardUnsharpMaskFineness StandardUnsharpMaskThreshold	int16s int16s
152	PortraitUnsharpMaskStrength	int16s
154	PortraitUnsharpMaskFineness	int16s
156	PortraitUnsharpMaskThreshold	int16s
158	LandscapeUnsharpMaskStrength	int16s
160	LandscapeUnsharpMaskFineness	int16s
162	LandscapeUnsharpMaskThreshold	int16s
164	NeutraUnsharpMaskStrength	int16s
166	NeutralUnsharpMaskFineness	int16s
168	NeutralUnsharpMaskThreshold	int16s
170 172	FaithfulUnsharpMaskStrength FaithfulUnsharpMaskFineness	int16s int16s
174	FaithfulUnsharpMaskThreshold	int16s
176	MonochromeUnsharpMaskStrength	int16s
178	MonochromeUnsharpMaskFineness	int16s
180	MonochromeUnsharpMaskThreshold	int16s
182	CustomUnsharpMaskStrength	int16s

184	CustomUnsharpMaskFineness	int16s
186	CustomUnsharpMaskThreshold	int16s
188	CustomDefaultUnsharpStrength	int16s
190	CustomDefaultUnsharpFineness	int16s
192	CustomDefaultUnsharpThreshold	int16s
214	CropCircleActive	int16s
215	CropCircleX	int16s
216	CropCircleY	int16s
217	CropCircleRadius	int16s
220	DLOOn	int16s
221	DLOSetting	int16s
222	DLOShootingDistance	int16s
223	DLODataLength	no
224	DLOInfo	CanonVRD DLOInfo
225	CameraRawColorTone	int16s
226	CameraRawSaturation	int16s
227	CameraRawContrast	int16s
228	CameraRawLinear	int16s
229	CameraRawSharpness	int16s
230	CameraRawHighlightPoint	int16s
231	CameraRawShadowPoint	int16s
232	CameraRawOutputHighlightPoint	int16s
233	CameraRawOutputShadowPoint	int16s

### CanonVRD DLOInfo Tags

Tags added when DLO (Digital Lens Optimizer) is on.

Index2	Tag Name	Writable
4	DLOSettingApplied	int16s
5	DLOVersion	string[10]
10	DLOData	no

### CanonVRD IHL Tags

Tag ID	Tag Name	Writable
0x0001	IHL_EXIF	EXIF
	IHL_EXIF?	no
0x0003	ThumbnailImage	no
$0 \times 0 0 0 4$	PreviewImage	no
0x0005	RawCodecVersion	no
0x0006	CRCDevelParams?	no

### CanonVRD Edit4 Tags

Canon DPP version 4 edit information.

Index	Tag Name	Writable	
0	DR4	CanonVRD	DR4

# CanonVRD DR4 Tags

Tags written by Canon DPP version 4 in CanonVRD trailers and DR4 files. Each tag has three associated flag words which are stored with the directory entry, some of which are extracted as a separate tag, indicated in the table below by a decimal appended to the tag ID (.0, .1 or .2).

Tag ID	Tag Name	Writable
'header'	DR4Header	CanonVRD DR4Header
0x10002	Rotation	yes
0x10003	AngleAdj	yes
0x10021	CustomPictureStyle	yes
0x10100	Rating	yes
$0 \times 10101$	CheckMark	yes
$0 \times 10200$	WorkColorSpace	yes

0x20001	PawPrightnoggAdi	7700
0x20001 0x20101	RawBrightnessAdj WhiteBalanceAdj	yes
0x20101 $0x20102$	WBAdjColorTemp	yes yes
0x20102 0x20105	WBAdjMagentaGreen	yes
0x20105	WBAdjBlueAmber	yes
0x20125	WBAdjRGGBLevels	yes
0x20200	GammaLinear	yes
0x20301	PictureStyle	yes
0x20303	ContrastAdj	yes
0x20304	ColorToneAdj	yes
0x20305	ColorSaturationAdj	yes
0x20306	MonochromeToningEffect	yes
0x20307	MonochromeFilterEffect	yes
0x20308	UnsharpMaskStrength	yes
0x20309	UnsharpMaskFineness	yes
0x2030a	UnsharpMaskThreshold	yes
0x2030b	ShadowAdj	yes
0x2030c	HighlightAdj	yes
0x20310	SharpnessAdj	yes
0x20310.0	SharpnessAdjOn	yes
0x20311	SharpnessStrength	yes
0x20400	ToneCurve	CanonVRD ToneCurve
0x20400.1	ToneCurveOriginal	yes
0x20410	ToneCurveBrightness	yes
0x20411	ToneCurveContrast	yes
0x20500	AutoLightingOptimizer	yes
0x20500.0	AutoLightingOptimizerOn	yes
0x20600	LuminanceNoiseReduction	yes
0x20601	ChrominanceNoiseReduction	yes
0x20670	ColorMoireReduction	yes
0x20670.0	ColorMoireReductionOn	yes
0x20701	ShootingDistance	yes
0x20702 0x20702.0	PeripheralIllumination	yes
0x20702.0 $0x20703$	PeripheralIlluminationOn ChromaticAberration	yes
0x20703 $0x20703.0$	ChromaticAberrationOn	yes
$0 \times 20703.0$ $0 \times 20704$	ColorBlurOn	yes yes
0x20704 $0x20705$	DistortionCorrection	yes
0x20705.0	DistortionCorrectionOn	yes
0x20705.0	DLOSetting	yes
0x20706.0	DLOOn	yes
0x20707	ChromaticAberrationRed	yes
0x20708	ChromaticAberrationBlue	yes
0x20709	DistortionEffect	yes
0x2070b	DiffractionCorrectionOn	yes
0x20900	ColorHue	yes
0x20901	SaturationAdj	yes
0x20910	RedHSL	yes
0x20911	OrangeHSL	yes
0x20912	YellowHSL	yes
0x20913	GreenHSL	yes
0x20914	AquaHSL	yes
0x20915	BlueHSL	yes
0x20916	PurpleHSL	yes
0x20917	MagentaHSL	yes
0x20a00	GammaInfo	CanonVRD GammaInfo
0x20b10	DPRAWMicroadjustBackFront	yes
0x20b12	DPRAWMicroadjustStrength	yes
0x20b20	DPRAWBokehShift	yes
0x20b21	DPRAWBokehShiftArea	yes
0x20b30	DPRAWGhostingReductionArea	yes
0x30101	CropAspectRatio	yes
0x30102 0xf0100	CropAspectRatioCustom	yes
OXTOTOO	CronInfo	CanonIIDD CronInfo
$0 \times f \cap F \cap O$	CropInfo	CanonVRD CropInfo
0xf0500	CustomPictureStyleData	yes
0xf0510	CustomPictureStyleData StampInfo	yes CanonVRD StampInfo
	CustomPictureStyleData	yes

Index4	Tag Name	Writable
3		int32u
<u>CanonVRD</u>	ToneCurve Tags	
Index4	3	Writable
0	ToneCurveColorSpace	int32u
1	ToneCurveShape	int32u
3	ToneCurveInputRange	int32u[2]
5	ToneCurveOutputRange	int32u[2]
7	RGBCurvePoints	int32u[21]
10	ToneCurveX	int32u
11	ToneCurveY	int32u
45	RedCurvePoints	int32u[21]
83	GreenCurvePoints	int32u[21]
121	BlueCurvePoints	int32u[21]
<u>CanonVRD</u>	<u>GammaInfo</u> <u>Tags</u>	
Index8	2	Writable
2	GammaContrast	double
3	GammaColorTone	double
4 5	GammaSaturation GammaUnsharpMaskStrength	double double
6	GammaUnsharpMaskFineness	double
7	GammaUnsharpMaskThreshold	double
8	GammaSharpnessStrength	double
9	GammaShadow	double
10	GammaHighlight	double
12	GammaBlackPoint	double
13	GammaWhitePoint	double
14	GammaMidPoint	double
15	GammaCurveOutputRange	double[2]
<u>CanonVRD</u>	CropInfo Tags	
Index4	Tag Name	Writable
0	CropActive	int32s
1	CropRotatedOriginalWidth	int32s
2	CropRotatedOriginalHeight	int32s
3	CropX	int32s
4	CropY	int32s
5	CropWidth	int32s
6	CropHeight	int32s
7	CropRotation	int32s double
8 10	CropAngle CropOriginalWidth	int32s
11	CropOriginalHeight	int32s
CanonVRD	StampInfo Tags	
Index4	Tag Name	Writable
2		no
	-	
<u>CanonVRD</u>	<u>DustInfo</u> <u>Tags</u>	
Index4	3	Writable
2	DustDeleteApplied	no
Casio Tags	Tag Name	Writable
1ag 1D		WIICADIE
0x0001	RecordingMode	int16u
	-	

$0 \times 0002$	Quality	int16u
0x0003	FocusMode	int16u
$0 \times 0004$	FlashMode	int16u
0x0005	FlashIntensity	int16u
0x0006	ObjectDistance	int32u
$0 \times 0007$	WhiteBalance	int16u
0x000a	DigitalZoom	int32u
0x000b	Sharpness	int16u
0x000c	Contrast	int16u
0x000d	Saturation	int16u
$0 \times 0014$	ISO	int16u
$0 \times 0015$	FirmwareDate	string[18]
$0 \times 0016$	Enhancement	int16u
$0 \times 0017$	ColorFilter	int16u
0x0018	AFPoint	int16u
$0 \times 0019$	FlashIntensity	int16u
0x0e00	PrintIM	PrintIM

# Casio Type2 Tags

Tag ID	Tag Name	Writable
0x0002	PreviewImageSize	int16u[2]
0x0003	PreviewImageLength	int32u*
$0 \times 0004$	PreviewImageStart	int32u*
0x0008	QualityMode	int16u
0x0009	CasioImageSize	int16u
0x000d	FocusMode	int16u
$0 \times 0014$	ISO	int16u
0x0019	WhiteBalance	int16u
0x001d	FocalLength	rational64u
0x001f	Saturation	int16u
0x0020	Contrast	int16u
$0 \times 0021$	Sharpness	int16u
0x0e00	PrintIM	PrintIM
0x2000	PreviewImage	undef
0x2001	FirmwareDate	string[18]
0x2011	WhiteBalanceBias	int16u[2]
0x2012	WhiteBalance	int16u
0x2021	AFPointPosition	int16u[4]~
0x2022	ObjectDistance	int32u
0x2034	FlashDistance	int16u
0x2076	${f SpecialEffect Mode}$	int8u[3]
0x2089	FaceInfo1	Casio FaceInfol
	FaceInfo2	Casio FaceInfo2
	FaceInfoUnknown?	yes
0x211c	FacesDetected	int8u
0x3000	RecordMode	int16u
0x3001	ReleaseMode	int16u
0x3002	Quality	int16u
0x3003	FocusMode	int16u
0x3006	HometownCity	string
0x3007	BestShotMode	int16u
0x3008	AutoISO	int16u
0x3009	AFMode	int16u
0x3011	Sharpness	undef[2]
0x3012	Contrast	undef[2]
0x3013	Saturation	undef[2]
0x3014	ISO	int16u int16u
0x3015	ColorMode Enhancement	int16u
0x3016 0x3017	ColorFilter	int16u
0x3017 0x301b	ArtMode	int16u
0x301b	SequenceNumber	int16u
0x301d	BracketSequence	int16u[2]
0x301d	ImageStabilization	int16u
0x3020 0x302a	LightingMode	int16u
0x302a 0x302b	PortraitRefiner	int16u
0x302D	SpecialEffectLevel	int16u
0x3030	SpecialEffectSetting	int16u
0223031	Programment	111C1 O G

0x3103	DriveMode	int16u
0x310b	ArtModeParameters	int8u[3]
$0 \times 4001$	CaptureFrameRate	int16u[n]
0x4003	VideoQuality	int16u

### Casio FaceInfol Tags

Face-detect tags extracted from models such as the EX-H5.

Index1	Tag Name	Writable
0	FacesDetected	int8u
1	FaceDetectFrameSize	int16u[2]
13	FacelPosition	int16u[4]
124	Face2Position	int16u[4]
235	Face3Position	int16u[4]
346	Face4Position	int16u[4]
457	Face5Position	int16u[4]
568	Face6Position	int16u[4]
679	Face7Position	int16u[4]
790	Face8Position	int16u[4]
901	Face9Position	int16u[4]
1012	Face10Position	int16u[4]

### <u>Casio FaceInfo2 Tags</u>

Face-detect tags extracted from models such as the EX-H20G and  $\ensuremath{\text{EX-ZR100}}\xspace$  .

Index1	Tag Name	Writable
2	FacesDetected	int8u
4	FaceDetectFrameSize	int16u[2]
8	FaceOrientation	int8u
24	Face1Position	int16u[4]
76	Face2Position	int16u[4]
128	Face3Position	int16u[4]
180	Face4Position	int16u[4]
232	Face5Position	int16u[4]
284	Face6Position	int16u[4]
336	Face7Position	int16u[4]
388	Face8Position	int16u[4]
440	Face9Position	int16u[4]
492	Face10Position	int16u[4]

# <u>Casio QVCI Tags</u>

This information is found in the APP1 QVCI segment of JPEG images from the Casio QV-7000SX.

Index1	Tag Name	Writable
44	CasioQuality	no
55	FocalRange?	no
77	DateTimeOriginal	no
98	ModelType	no
114	ManufactureIndex	no
124	ManufactureCode	no

### Casio AVI Tags

This information is found in Casio GV-10 AVI videos.

Index1	Tag Name	Writable
0	Software	no

### DJI Tags

This table lists tags found in the maker notes of images from some DJI Phantom drones.

Tag ID	Tag Name	Writable
$0 \times 0001$	Make	string
0x0003	SpeedX	float
$0 \times 0004$	SpeedY	float
$0 \times 0005$	SpeedZ	float
0x0006	Pitch	float
0x0007	Yaw	float
0x0008	Roll	float
0x0009	CameraPitch	float
0x000a	CameraYaw	float
0x000b	CameraRoll	float

# DJI XMP Tags

XMP tags used by DJI for images from drones.

These tags belong to the ExifTool XMP-drone-dji family 1 group.

Tag Name	Writable
AbsoluteAltitude	real
CalibratedFocalLength	real
CalibratedOpticalCenterX	real
CalibratedOpticalCenterY	real
CamReverse	string
DewarpData	string
DewarpFlag	string
FlightPitchDegree	real
FlightRollDegree	real
FlightXSpeed	real
FlightYSpeed	real
FlightYawDegree	real
FlightZSpeed	real
GPSLatitude	real/
GPSLongitude	real/
GPSLongtitude	real/
GimbalPitchDegree	real
GimbalReverse	string
GimbalRollDegree	real
GimbalYawDegree	real
Latitude	real
Longitude	real
RelativeAltitude	real
RtkFlag	string
RtkStdHgt	real
RtkStdLat	real
RtkStdLon	real
SelfData	string

# DJI Info Tags

Tags written by some DJI drones.

Tag ID	Tag Name	Writable
'FlightDegree(Y,P,R)	5 5	no
'FlightSpeed(X,Y,Z)'	FlightSpeed	no
'GimbalDegree(Y,P,R)	' GimbalDegree	no
'adj_dbg_info'	ADJDebugInfo	no
'ae_dbg_info'	AEDebugInfo	no
'ae_histogram_info'	AEHistogramInfo	no
'ae_liveview_histogr	am_info'	
	AELiveViewHistogramInfo	no
'ae_liveview_local_h	istogram'	
	AELiveViewLocalHistogram	no
'ae_local_histogram'	AELocalHistogram	no
'af_dbg_info'	AFDebugInfo	no
'awb_dbg_info'	AWBDebugInfo	no

'hiso'	Histogram	no
'hyperlapse_dbg_i	.nfo' HyperlapsDebugInfo	no
'sensor_id'	SensorID	no
'xidiri'	Xidiri	no

#### DJI ThermalParams Tags

Thermal parameters extracted from APP4 of DJI RJPEG files from the  $\mathtt{ZH20T}.$ 

Index1	Tag Name	Writable
36	K1	no
40	K2	no
44	K3	no
48	K4	no
52	KF	no
56	B1	no
60	B2	no
68	ObjectDistance	no
70	RelativeHumidity	no
72	Emissivity	no
74	Reflection	no
76	AmbientTemperature	no
80	D2	no
84	KJ	no
86	DB	no
88	KK	no

#### DJI ThermalParams2 Tags

Thermal parameters extracted from APP4 of DJI M3T RJPEG files.

Index1	Tag Name	Writable
0	AmbientTemperature	no
4	ObjectDistance	no
8	Emissivity	no
12	RelativeHumidity	no
16	ReflectedTemperature	no
101	IDString	no

### DJI ThermalParams3 Tags

Thermal parameters extracted from APP4 of some DJI RJPEG files.

Index1	Tag Name	Writable
4	RelativeHumidity	no
6	ObjectDistance	no
8	Emissivity	no
10	ReflectedTemperature	no

#### DJI Protobuf Tags

Tags found in protobuf-format DJI djmd and dbgi timed metadata. The known tags listed below are extracted by default, but unknown djmd tags may be extracted as well by setting the Unknown option to 1, or 2 to also extract unknown dbgi debug tags. Tag ID's are composed of the corresponding .proto file name combined with the hierarchical protobuf field numbers.

ExifTool currently extracts timed GPS plus a few other tags from DJI devices which use the following protocols: dvtm\_AVATA2.proto (Avata 2), dvtm\_ac203.proto (Osmo Action 4), dvtm\_ac204.proto (Osmo Action 5), dvtm\_wm265e.proto (Mavic 3), dvtm\_pm320.proto (Matrice 30) and dvtm\_pm320.proto (Mini 4 Pro).

Note that with the protobuf format, numerical tags missing from the output for a given protocol should be considered to have the default

value of 0.

Tag ID	Tag Name	Writable
'Protocol'	Protocol	no
'dvtm_AVATA2_1-1-5'	SerialNumber	no
'dvtm_AVATA2_1-1-10'	Model	no
'dvtm_AVATA2_1 1 10	SerialNumber2	no
'dvtm_AVATA2_2-3'	FrameInfo	DJI FrameInfo
'dvtm_AVATA2_3-1-2'	TimeStamp	no
'dvtm_AVATA2_3-2-2-1'	ISO	no
'dvtm_AVATA2_3-2-4-1'	ShutterSpeed	no
'dvtm_AVATA2_3-2-6-1'	ColorTemperature	no
'dvtm_AVATA2_3-2-10-1'	FNumber	no
'dvtm_AVATA2_3-4-3'	DroneInfo	DJI DroneInfo
'dvtm_AVATA2_3-4-4-1'	GPSInfo	DJI GPSInfo
'dvtm_AVATA2_3-4-4-2'	AbsoluteAltitude	no
'dvtm_AVATA2_3-4-5-1'	RelativeAltitude	no
'dvtm_Mini4_Pro_1-1-5'	SerialNumber	no
'dvtm_Mini4_Pro_1-1-10'	Model	no
'dvtm_Mini4_Pro_2-3'	FrameInfo	DJI FrameInfo
'dvtm_Mini4_Pro_3-2-7-1'	ISO	no
'dvtm_Mini4_Pro_3-3-3'	DroneInfo	DJI DroneInfo
'dvtm_Mini4_Pro_3-3-4-1'	GPSInfo	DJI GPSInfo
'dvtm_Mini4_Pro_3-3-4-2'	AbsoluteAltitude	no
'dvtm_Mini4_Pro_3-3-5-1'	RelativeAltitude	no
 'dvtm_Mini4_Pro_3-4-3'	GimbalInfo	DJI GimbalInfo
'dvtm_Mini4_Pro_3-2-10-1'	ShutterSpeed	no
'dvtm_Mini4_Pro_3-2-11-1'		no
'dvtm_Mini4_Pro_3-2-32-1'		no
'dvtm_ac203_1-1-5'	SerialNumber	no
'dvtm_ac203_1-1-10'	Model	no
'dvtm_ac203_2-3'	FrameInfo	DJI FrameInfo
'dvtm_ac203_3-2-2-1'	ISO	no
'dvtm_ac203_3-2-4-1'	ShutterSpeed	no
'dvtm_ac203_3-2-6-1'	ColorTemperature	no
'dvtm_ac203_3-2-10-2'	AccelerometerX	no
'dvtm_ac203_3-2-10-3'	AccelerometerY	no
'dvtm_ac203_3-2-10-4'	AccelerometerZ	no
'dvtm_ac203_3-4-2-1'	GPSInfo	DJI GPSInfo
'dvtm_ac203_3-4-2-2'	GPSAltitude	no
'dvtm_ac203_3-4-2-6-1'	GPSDateTime	no
'dvtm_ac204_1-1-5'	SerialNumber Model	no
'dvtm_ac204_1-1-10' 'dvtm_ac204_2-3'	FrameInfo	no DJI FrameInfo
'dvtm_ac204_3-2-4-1'	ShutterSpeed	no
'dvtm_ac204_3-2-6-1'	ColorTemperature	no
'dvtm_ac204_3-2-10-2'	AccelerometerX	no
'dvtm_ac204_3-2-10-3'	AccelerometerY	no
'dvtm_ac204_3-2-10-4'	AccelerometerZ	no
 'dvtm_ac204_3-4-2-1'	GPSInfo	DJI GPSInfo
'dvtm_ac204_3-4-2-2'	GPSAltitude	no
'dvtm_ac204_3-4-2-6-1'	GPSDateTime	no
'dvtm_pm320_1-1-5'	SerialNumber	no
'dvtm_pm320_1-1-10'	Model	no
'dvtm_pm320_2-2'	FrameInfo	DJI FrameInfo
'dvtm_pm320_3-2-2-1'	ISO	no
'dvtm_pm320_3-2-3-1'	ShutterSpeed	no
'dvtm_pm320_3-2-4-1'	FNumber	no
'dvtm_pm320_3-2-6-1'	DigitalZoom	no
'dvtm_pm320_3-3-3'	DroneInfo	DJI DroneInfo
'dvtm_pm320_3-3-4-1'	GPSInfo	DJI GPSInfo
'dvtm_pm320_3-3-4-2'	AbsoluteAltitude	no
'dvtm_pm320_3-3-5-1'	RelativeAltitude	no
'dvtm_pm320_3-4-3'	GimbalInfo	DJI GimbalInfo
'dvtm_wm265e_1-1-5'	SerialNumber	no
'dvtm_wm265e_1-1-10'	Model FrameInfo	no
'dvtm_wm265e_2-2' 'dvtm_wm265e_3-2-2-1'	ISO	DJI FrameInfo no
'dvtm_wm265e_3-2-3-1'	ShutterSpeed	no
		220

DigitalZoom	no
DroneInfo	DJI DroneInfo
GPSInfo	DJI GPSInfo
AbsoluteAltitude	no
RelativeAltitude	no
GimbalInfo	DJI GimbalInfo
	DroneInfo GPSInfo AbsoluteAltitude RelativeAltitude

### DJI FrameInfo Tags

Field #	Tag Name	Writable
1	FrameWidth	no
2	FrameHeight	no
3	FrameRate	no

# DJI DroneInfo Tags

Tag Name	Writable
DroneRoll	no
DronePitch	no
DroneYaw	no
	DronePitch

# DJI GPSInfo Tags

Field #	Tag Name	Writable
1	CoordinateUnits	no
2	GPSLatitude	no
3	GPSLongitude	no

# DJI GimbalInfo Tags

Field #	Tag Name	Writable
1	GimbalPitch	no
2	GimbalRoll	no
3	GimbalYaw	no
	1 2	2 GimbalRoll

# DJI Glamour Tags

Glamour settings used by some DJI models.

Tag ID	Tag Name	Writable
'acne_spot_removal'	AcneSpotRemoval	no
'beauty_enable'	BeautyEnable	no
'blush'	Blush	no
'dark_circle'	DarkCircle	no
'eye_enlarge'	EyeEnlarge	no
'eyebrows'	Eyebrows	no
'face_slimming'	FaceSlimming	no
'head_shrinking'	HeadShrinking	no
'leg_longer'	LegLonger	no
'lipstick'	Lipstick	no
'mouth_beautify'	MouthModify	no
'nose_slimming'	NoseSlimming	no
'smoother'	Smoother	no
'teeth_whitening'	TeethWhitening	no
'whitening'	Whitening	no

### FLIR Tags

Information extracted from the maker notes of JPEG images from thermal imaging cameras by FLIR Systems Inc.  $\,$ 

Tag ID	Tag Name	Writable
$0 \times 0001$	ImageTemperatureMax	rational64u
0x0002	ImageTemperatureMin	rational64u
0x0003	Emissivity	rational64u

$0 \times 0004$	UnknownTemperature?	rational64u
0x0005	CameraTemperatureRangeMax?	rational64u
0x0006	CameraTemperatureRangeMin?	rational64u

### FLIR FFF Tags

Information extracted from FLIR FFF images and the APP1 FLIR segment of JPEG images. These tags may also be extracted from the first frame of an FLIR SEQ file, or all frames if the ExtractEmbedded option is used. Setting ExtractEmbedded to 2 also the raw thermal data from all frames.

Tag ID	Tag Name	Writable
'_header'	FFFHeader	FLIR Header
0x0001	RawData	FLIR RawData
$0 \times 0005$	GainDeadData	FLIR GainDeadData
0x0006	CoarseData	FLIR CoarseData
0x000e	EmbeddedImage	FLIR EmbeddedImage
$0 \times 0020$	CameraInfo	FLIR CameraInfo
$0 \times 0021$	MeasurementInfo	FLIR MeasInfo
$0 \times 0022$	PaletteInfo	FLIR PaletteInfo
$0 \times 0023$	TextInfo	FLIR TextInfo
$0 \times 0024$	EmbeddedAudioFile	no
$0 \times 0028$	PaintData	FLIR PaintData
0x002a	PiP	FLIR PiP
0x002b	GPSInfo	FLIR GPSInfo
0x002c	MeterLink	FLIR MeterLink
0x002e	ParameterInfo	FLIR ParamInfo

#### FLIR Header Tags

Tags extracted from the FLIR FFF/AFF header.

Index1	Tag Name	Writable
4	CreatorSoftware	no

### FLIR RawData Tags

The thermal image data may be stored either as raw data, or in PNG format. If stored as raw data, ExifTool adds a TIFF header to allow the data to be viewed as a TIFF image. If stored in PNG format, the PNG image is extracted as-is. Note that most FLIR cameras using the PNG format seem to write the 16-bit raw image data in the wrong byte order.

Index2	Tag Name	Writable
1	RawThermalImageWidth	no
2	RawThermalImageHeight	no
16	RawThermalImageType	no
16.1	RawThermalImage	no

#### FLIR GainDeadData Tags

Information found in FFF-format .GAN calibration image files.

Index2	Tag Name	Writable
1	GainDeadMapImageWidth	no
2	GainDeadMapImageHeight	no
16	GainDeadMapImageType	no
16.1	GainDeadMapImage	no

### FLIR CoarseData Tags

Information found in FFF-format .CRS correction image files.

Index2	Tag Name	Writable

# -- ExifTool 13.24 Tag Names --

1	CoarseMapImageWidth	no
2	CoarseMapImageHeight	no
16	CoarseMapImageType	no
16.1	CoarseMapImage	no

### FLIR EmbeddedImage Tags

Index2	Tag Name	Writable
1	EmbeddedImageWidth	no
2	EmbeddedImageHeight	no
16	EmbeddedImageType	no
16.1	EmbeddedImage	no

# FLIR CameraInfo Tags

FLIR camera information. The Planck tags are variables used in the temperature calculation. See <a href="https://exiftool.org/forum/index.php?topic=4898.msg23972#msg23972">https://exiftool.org/forum/index.php?topic=4898.msg23972#msg23972</a> for details.

Index1	Tag Name	Writable
32	Emissivity	no
36	ObjectDistance	no
40	ReflectedApparentTemperature	no
44	AtmosphericTemperature	no
48	IRWindowTemperature	no
52	IRWindowTransmission	no
60	RelativeHumidity	no
88	PlanckR1	no
92	PlanckB	no
96	PlanckF	no
112	AtmosphericTransAlpha1	no
116	AtmosphericTransAlpha2	no
120	AtmosphericTransBeta1	no
124	AtmosphericTransBeta2	no
128	AtmosphericTransX	no
144	CameraTemperatureRangeMax	no
148	CameraTemperatureRangeMin	no
152	CameraTemperatureMaxClip	no
156	CameraTemperatureMinClip	no
160	CameraTemperatureMaxWarn	no
164	CameraTemperatureMinWarn	no
168	CameraTemperatureMaxSaturated	no
172	CameraTemperatureMinSaturated	no
212	CameraModel	no
244	CameraPartNumber	no
260	CameraSerialNumber	no
276	CameraSoftware	no
368	LensModel	no
400	LensPartNumber	no
416	LensSerialNumber	no
436	FieldOfView	no
492	FilterModel	no
508	FilterPartNumber	no
540	FilterSerialNumber	no
776	PlanckO	no
780	PlanckR2	no
784	RawValueRangeMin	no
786	RawValueRangeMax	no
824	RawValueMedian	no
828	RawValueRange	no
900	DateTimeOriginal	no
912	FocusStepCount	no
1116	FocusDistance	no
1124	FrameRate	no

Tags listed below are only for the first measurement tool, however multiple measurements may be added, and information is extracted for all of them. Tags for subsequent measurements are generated as required with the prefixes "Meas2", "Meas3", etc.

Tag Name	Writable
Meas1Label	no
Meas1Params	no
Meas1Type	no

### FLIR PaletteInfo Tags

Index1	Tag Name	Writable
0	PaletteColors	no
6	AboveColor	no
9	BelowColor	no
12	OverflowColor	no
15	UnderflowColor	no
18	Isotherm1Color	no
21	Isotherm2Color	no
26	PaletteMethod	no
27	PaletteStretch	no
48	PaletteFileName	no
80	PaletteName	no
112	Palette	no

# FLIR TextInfo Tags

Tag Name	Writable
Label0	no
Label1	no
Label2	no
Label3	no
Value0	no
Value1	no
Value2	no
Value3	no

# FLIR PaintData Tags

Information generated by FLIR Tools "Paint colors" tool.

Index2	Tag Name	Writable
5	PaintImageWidth	no
6	PaintImageHeight	no
20	PaintImageType	no
20.1	PaintImage	no

# FLIR PiP Tags

FLIR Picture in Picture tags.

Index2	Tag Name	Writable
0	Real2IR	no
2	OffsetX	no
3	OffsetY	no
4	PiPX1	no
5	PiPX2	no
6	PiPY1	no
7	PiPY2	no

# FLIR GPSInfo Tags

Index1	Tag Name	Writable

# -- ExifTool 13.24 Tag Names --

0	GPSValid	no
Ū		110
4	GPSVersionID	no
8	GPSLatitudeRef	no
10	GPSLongitudeRef	no
16	GPSLatitude	no
24	GPSLongitude	no
32	GPSAltitude	no
64	GPSDOP	no
68	GPSSpeedRef	no
70	GPSTrackRef	no
72	GPSImgDirectionRef	no
76	GPSSpeed	no
80	GPSTrack	no
84	GPSImgDirection	no
88	GPSMapDatum	no

# FLIR MeterLink Tags

Tags containing Meterlink humidity meter information.

Index1	l Tag Name	Writable
26	ReadinglUnits	no
28	Reading1Description	no
32	Reading1Device	no
96	Reading1Value	no
126	Reading2Units	no
128	Reading2Description	no
132	Reading2Device	no
196	Reading2Value	no
226	Reading3Units	no
228	Reading3Description	no
232	Reading3Device	no
296	Reading3Value	no
326	Reading4Units	no
328	Reading4Description	no
332	Reading4Device	no
396	Reading4Value	no

# FLIR ParamInfo Tags

Tag Name	Writable
DateTimeGenerated	no
Param0	no
Param1	no
Param2	no
Param3	no

# FLIR UserData Tags

Tags written by some FLIR cameras in a top-level (!) "udta" atom of MP4 videos.

Tag ID	Tag Name	Writable
'uuid'	FLIR_Parts	FLIR Parts
	FLIR_Serial	FLIR SerialNums
	FLIR_Params	FLIR Params
	FLIR_UnknownUUID	FLIR UnknownUUID
	FLIR_GPS	FLIR GPS_UUID
	FLIR_MoreInfo	FLIR MoreInfo
	SoftwareComponents?	no
	FLIR_Unknown?	no
	Units	no+
	ThumbnailImage	no

# FLIR Parts Tags

Tags extracted from the "uuid" box with ID

43c3993b0f94424b82056b66513f485d in FLIR MP4 videos.

Index1	Tag Name	Writable
4	BAHPVer	no
	BALPVer	no
	Battery	no
	BAVPVer	no
	CamCore	no
	DetectorBoard	no
	Detector	no
	GIDCVer	no
	GIDPVer	no
	GIPC_CPLD	no
	GIPCVer	no
	GIXIVer	no
	MainBoard	no
	Optics	no
	PartNumber	no

#### FLIR SerialNums Tags

Tags extracted from the "uuid" box with ID 57f5b93e51e448afa0d9c3ef1b37f712 in FLIR MP4 videos.

Index1	Tag Name	Writable
12	UnknownSerial1?	no
45	UnknownSerial2?	no
78	UnknownSerial3?	no
111	UnknownSerial4?	no
123	UnknownNumber?	no
126	CameraSerialNumber	no

# FLIR Params Tags

Tags extracted from the "uuid" box with ID 41e5dcf9e80a41ceadfe7f0c58082c19 in FLIR MP4 videos.

Index4	Tag Name	Writable
1	ReflectedApparentTemperature	no
2	AtmosphericTemperature	no
3	Emissivity	no
4	ObjectDistance	no
5	RelativeHumidity	no
6	EstimatedAtmosphericTrans	no
7	IRWindowTemperature	no
8	IRWindowTransmission	no

### FLIR UnknownUUID Tags

Tags extracted from the "uuid" box with ID 574520502cbb44adae5415e9b839d903 in FLIR MP4 videos.

Index4	Tag Name	Writable
[no tags	known]	

### FLIR GPS UUID Tags

Tags extracted from the "uuid" box with ID 7f2e21008b464918afb1de709a74f6f5 in FLIR MP4 videos.

Index4	Tag Name	Writable
1	GPSLatitude	no
2	GPSLongitude	no
3	GPSAltitude	no

### FLIR MoreInfo Tags

Tags extracted from the "uuid" box with ID 2b452fdc74354094baee22a6b23a7cf8 in FLIR MP4 videos.

Index1	Tag Name	Writable
5	LensModel	no
11	UnknownTemperature1?	no
15	UnknownTemperature2?	no

#### FLIR AFF Tags

Tags extracted from FLIR "AFF" SEQ images.

Tag ID	Tag Name	Writa	able
'_header'	AFFHeader	FLIR	Header
0x0001	AFF1	FLIR	AFF1
0x0005	AFF5	FLIR	AFF5

# FLIR AFF1 Tags

Index2	Tag Name	Writable
1	SensorWidth	no
2	SensorHeight	no

# FLIR AFF5 Tags

Index2	Tag Name	Writable
19	SensorWidth	no
20	SensorHeight	no

# FLIR FPF Tags

Tags extracted from FLIR Public image Format (FPF) files.

Index1	Tag Name	Writable
32	FPFVersion	no
36	ImageDataOffset	no
40	ImageType	no
42	ImagePixelFormat	no
44	ImageWidth	no
46	ImageHeight	no
48	ExternalTriggerCount	no
52	SequenceFrameNumber	no
120	CameraModel	no
152	CameraPartNumber	no
184	CameraSerialNumber	no
216	CameraTemperatureRangeMin	no
220	CameraTemperatureRangeMax	no
224	LensModel	no
256	LensPartNumber	no
288	LensSerialNumber	no
320	FilterModel	no
336	FilterPartNumber	no
384	FilterSerialNumber	no
480	Emissivity	no
484	ObjectDistance	no
488	${\tt ReflectedApparentTemperature}$	no
492	AtmosphericTemperature	no
496	RelativeHumidity	no
500	ComputedAtmosphericTrans	no
504	${\tt EstimatedAtmosphericTrans}$	no
508	ReferenceTemperature	no
512	IRWindowTemperature	no
516	IRWindowTransmission	no

	ExifTool 13.24 Tag Names -	· <del>-</del>
584	DateTimeOriginal	no
676	CameraScaleMin	no
680	CameraScaleMax	no
684	CalculatedScaleMin	no
688	CalculatedScaleMax	no
692	ActualScaleMin	no
696	ActualScaleMax	no
FujiFilm Tags		1. 1.1
Tag ID	Tag Name	Writable
0×0000	Version	undef
	InternalSerialNumber	
0x0010 0x1000	Quality	string string
0x1000 0x1001	Sharpness	int16u
0x1001 0x1002	WhiteBalance	int16u
0x1002 0x1003	Saturation	int16u
0x1003	Contrast	int16u
0x1004 0x1005	ColorTemperature	int16u
0x1005 0x1006	Contrast	int16u
0x1000 0x100a	WhiteBalanceFineTune	int32s[2]
0x100a 0x100b	NoiseReduction	int16u
0x100b 0x100e	NoiseReduction	int16u
	Clarity	int32s
0x1001 0x1010	FujiFlashMode	int16u
0x1010 0x1011	FlashExposureComp	rational64s
0x1011 0x1020	Macro	int16u
0x1020 0x1021	FocusMode	int16u
	AFMode	int16u
	FocusPixel	int16u[2]
0x1023 0x102b	PrioritySettings	FujiFilm PrioritySettings
0x102b 0x102d	FocusSettings	FujiFilm FocusSettings
0x102a	AFCSettings	FujiFilm AFCSettings
0x102C	SlowSync	int16u
0x1030	PictureMode	int16u
0x1032	ExposureCount	int16u
0x1033	EXRAuto	int16u
0x1034	EXRMode	int16u
0x1040	ShadowTone	int32s
0x1041	HighlightTone	int32s
0x1044	DigitalZoom	int32u
0x1045	LensModulationOptimizer	int32u
0x1047	GrainEffectRoughness	int32s
0x1048	ColorChromeEffect	int32s
0x1049	BWAdjustment	int8s
0x104b	BWMagentaGreen	int8s
0x104c	GrainEffectSize	int16u
0x104d	CropMode	int16u
0x104e	ColorChromeFXBlue	int32s
0x1050	ShutterType	int16u
0x1051	CropFlag	int8u
0x1052	CropTopLeft	int32u
0x1053	CropSize	int32u
0x1100	AutoBracketing	int16u
0x1101	SequenceNumber	int16u
0x1103	DriveSettings	FujiFilm DriveSettings
0x1105	PixelShiftShots	int16u
0x1106	PixelShiftOffset	rational64s[2]
0x1153	PanoramaAngle	int16u
0x1154	PanoramaDirection	int16u
0x1201	AdvancedFilter	int32u
0 1 2 1 0	ColorModo	in+1611

int16u

int16u

int16u

int16u

string

int16u

int16u

int16u

int16u

0x1210 ColorMode

0x1304

0x1400

 $0 \times 1401$ 

0x1402

0x1403

0x1300 BlurWarning

0x1301 FocusWarning

0x1302 ExposureWarning

GEImageSize

FilmMode

DynamicRange

DynamicRangeSetting

DevelopmentDynamicRange

	EXITTOOL 13.24	rag Names
0x1404	MinFocalLength	rational64s
$0 \times 1405$	MaxFocalLength	rational64s
0x1406	MaxApertureAtMinFocal	rational64s
$0 \times 1407$	MaxApertureAtMaxFocal	rational64s
0x140b	AutoDynamicRange	int16u
0x1422	ImageStabilization	int16u[3]
0x1425	SceneRecognition	int16u
0x1431	Rating	int32u
0x1436	ImageGeneration	int16u
0x1438	ImageCount	int16u
0x1443	DRangePriority	int16u
0x1444	DRangePriorityAuto	int16u
0x1445	DRangePriorityFixed	int16u
0x1446	FlickerReduction	int32u
0x1447	FujiModel	string
0x1448	FujiModel2	string
0x144d	RollAngle	rational64s
0x3803	VideoRecordingMode	int32u
0x3804	PeripheralLighting	int16u
0x3806	VideoCompression	int16u
0x3820	FrameRate	int16u
0x3821	FrameWidth	int16u
0x3822	FrameHeight	int16u
0x3824	FullHDHighSpeedRec	int32u
$0 \times 4005$	FaceElementSelected	int16u[4]
$0 \times 4100$	FacesDetected	int16u
$0 \times 4103$	FacePositions	int16u[n]
$0 \times 4200$	NumFaceElements	int16u
$0 \times 4201$	FaceElementTypes	int8u[n]
0x4203	FaceElementPositions	int16u[n]
0x4282	FaceRecInfo	FujiFilm FaceRecInfo
0x8000	FileSource	string
0x8002	OrderNumber	int32u
0x8003	FrameNumber	int16u
0xb211	Parallax	rational64s
<u>ujiFilm</u>	PrioritySettings Tags	

# Fu

Index2	Tag Name	Writable
0.1	AF-SPriority	int16u & 0x0f
0.2	AF-CPriority	int16u & 0xf0

# FujiFilm FocusSettings Tags

Index4	Tag Name	Writable
0.1	FocusMode2	int32u & 0x0f
0.2	PreAF	int32u & 0xf0
0.3	AFAreaMode	int32u & 0xf00
0.4	AFAreaPointSize	int32u & 0xf000
0.5	AFAreaZoneSize	int32u & 0xff0000

# FujiFilm AFCSettings Tags

Index4	Tag Name	Writable
0	AF-CSetting	int32u
0.1	AF-CTrackingSensitivity	int32u & 0x0f
0.2	AF-CSpeedTrackingSensitivity	int32u & 0xf0
0.3	AF-CZoneAreaSwitching	int32u & 0xf00

# FujiFilm DriveSettings Tags

Index4	Tag Name	Writable
0.1	DriveMode	int32u & 0xff
0.2	DriveSpeed	int32u & 0xff000000

# FujiFilm FaceRecInfo Tags

Face recognition information.

Tag Name	Writable
FacelBirthday	no
Face1Category	no
Face1Name	no
Face2Birthday	no
Face2Category	no
Face2Name	no
Face3Birthday	no
Face3Category	no
Face3Name	no
Face4Birthday	no
Face4Category	no
Face4Name	no
Face5Birthday	no
Face5Category	no
Face5Name	no
Face6Birthday	no
Face6Category	no
Face6Name	no
Face7Birthday	no
Face7Category	no
Face7Name	no
Face8Birthday	no
Face8Category	no
Face8Name	no

### FujiFilm RAFHeader Tags

Tags extracted from the header of RAF images.

Index1	Tag Name	Writable
60	RAFVersion	no
108	RAFCompression	no

# FujiFilm RAF Tags

FujiFilm RAF images contain meta information stored in a proprietary FujiFilm RAF format, as well as EXIF information stored inside an embedded JPEG preview image. The table below lists tags currently decoded from the RAF-format information.

Tag ID	Tag Name	Writable
$0 \times 0100$	RawImageFullSize	no
$0 \times 0110$	RawImageCropTopLeft	no
$0 \times 0111$	RawImageCroppedSize	no
$0 \times 0115$	RawImageAspectRatio	no
$0 \times 0117$	RawZoomActive	no
0x0118	RawZoomTopLeft	no
$0 \times 0119$	RawZoomSize	no
0x0121	RawImageSize	no
$0 \times 0130$	FujiLayout	no
0x0131	XTransLayout	no
0x2000	WB_GRGBLevelsAuto	no
0x2100	WB_GRGBLevelsDaylight	no
0x2200	WB_GRGBLevelsCloudy	no
0x2300	WB_GRGBLevelsDaylightFluor	no
0x2301	WB_GRGBLevelsDayWhiteFluor	no
0x2302	WB_GRGBLevelsWhiteFluorescent	no
0x2310	WB_GRGBLevelsWarmWhiteFluor	no
0x2311	WB_GRGBLevelsLivingRoomWarmWhiteFluor	no
0x2400	WB_GRGBLevelsTungsten	no
0x2ff0	WB_GRGBLevels	no
$0 \times 9200$	RelativeExposure	no
$0 \times 9650$	RawExposureBias	no

0xc000 RAFData FujiFilm RAFData

# FujiFilm RAFData Tags

Index1	Tag Name	Writable
0	RawImageWidth	no
4	RawImageWidth	no
	RawImageHeight	no
8	RawImageWidth	no
	RawImageHeight	no
12	RawImageHeight	no

### FujiFilm IFD Tags

Tags found in the FujiIFD information of RAF images from some models.

Tag ID	Tag Name	Writable
0xf000	FujiIFD	FujiFilm IFD
0xf001	RawImageFullWidth	no
0xf002	RawImageFullHeight	no
0xf003	BitsPerSample	no
0xf007	StripOffsets	no
0xf008	StripByteCounts	no
0xf00a	BlackLevel	no
0xf00b	GeometricDistortionParams	no
0xf00c	WB_GRBLevelsStandard	no
0xf00d	WB_GRBLevelsAuto	no
0xf00e	WB_GRBLevels	no
0xf00f	ChromaticAberrationParams	no
0xf010	VignettingParams	no

#### FujiFilm MRAW Tags

Tags extracted from the M-RAW header of multi-image RAF files. The family 1 group name for these tags is "M-RAW".

Tag ID	Tag Name	Writable
$0 \times 0001$	RawImageNumber	no
0x0005	ExposureTime	no
0x0006	FNumber	no
$0 \times 0007$	ISO	no

### FujiFilm FFMV Tags

Information found in the FFMV atom of MOV videos.

Index1	Tag Name	Writable
0	MovieStreamName	no

# FujiFilm MOV Tags

This information is found in MOV videos from some FujiFilm cameras.

Index1	Tag Name	Writable
0	Make	no
24	Model	no
46	ExposureTime	no
50	FNumber	no
58	ExposureCompensation	no

# GE Tags

This table lists tags found in the maker notes of some General Imaging camera models.

$0 \times 0202$	Macro	int16u
$0 \times 0207$	GEModel	string
0x0300	GEMake	string

### GoPro Tags

GoPro GPMF Tags

Tags extracted from the GPMF box of GoPro MP4 videos, the APP6 "GoPro" segment of JPEG files, and from the "gpmd" timed metadata if the ExtractEmbedded (-ee) option is enabled. Many more tags exist, but are currently unknown and extracted only with the Unknown (-u) option. Please let me know if you discover the meaning of any of these unknown tags. See <a href="https://github.com/gopro/gpmf-parser">https://github.com/gopro/gpmf-parser</a> for details about this format.

Tag ID	Tag Name	Writable
'AALP'	AudioLevel	no
'ABSC'	AutoBoostScore	no
'ACCL'	Accelerometer	no
'ALLD'	AutoLowLightDuration	no
'APTO'	AudioProtuneOption	no
'ARUW'	AspectRatioUnwarped	no
'ARWA'	AspectRatioWarped	no
'ATTD'	Attitude	no
'ATTR'	AttitudeTarget	no
'AUBT'	AudioBlueTooth	no
'AUDO'	AudioSetting	no
'AUPT'	AutoProtune	no
'BITR'	BitrateSetting	no
'BPOS'	Controller?	no
'CASN'	CameraSerialNumber	no
'CDAT'	CreationDate	no
'CDTM'	CaptureDelayTimer	no
'CLDP'	ClassificationDataPresent	no
'CORI'	CameraOrientation	no
'CPIN'	ChapterNumber	no
'CSEN'	CoyoteSense	no
'CTRL'	ControlLevel	no
'CYTS'	CoyoteStatus	no
'DEVC'	DeviceContainer	GoPro GPMF
'DUST'	DurationSetting	no
'DVID'	DeviceID?	no
'DVNM'	DeviceName	no
'DZMX'	DigitalZoomAmount	no
'DZOM'	DigitalZoomOn	no
'DZST'	DigitalZoom	no
'EISA'	ElectronicImageStabilization	no
'EISE'	ElectronicStabilizationOn	no
'EMPT'	Empty?	no
'ESCS'	EscapeStatus?	no
'EXPT'	ExposureType	no
'FACE'	FaceDetected	no
'FCNM'	FaceNumbers	no
'FMWR'	FirmwareVersion	no
'FWVS'	OtherFirmware	no
'GLPI'	GPSPos	GoPro GLPI
'GPRI'	GPSRaw?	GoPro GPRI
'GPS5'	GPSInfo	GoPro GPS5
'GPS9'	GPSInfo9	GoPro GPS9
'GPSA'	GPSAltitudeSystem	no
'GPSF'	GPSMeasureMode	no
'GPSP'	GPSHPositioningError	no
'GPSU'	GPSDateTime	no
'GRAV'	GravityVector	no
'GYRO'	Gyroscope	no
'HCLT'	HorizonControl	no
'HDRV'	HDRVideo	no
'HSGT'	HindsightSettings	no

	EXILIOOI 13.21 149 Names	
'HUES'	PrediminantHue	no
'IORI'	ImageOrientation	no
'ISOE'	ISOSpeeds	no
'ISOG'	ImageSensorGain	no
'KBAT'	BatteryStatus	GoPro KBAT
'LNED'	LocalPositionNED	no
'MAGN'	Magnetometer	no
'MAPX'	MappingXCoefficients	no
'MAPY'	MappingYCoefficients	no
'MINF'	Model	no
'MMOD'	MediaMode	no
'MTRX'	AccelerometerMatrix	no
'MUID'	MediaUniqueID	no
'MWET'	MicrophoneWet	no
'MXCF'	MappingXMode	no
'MYCF'	MappingYMode	no
'ORDP'	OrientationDataPresent	no
'OREN'	AutoRotation	no
'ORIN'	InputOrientation	no
'ORIO'	OutputOrientation	no
'PHDR'	HDRSetting	no
'PIMD'	ProtuneISOMode	no
'PIMN'	AutoISOMin	no
'PIMX'	AutoISOMax	no
'POLY'	PolynomialCoefficients	no
'PRES'	PhotoResolution	no
'PRJT'	LensProjection	no
'PRTN'	Protune	no
'PTCL'	ColorMode	no
'PTEV'	ExposureCompensation	no
'PTSH'	Sharpness	no
'PTWB'	WhiteBalance PowerProfile	no
'PWPR'	PolynomialPower	no
'PYCF' 'RAMP'	SpeedRampSetting	no
'RATE'	Rate	no
'RMRK'	Comments	no no
'SCAL'	ScaleFactor?	no
'SCAP'	ScheduleCapture	no
'SCEN'	SceneClassification	no
'SCPR'	ScaledPressure	no
'SCTM'	ScheduleCaptureTime	no
'SHUT'	ExposureTimes	no
'SIMU'	ScaledIMU	no
'SIUN'	SIUnits?	no
'SMTR'	SpotMeter	no
'SROT'	SensorReadoutTime	no
'STMP'	TimeStamp	no
'STNM'	StreamName?	no
'STRM'	NestedSignalStream	GoPro GPMF
'SYST'	SystemTime	no
'TMPC'	CameraTemperature	no
'TSMP'	TotalSamples?	no
'TYPE'	StructureType?	no
'TZON'	TimeZone	no
'UNIF'	InputUniformity	no
'UNIT'	Units?	no
'VERS'	MetadataVersion	no
'VFOV'	FieldOfView	no
'VFPS'	VideoFrameRate	no
'VFRH'	VisualFlightRulesHUD	no
'VRES'	VideoFrameSize	no
'WBAL'	ColorTemperatures	no
'WNDM'	WindProcessing	no
'WRGB'	WhiteBalanceRGB	no
'YAVG'	LumaAverage	no
		110
'ZFOV' 'ZMPL'	DiagonalFieldOfView ZoomScaleNormalization	no

Index	Tag Name	Writable
	anan I m'	
0	GPSDateTime	no
1	GPSLatitude	no
2	GPSLongitude	no
3	GPSAltitude	no
5	GPSSpeedX	no
6	GPSSpeedY	no
7	GPSSpeedZ	no
8	GPSTrack	no

### GoPro GPRI Tags

Index	Tag Name	Writable
0	GPSDateTimeRaw	no
1	GPSLatitudeRaw	no
2	GPSLongitudeRaw	no
3	GPSAltitudeRaw	no
6	GPSSpeedRaw	no
7	GPSTrackRaw	no

# GoPro GPS5 Tags

Index	Tag Name	Writable
0	GPSLatitude	no
1	GPSLongitude	no
2	GPSAltitude	no
3	GPSSpeed	no
4	GPSSpeed3D	no

# GoPro GPS9 Tags

Index	Tag Name	Writable
0	GPSLatitude	no
1	GPSLongitude	no
2	GPSAltitude	no
3	GPSSpeed	no
4	GPSSpeed3D	no
6	GPSDateTime	no
7	GPSDOP	no
8	GPSMeasureMode	no

# GoPro KBAT Tags

Battery status information found in GoPro Karma videos.

Index	Tag Name	Writable
0	BatteryCurrent	no
1	BatteryCapacity	no
3	BatteryTemperature	no
4	BatteryVoltage1	no
5	BatteryVoltage2	no
6	BatteryVoltage3	no
7	BatteryVoltage4	no
8	BatteryTime	no
14	BatteryLevel	no

# GoPro fdsc Tags

Tags extracted from the MP4 "fdsc" timed metadata when the  ${\tt ExtractEmbedded}$  (-ee) option is used.

Index1	Tag Name	Writable
8	FirmwareVersion	no

23	SerialNumber	no
87	OtherSerialNumber	no
102	Model	no

#### HP Tags

These tables list tags found in the maker notes of some Hewlett-Packard camera models.

The first table lists tags found in the EXIF-format maker notes of the PhotoSmart 720 (also used by the Vivitar ViviCam 3705, 3705B and 3715).

Tag ID	Tag Name	Writable
0x0e00	PrintIM	PrintIM

#### HP Type2 Tags

These tags are used by the PhotoSmart E427.

Tag ID	Tag Name	Writable
'Lens Shading'	LensShading	no
'PreviewImage'	PreviewImage	no
'Serial Number'	SerialNumber	no

### HP Type4 Tags

These tags are used by the PhotoSmart M627.

Index1	Tag Name	Writable
12	MaxAperture	no
16	ExposureTime	no
20	CameraDateTime	no
52	ISO	no
92	SerialNumber	no

#### HP Type6 Tags

These tags are used by the PhotoSmart M425, M525 and M527.

Index1	Tag Name	Writable
12	FNumber	no
16	ExposureTime	no
20	CameraDateTime	no
52	ISO	no
88	SerialNumber	no

#### HP TDHD Tags

These tags are extracted from the APP6 "TDHD" segment of Photosmart R837 JPEG images. Many other unknown tags exist in is data, and can be seen with the Unknown (-u) option.

Tag ID	Tag Name	Writable
'CMSN'	SerialNumber	no
'FWRV'	FirmwareVersion	no
'LSLV'	LSLV	HP TDHD
'TDHD'	TDHD	HP TDHD

#### JVC Tags

JVC EXIF maker note tags.

Tag ID	Tag Name	Writable
$0 \times 0002$	CPUVersions	no
$0 \times 0003$	Ouality	no

#### JVC Text Tags

JVC/Victor text-based maker note tags.

Tag ID	Tag Name	Writable
'QTY'	Quality	no
'VER'	MakerNoteVersion	no

#### Kodak Tags

Many Kodak models don't store the maker notes in standard IFD format, and these formats vary with different models. Some information has been decoded, but much of the Kodak information remains unknown.

The table below contains the most common set of Kodak tags. The following Kodak camera models have been tested and found to use these tags: C360, C663, C875, CX6330, CX6445, CX7330, CX7430, CX7525, CX7530, DC4800, DC4900, DX3500, DX3600, DX3900, DX4330, DX4530, DX4900, DX6340, DX6440, DX6490, DX7440, DX7590, DX7630, EasyShare-One, LS420, LS443, LS633, LS743, LS753, V530, V550, V570, V603, V610, V705, Z650, Z700, Z710, Z730, Z740, Z760 and Z7590.

Index1	Tag Name	Writable
0	KodakModel	string[8]
9	Quality	int8u
10	BurstMode	int8u
12	KodakImageWidth	int16u
14	KodakImageHeight	int16u
16	YearCreated	int16u
18	MonthDayCreated	int8u[2]
20	TimeCreated	int8u[4]
24	BurstMode2?	int16u
27	ShutterMode	int8u
28	MeteringMode	int8u
29	SequenceNumber	int8u
30	FNumber	int16u
32	ExposureTime	int32u
36	ExposureCompensation	int16s
38	VariousModes?	int16u
40	Distancel?	int32u
44	Distance2?	int32u
48	Distance3?	int32u
52	Distance4?	int32u
56	FocusMode	int8u
58	VariousModes2?	int16u
60	PanoramaMode?	int16u
62	SubjectDistance?	int16u
64	WhiteBalance	int8u
92	FlashMode	int8u
93	FlashFired	int8u
94	ISOSetting	int16u
96	ISO	int16u
98	TotalZoom	int16u
100	DateTimeStamp	int16u
102	ColorMode	int16u
104	DigitalZoom	int16u
107	Sharpness	int8s

#### Kodak IFD Tags

These tags are found in a separate IFD of JPEG, TIFF, DCR and KDC images from some older Kodak models such as the DC50, DC120, DCS760C, DCS Pro 14N, 14nx, SLR/n, Pro Back and Canon EOS D2000.

Tag ID	Tag Name	Writable
0x0000	KodakVersion	int8u[4]
$0 \times 0001$	UnknownEV?	rational64u
0x0003	ExposureValue	rational64u

	ExifTool 13.24 Tag Names	
0x03e9	OriginalFileName	string
0x03ea	KodakTag	int32u
0x03eb	SensorLeftBorder	int16u
0x03ec	SensorTopBorder	int16u
0x03ed	SensorImageWidth	int16u
0x03ee	SensorImageHeight	int16u
0x03ef	BlackLevelTop	int16u
0x03f0	BlackLevelBottom	int16u
0x03f1	TextualInfo	Kodak TextualInfo
0x03f2	FlashMode?	int16u
0x03f3	FlashCompensation	rational64s
0x03f4	WindMode?	int16u
0x03f5	FocusMode?	int16u
0x03f8 0x03f9	MinAperture MaxAperture	rational64u rational64u
0x0319 0x03fa	WhiteBalanceMode?	int16u
0x03fa	WhiteBalanceDetected?	int16u
0x03fc	WhiteBalance	int16u
0x03fd	Processing	Kodak Processing
	ProcessingParameters	no
0x03fe	ImageAbsoluteX	int16s
0x03ff	ImageAbsoluteY	int16s
$0 \times 0400$	ApplicationKeyString	string
$0 \times 0401$	Time	string
$0 \times 0402$	GPSString	string
$0 \times 0403$	EventLogCapture?	no
$0 \times 0404$	ComponentTable?	no
$0 \times 0405$	CustomIlluminant?	int16u
0x0406	CameraTemperature	rational64s
0x0407	CameraTemperature AdapterVoltage	no rational64u
0x0407 0x0408	BatteryVoltage	rational64u
$0 \times 0409$	DacVoltages	no
0x040a	IlluminantDetectorData?	no
0x040b	PixelClockFrequency	int32u
0x040c	CenterPixel	int16u[3]
0x040d	BurstCount	int16u
0x040e	BlackLevelRough	int16u
0x040f	OffsetMapHorizontal?	no
$0 \times 0410$	OffsetMapVertical?	no
$0 \times 0411$	Histogram?	no
$0 \times 0412$ $0 \times 0413$	VerticalClockOverlaps	int16u[2]
0x0413 0x0414	SensorTemperature XilinxVersion	no string
0x0414 0x0415	FirmwareVersion	int32u
0x0416	BlackLevelRoughAfter	int16u
$0 \times 0417$	BrightRowsTop	no
$0 \times 0418$	EventLogProcess	no
$0 \times 0419$	DacVoltagesFlush	no
0x041a	FlashUsed	no
$0 \times 041b$	FlashType	no
0x041c	SelfTimer	no
0x041d	AFMode	no
0x041e 0x041f	LensType ImageCropX	no int16s
0x0411 0x0420	ImageCropY	int16s
0x0420 $0x0421$	AdjustedTbnImageWidth	no
$0 \times 0422$	AdjustedTbnImageHeight	no
$0 \times 0423$	IntegrationTime	int32u
$0 \times 0424$	BracketingMode	no
$0 \times 0425$	BracketingStep	no
$0 \times 0426$	BracketingCounter	no
0x042e	HuffmanTableLength	no
0x042f	HuffmanTableValue	no
$0 \times 0438$	MainBoardVersion	int32u
$0 \times 0439$	ImagerBoardVersion	int32u
0x044c 0x05e6	FocusEdgeMap IdleTiming	no
0x05e6 0x05e7	FlushTiming	no no
0x05e7	IntegrateTiming	no
		-

	Exiliooi 13.24 lag Names	
0x05e9	RegisterReadTiming	no
0x05ea	FirstLineTransferTiming	no
0x05eb	ShiftTiming	no
0x05ec	NormalLineTransferTiming	no
0x05ed	TestTransferTiming	no
0x05fa	MinimumFlushRows	no
0x05fd 0x05fe	ImagerPowerOnDelayMsec ImagerInitialTimingCode	int32u no
0x051e 0x05ff	ImagerLogicProgram	no
0x0600	ImagerBiasSettlingDelayMsec	int32u
0x0604	IdleSequence	no
0x0605	FirstFlushSequence	no
0x0606	FinalFlushSequence	no
$0 \times 0607$	SampleBlackSequence	no
$0 \times 0608$	TransferSequence	no
0x060e	DacCountsPerVolt	no
0x060f	BlackDacChannel	no
0x0610	BlackAdCountsPerDacVolt	no
0x0611 0x0612	BlackTarget	no
0x0012 0x07d0	BlackDacSettlingMsec StandardMatrixDaylight	no rational64s[9]
0x07d0 0x07d1	StandardMatrixTungsten	rational64s[9]
0x07d1	StandardMatrixFluorescent	rational64s[9]
0x07d3	StandardMatrixFlash	rational64s[9]
0x07d4	StandardMatrixCustom	rational64s[9]
0x07da	DeviantMatrixDaylight	rational64s[9]
0x07db	DeviantMatrixTungsten	rational64s[9]
0x07dc	DeviantMatrixFluorescent	rational64s[9]
$0 \times 0.7 dd$	DeviantMatrixFlash	rational64s[9]
0x07de	DeviantMatrixCustom	rational64s[9]
0x07e4 0x07e5	UniqueMatrixDaylight	rational64s[9] rational64s[9]
0x07e5	UniqueMatrixTungsten UniqueMatrixFluorescent	rational64s[9]
0x07e0 0x07e7	UniqueMatrixFlash	rational64s[9]
0x07e8	UniqueMatrixCustom	rational64s[9]
0x07e9	UniqueMatrixAuto	rational64s[9]
0x0834	StandardWhiteDaylight	rational64s[3]
0x0835	StandardWhiteTungsten	rational64s[3]
$0 \times 0836$	StandardWhiteFluorescent	rational64s[3]
0x0837	StandardWhiteFlash	rational64s[3]
0x0838	StandardWhiteCustom	rational64s[3]
0x083e	DeviantWhiteDaylight	rational64s[3]
0x083f 0x0840	DeviantWhiteTungsten DeviantWhiteFluorescent	rational64s[3] rational64s[3]
0x0840 $0x0841$	DeviantWhiteFlash	rational64s[3]
0x0841	DeviantWhiteCustom	rational64s[3]
0x0846	ColorTemperature	int16u
$0 \times 0847$	WB_RGBLevelsAsShot	no
0x0848	WB_RGBLevelsDaylight	no
$0 \times 0849$	WB_RGBLevelsTungsten	no
0x084a	WB_RGBLevelsFluorescent	no
0x084b	WB_RGBLevelsFlash	no
0x084c	WB_RGBLevelsCustom	no
0x084d 0x0852	WB_RGBLevelsAuto	no rational64u[3]
0x0852 $0x0853$	WB_RGBMulDaylight WB_RGBMulTungsten	rational64u[3]
0x0055	WB_RGBMulFluorescent	rational64u[3]
0x0855	WB_RGBMulFlash	rational64u[3]
0x085c	WB_RGBCoeffsDaylight	no
0x085d	WB_RGBCoeffsTungsten	no
0x085e	WB_RGBCoeffsFluorescent	no
0x085f	WB_RGBCoeffsFlash	no
0x0898	ExposureGainDaylight	rational64s
$0 \times 0899$	ExposureGainTungsten	rational64s
0x089a	ExposureGainFluorescent	rational64s rational64s
0x089b 0x089c	ExposureGainFlash ExposureGainCustom	rational64s rational64s
0x089d	AnalogISOTable	rational64u[3]
0x089a	AnalogCaptureISO	int32u
0x089f	ISOCalibrationGain	rational64u

	ExifTool 13.24 Tag Names	
0x08a0	ISOCalibrationGainTable	no
0x08a1	ExposureHeadroomFactor	no
0x08ab	LinearitySplineTags	no
0x08fc 0x08fd	MonitorMatrix TonScaleTable	rational64s[9]
0x08fe	Gamma	no rational64u
0x08ff	LogLinTable	no
0x0900	LinLogTable	no
0x0901	GammaTable	no
0x0902	LogScale	rational64u
$0 \times 0903$	BaseISO	rational64u
$0 \times 0904$ $0 \times 0905$	LinLogCoring PatternGainConversionTable	int16u no
0x0906	DefectCount	no
0x0907	DefectList	no
$0 \times 0908$	DefectListPacked	no
$0 \times 0909$	ImageSpace	int16u
0x090a	ThumbnailCompressionTable	no
0x090b 0x090c	ThumbnailExpansionTable ImageCompressionTable	no no
0x090d	ImageExpansionTable	no
0x090e	EighteenPercentPoint	no
0x090f	DefectIsoCode	int16u
$0 \times 0910$	BaseISODaylight	rational64u
0x0911	BaseISOTungsten	rational64u
0x0912 0x0913	BaseISOFluorescent BaseISOFlash	rational64u rational64u
0x0913 0x091a	MatrixSelectThreshold	int16s
0x091b	MatrixSelectK	rational64u
0x091c	IlluminantDetectTable	no
0x091d	RGTable	no
0x091e	MatrixSelectThreshold1	int16s
0x091f 0x0924	MatrixSelectThreshold2 PortraitMatrix	int16s
0x0924 $0x0925$	PortraitToneScaleTable	no no
0x092e	EnableSharpening	int16u
0x092f	SharpeningKernel	int16s[25]
$0 \times 0930$	EdgeMapSlope	int16u
0x0931	EdgeMapX1	int16u
0x0932 0x0933	EdgeMapX2 KernelDenominators	int16u int16u[3]
0x0934	EdgeMapX3	int16u
0x0935	EdgeMapX4	int16u
$0 \times 0936$	SharpenForThumbnail	no
0x0937	EdgeSpline	no
$0 \times 0.938$	DownSampleBy2Hor	no
0x0939 0x093a	DownSampleBy2Ver DownSampleBy4Hor	no no
0x093b	DownSampleBy4Ver	no
0x093c	DownSampleBy3Hor	no
0x093d	DownSampleBy3Ver	no
0x093e	DownSampleBy6Hor	no
0x093f 0x0940	DownSampleBy6Ver DownSampleBy2Hor3MPdcr	no
0x0940 $0x0941$	DownSampleBy2Ver3MPdcr	no no
$0 \times 0942$	ThumbnailResizeRatio	no
$0 \times 0943$	AtCaptureUserCrop	int32u[4]
$0 \times 0944$	ImageResolution	int32u
$0 \times 0945$	ImageResolutionJpg	int32u
0x094c 0x094d	USMParametersLow USMParametersMed	no
0x094a 0x094e	USMParametersHigh	no no
0x094f	USMParametersHost	no
$0 \times 0950$	EdgeSplineLow	no
0x0951	EdgeSplineMed	no
$0 \times 0.0952$	EdgeSplineHigh	no
$0 \times 0953$ $0 \times 0954$	USMParametersHost6MP	no
0x0954 $0x0960$	USMParametersHost3MP PatternImagerWidth	no int16u
0x0961	PatternImagerHeight	int16u

	ExifTool 13.24 Tag Names	
$0 \times 0962$	PatternAreaWidth	int16u
$0 \times 0963$	PatternAreaHeight	int16u
$0 \times 0964$	PatternCorrectionGains	no
0x0965	PatternCorrectionOffsets	no
0x0966 0x0967	PatternX PatternY	int16u int16u
0x0967 $0x0968$	PatternCorrectionFactors	no
0x0969	PatternCorrectionFactorScale	int16u
0x096a	PatternCropRows1	int16u
0x096b	PatternCropRows2	int16u
0x096c	PatternCropCols1	int16u
0x096d	PatternCropCols2	int16u
0x096e	PixelCorrectionGains	no
0x096f 0x0970	StitchRows StitchColumns	no no
0x0970 $0x0971$	PixelCorrectionScale	int16u
0x0972	PixelCorrectionOffset	int16u
0x0988	LensTableIndex	no
$0 \times 0992$	DiffTileGains602832	no
$0 \times 0993$	DiffTileGains24t852822	no
0x099c	TileGainDeterminationTable	no
0x099d 0x099e	NemoBlurKernel NemoTileSize	no
0x099E 0x099f	NemoGainFactors	no no
0x09a0	NemoDarkLimit	no
0x09a1	NemoHighlight12Limit	no
0x09c4	ImagerFileProductionLevel	int16u
0x09c5	ImagerFileDateCreated	int32u
0x09c6	CalibrationVersion	string
0x09c7	ImagerFileTagsVersionStandard IFCameraModel	int16u
0x09c8 0x09c9	CalibrationHistory	string string
0x09ca	CalibrationLog	no
0x09ce	SensorSerialNumber	string
0x09f6	DefectConcealArtCorrectThres	no
0x09f7	SglColDCACThres1	no
0x09f8	SglColDCACThres2	no
0x09f9 0x0a01	SglColDCACTHres3	no
0x0a01 0x0a02	DblColDCACThres1 DblColDCACThres2	no no
0x0a0z	DefectConcealThresTable	no
0x0a28	MonoUniqueMatrix	no
0x0a29	MonoMonitorMatrix	no
0x0a2a	MonoToneScaleTable	no
0x0a5a	OmenInitialScaling	no
0x0a5b 0x0a5c	OmenInitialRows OmenInitialColumns	no
0x0a5c 0x0a5d	OmenInitialColumns OmenInitialIPFStrength	no int32s[4]
0x0a5a 0x0a5e	OmenEarlyStrength	int32s[4]
0x0a5f	OmenAutoStrength	int32s[4]
0x0a60	OmenAtCaptureStrength	int32s[4]
0x0a61	OmenAtCaptureMode	no
0x0a62	OmenFocalLengthLimit	int16s
0x0a64	OmenSurfaceIndex	int16s
0x0a65 0x0a66	OmenPercentToRationalLimitsRed OmenPercentToRationalLimitsGoR	no
0x0a67	OmenPercentToRationalLimitsBlue	no no
0x0a68	OmenPercentToRationalLimitsGoB	no
0x0a6e	OmenEarlyGoBSurface	no
0x0a6f	OmenEarlyGoBRows	no
0x0a70	OmenEarlyGoBColumns	no
0x0a73	OmenSmoothingKernel	no
0x0a74 0x0a75	OmenGradientOffset OmenGradientKernel	no
0x0a75 0x0a76	OmenGradientKernelTaps	no no
0x0a70	OmenRatioClipFactors	no
0x0a78	OmenRatioExclusionFactors	no
0x0a79	OmenGradientExclusionLimits	no
0x0a7a	OmenROICoordinates	no
0x0a7b	OmenROICoefficients	no

	ExilTool 13.24 Tag Names	
0x0a7c	OmenRangeWeighting	no
0x0a7d	OmenMeanToStrength	no
0x0bb8	FactoryWhiteGainsDaylight	no
0x0bb9	FactoryWhiteOffsetsDaylight	no
0x0bbb	DacGainsCoarse	
0x0bba	DacGainsFine	no
		no
0x0bbc	DigitalExposureGains	no
0x0bbd	DigitalExposureBiases	no
0x0bbe	BlackClamp	no
0x0bbf	ChannelCoarseGainAdjust	no
0x0bc0	BlackClampOffset	no
$0 \times 0 \text{bf } 4$	DMPixelThresholdFactor	no
0x0bf5	DMWindowThresholdFactor	no
0x0bf6	DMTrimFraction	no
0x0bf7	DMSmoothRejThresh	no
0x0bf8	DMFillRejThresh	no
0x0bf9	VMWsize	no
0x0bfa	DMErodeRadius	no
0x0bfb	DMNumPatches	no
0x0bfc	DMNoiseScale	no
0x0bfe	BrightDefectThreshold	no
0x0bfe	BrightDefectIntegrationMS	
0x0c00		no
	BrightDefectIsoCode	no
0x0c03	TopDarkRow1	no
0x0c04	TopDarkRow2	no
0x0c05	BottomDarkRow1	no
0x0c06	BottomDarkRow2	no
0x0c07	LeftDarkCol1	no
0x0c08	LeftDarkCol2	no
0x0c09	RightDarkCol1	no
0x0c0a	RightDarkCol2	no
0x0c0b	HMPixThresh	no
0x0c0c	HMColThresh	no
0x0c0d	HMWsize	no
0x0c0e	HMColRejThresh	no
0x0c0f	VMPixThresh	no
0x0c10	VMColThresh	no
0x0c10	VMNbands	no
0x0c11	VMColDropThresh	no
	<del>-</del>	
0x0c13 0x0c14	VMPatchResLimit	no
	MapScale	no
0x0c1c	Klut	no
0x0c1d	RimNonlinearity	no
0x0c1e	InverseRimNonlinearity	no
0x0c1f	RembrandtToneScale	no
0x0c20	RimToNifColorTransform	no
0x0c21	RimToNifScaleFactor	no
0x0c22	NifNonlinearity	no
0x0c23	SBALogTransform	no
0x0c24	InverseSBALogTransform	no
0x0c25	SBABlack	int16u
0x0c26	SBAGray	int16u
0x0c27	SBAWhite	int16u
0x0c28	GaussianWeights	no
0x0c29	SfsBoundary	no
0x0c2a	CoringTableBest	no
0x0c2b	CoringTableBetter	no
0x0c2c	CoringTableGood	no
0x0c2d	ExposureReferenceGain	no
0x0c2c		
0x0c2e 0x0c2f	ExposureReferenceOffset SBARedBalanceLut	no
		no
0x0c30	SBAGreenBalanceLut	no
0x0c31	SBABlueBalanceLut	no
0x0c32	SBANeutralBAL	int32s
0x0c33	SBAGreenMagentaBAL	int32s
0x0c34	SBAIlluminantBAL	int32s
0x0c35	SBAAnalysisComplete	int8u
0x0c36	JPEGQTableBest	no
0x0c37	JPEGQTableBetter	no
0x0c38	JPEGQTableGood	no

	ExifTool 13.24 Tag Names	-
0x0c39	RembrandtPortraitToneScale	no
0x0c3a	RembrandtConsumerToneScale	no
0x0c3b	CFAGreenThreshold1	no
0x0c3c	CFAGreenThreshold2	no
0x0c3d 0x0c3e	QTableLarge50Pct	no
0x0c3e 0x0c3f	QTableLarge67Pct QTableLarge100Pct	no no
0x0c31	QTableMedium50Pct	no
0x0c41	QTableMedium67Pct	no
0x0c42	QTableMedium100Pct	no
0x0c43	QTableSmall50Pct	no
0x0c44	QTableSmall67Pct	no
0x0c45 0x0c46	QTableSmall100Pct SBAHighGray	no int16u
0x0c40 0x0c47	SBALowGray	int16u
0x0c48	CaptureLook	int16u
0x0c49	SBAIllOffset	int16s
0x0c4a	SBAGmOffset	int16s
0x0c4b	NifNonlinearity12Bit	no
0x0c4c 0x0c4d	SharpeningOn NifNonlinearity16Bit	no
0x0c4a 0x0c4e	RawHistogram	no no
0x0c1c 0x0c4f	RawCFAComponentAverages	no
0x0c50	DisableFlagsPresent	no
0x0c51	DelayCols	no
0x0c52	DummyColsLeft	no
0x0c53	TrashColsRight	no
0x0c54 0x0c55	BlackColsRight DummyColsRight	no no
0x0c55	OverClockColsRight	no
0x0c57	UnusedBlackRowsTopOut	no
0x0c58	TrashRowsBottom	no
0x0c59	BlackRowsBottom	no
0x0c5a	OverClockRowsBottom	no
0x0c5b 0x0c5c	BlackColsLeft BlackRowsTop	no
0x0c5c	PartialActiveColsLeft	no no
0x0c5e	PartialActiveColsRight	no
0x0c5f	PartialActiveRowsTop	no
0x0c60	PartialActiveRowsBottom	no
0x0c61	ProcessBorderColsLeft	int16u
0x0c62 0x0c63	ProcessBorderColsRight ProcessBorderPoygTop	int16u int16u
0x0c63	ProcessBorderRowsTop ProcessBorderRowsBottom	int16u
0x0c65	ActiveCols	no
0x0c66	ActiveRows	no
0x0c67	FirstLines	no
0x0c68	UnusedBlackRowsTopIn	no
0x0c69	UnusedBlackRowsBottomIn UnusedBlackRowsBottomOut	no
0x0c6a 0x0c6b	UnusedBlackColsLeftOut	no no
0x0c6c	UnusedBlackColsLeftIn	no
0x0c6d	UnusedBlackColsRightIn	no
0x0c6e	UnusedBlackColsRightOut	no
0x0c6f	CFAOffsetRows	int32u
0x0c70	ShiftCols	int16s
0x0c71 0x0c76	CFAOffsetCols DarkMapScale	int32u no
0x0c70	HMapHandling	no
0x0c78	VMapHandling	no
0x0c79	DarkThreshold	no
0x0c7a	DMDitherMatrix	int16u
0x0c7b	DMDitherMatrixWidth	int16u
0x0c7c 0x0c7d	DMDitherMatrixHeight MaxPixelValueThreshold	int16u int16u
0x0c7a 0x0c7e	HoleFillDeltaThreshold	int16u
0x0c7f	DarkPedestal	int16u
0x0c80	${\tt ImageProcessingFileTagsVersionNumber}$	int16u
0x0c81	ImageProcessingFileDateCreated	string
0x0c82	DoublingMicrovolts	int32s

	ExifTool 13.24 Tag Names	
0x0c83	DarkFrameShortExposure	int32u
0x0c84	DarkFrameLongExposure	int32u
0x0c85	DarkFrameCountFactor	rational64u
0x0c88	HoleFillDarkDeltaThreshold	int16u
0x0c89 0x0c8a	FarkleWhiteThreshold ColumnResetOffsets	no no
0x0c8b	ColumnGainFactors	no
0x0c8c	Channel O LagKernel	no
0x0c8d	Channel1LagKernel	no
0x0c8e	Channel2LagKernel	no
0x0c8f	Channel 3LagKernel	no
0x0c90 0x0c91	BluegrassTable BluegrassScale1	no no
0x0c91	BluegrassScale2	no
0x0ce4	FinishedFileProcessingRequest	no
0x0ce5	FirmwareVersion	string
0x0ce6	HostSoftwareExportVersion	no
0x0ce7	HostSoftwareRendering	int32u
0x0dac 0x0dad	DCS3XXProcessingInfoIFD DCS3XXProcessingInfo	no no
0x0dad 0x0dae	IPAVersion	int32u
0x0db6	FinishIPAVersion	no
0x0db7	FinishIPFVersion	no
0x0db8	FinishFileType	int32u
0x0db9	FinishResolution	int32u
0x0dba 0x0dbb	FinishNoise FinishSharpening	int32u int32u
0x0dbc	FinishLook	int32u
0x0dbd	FinishExposure	int32u
0x0e0b	SigmaScalingFactorLowRes	rational64u
0x0e0c	SigmaScalingFactorCamera	rational64u
0x0e0d	SigmaImpulseParameters	int16u[n]
0x0e0e 0x0e0f	SigmaNoiseThreshTableV2 SigmaSizeTable	no int16u[n]
0x0e10	DacGainsCoarseAdjPreIF41	no
0x0e11	SigmaNoiseFilterCalTableV1	no
0x0e12	SigmaNoiseFilterTableV1	no
0x0e13	Lin12ToKlut8	no
0x0e14 0x0e15	SigmaNoiseFilterTableV1Version Lin12ToKlut12	no
0x0e15 0x0e16	Klut12ToLin12	no no
0x0e17	NifNonlinearity12To16	no
0x0e18	SBALog12Transform	no
0x0e19	InverseSBALog12Transform	no
0x0e1a 0x0e1b	ToneScale1	no
0x0elb 0x0elc	ToneScale1 ToneScale2	no no
0x0e1d	ToneScale3	no
0x0e1e	ToneScale4	no
0x0e1f	ToneScale5	no
0x0e20	ToneScale6	no
0x0e21 0x0e22	ToneScale7 ToneScale8	no no
0x0e23	ToneScale9	no
0x0e24	DayMat0	no
0x0e25	DayMat1	no
0x0e26	DayMat2	no
0x0e27	DayMat 4	no
0x0e28 0x0e29	DayMat4 DayMat5	no no
0x0e2a	DayMat6	no
0x0e2b	DayMat7	no
0x0e2c	DayMat8	no
0x0e2d	DayMat9	no
0x0e2e 0x0e2f	TungMat 1	no
0x0e21 0x0e30	TungMat1 TungMat2	no no
0x0e31	TungMat3	no
0x0e32	TungMat4	no
0x0e33	TungMat5	no

```
0x0e34
         TungMat6
                                                 no
0 \times 0 = 35
         TungMat7
                                                 no
0x0e36
         TungMat8
                                                 no
         TungMat9
0x0e37
                                                 no
0x0e38
        FluorMat0
                                                 no
0x0e39
        FluorMat1
                                                 no
0x0e3a
        FluorMat2
                                                 no
0x0e3b
        FluorMat3
                                                 no
0x0e3c FluorMat4
                                                 no
0x0e3d
       FluorMat5
                                                 no
       FluorMat6
0x0e3e
                                                 no
0x0e3f
        FluorMat7
                                                 no
0x0e40
        FluorMat8
                                                 no
0x0e41
         FluorMat9
                                                 no
0x0e42
         FlashMat0
                                                 no
0x0e43
         FlashMat1
                                                 no
0x0e44
         FlashMat2
                                                 no
0x0e45
         FlashMat3
                                                 no
0 \times 0 = 46
         FlashMat4
                                                 no
0x0e47
         FlashMat5
0x0e48
         FlashMat6
0x0e49
         FlashMat7
                                                 no
0x0e4a
         FlashMat8
                                                 no
0x0e4b
         FlashMat9
                                                 no
         KodakLook
0x0e4c
                                                 string
         IPFCameraModel
                                                 string
0x0e4d
         AH2GreenInterpolationThreshold
                                                 int16u
0 \times 0 = 4 =
                                                 int16u[3]
0x0e4f
         ResamplingKernelDenominators067
0x0e50
         ResamplingKernelDenominators050
                                                 int16u[3]
0x0e51
         ResamplingKernelDenominators100
                                                 int16u[3]
0x0e56
         LookMat0
0x0e57
         LookMat1
                                                 no
0x0e58
         LookMat2
                                                 no
0x0e59
        LookMat3
                                                 no
0x0e5a
        LookMat4
                                                 no
0x0e5b
        LookMat5
                                                 no
       LookMat6
0x0e5c
                                                 no
0x0e5d
         LookMat7
                                                 no
0x0e5e
         LookMat8
                                                 nο
0x0e5f
         LookMat9
                                                 no
0x0e60
         CFAInterpolationAlgorithm
                                                 int16u
0x0e61
         CFAInterpolationMetric
                                                 int16u
0x0e62
         CFAZipperFixThreshold
                                                 int16u
0x0e63
         NoiseReductionParametersKhufuRGB
                                                 int16u[9]
0x0e64
         NoiseReductionParametersKhufu6MP
                                                  int16u[9]
0x0e65
         NoiseReductionParametersKhufu3MP
                                                  int16u[9]
0x0e6a
         ChromaNoiseHighFThresh
                                                 int32u[2]
0 \times 0 = 6 b
         ChromaNoiseLowFThresh
                                                 int32u[2]
         ChromaNoiseEdgeMapThresh
                                                 int32u
0x0e6c
0 \times 0 = 6d
         ChromaNoiseColorSpace
                                                 int32u
0 \times 0 = 6 =
         EnableChromaNoiseReduction
                                                 int16u
0 \times 0 = 6f
         NoiseReductionParametersHostRGB
                                                 int16u[9]
0x0e70
         NoiseReductionParametersHost6MP
                                                 int16u[9]
0x0e71
         NoiseReductionParametersHost3MP
                                                 int16u[9]
0x0e72
         NoiseReductionParametersCamera
                                                 int16u[6]
0x0e73
         NoiseReductionParametersAtCapture
                                                 int16u[6]
0 \times 0 = 74
         LCDMatrix
                                                 rational64s[9]
0x0e75
        LCDMatrixChickFix
                                                 rational64s[9]
0x0e76
         LCDMatrixMarvin
                                                 rational64s[9]
0x0e7c
         LCDGammaTableChickFix
                                                 nο
0x0e7d
        LCDGammaTableMarvin
                                                 no
0x0e7e
         LCDGammaTable
                                                 no
0x0e7f
         LCDSharpeningF1
                                                 no
0x0e80
         LCDSharpeningF2
                                                 no
0 \times 0 = 81
         LCDSharpeningF3
                                                 no
         LCDSharpeningF4
0x0e82
                                                 no
0x0e83
         LCDEdgeMapX1
                                                 no
0x0e84
         LCDEdgeMapX2
                                                 no
0x0e85
         LCDEdgeMapX3
                                                 nο
0x0e86
         LCDEdgeMapX4
```

	ExilTool 13.24 Tag Names -	_
0x0e87	LCDEdgeMapSlope	no
0x0e88	YCrCbMatrix	no
0x0e89	LCDEdgeSpline	no
0x0e92	Fac18Per	int16u
0x0e93	Fac170Per	int16u
0x0e94	Fac100Per	int16u
0x0e9b	ExtraTickLocations	no
0x0e9c 0x0e9d	RGBtoeV0 RGBtoeV1	no no
0x0e9e	RGBtoeV2	no
0x0e9f	RGBtoeV3	no
0x0ea0	RGBtoeV4	no
0x0ea1	RGBtoeV5	no
0x0ea2	RGBtoeV6	no
0x0ea3	RGBtoeV7	no
0x0ea4	RGBtoeV8	no
0x0ea5	RGBtoeV9	no
0x0ea6	LCDHistLUT0	no
0x0ea7	LCDHistLUT1	no
0x0ea8	LCDHistLUT2	no
0x0ea9	LCDHistLUT3	no
0x0eaa 0x0eab	LCDHistLUT4 LCDHistLUT5	no
0x0eab	LCDHistLUT6	no no
0x0eac	LCDHistLUT7	no
0x0eae	LCDHistLUT8	no
0x0eaf	LCDHistLUT9	no
0x0eb0	LCDLinearClipValue	no
0x0ece	LCDStepYvalues	no
0x0ecf	LCDStepYvaluesChickFix	no
0x0ed0	LCDStepYvaluesMarvin	no
0x0ed8	InterpolationCoefficients	no
0x0ed9	InterpolationCoefficients6MP	no
0x0eda	InterpolationCoefficients3MP	no
0x0f00	NoiseReductionParametersHostNormal	no
0x0f01 0x0f02	NoiseReductionParametersHostStrong NoiseReductionParametersHostLow	no
0x0102 0x0f0a	MariahTextureThreshold	no int16u
0x0f0b	MariahMapLoThreshold	int16u
0x0f0c	MariahMapHiThreshold	int16u
0x0f0d	MariahChromaBlurSize	int16u
0x0f0e	MariahSigmaThreshold	int16u
0x0f0f	MariahThresholds	no
0x0f10	MariahThresholdsNormal	no
0x0f11	MariahThresholdsStrong	no
0x0f12	MariahThresholdsLow	no
0x0f14	KhufuLinearRedMixingCoefficient	no
0x0f15	KhufuLinearGreenMixingCoefficient	no
0x0f16	KhufuLinearBlueMixingCoefficient KhufuUSpaceC2MixingCoefficient	no
0x0f17 0x0f18	KhufuSiqmaGaussianWeights	no
0x0f18	KhufuSigmaScalingFactors6MP	no no
0x0f1a	KhufuSigmaScalingFactors3MP	no
0x0f1b	KhufuSigmaScalingFactors14MP	no
0x0f32	KhufuIOThresholds	no
0x0f33	KhufuI1Thresholds	no
0x0f34	KhufuI2Thresholds	no
0x0f35	KhufuI3Thresholds	no
0x0f36	KhufuI4Thresholds	no
0x0f37	KhufuI5Thresholds	no
0x0f3c	CondadoDayBVThresh	int16u
0x0f3d	CondadoNurage	int16u
0x0f3e 0x0f3f	CondadoBVFactor CondadoIllFactor	int16s int16s
0x0131 0x0f40	CondadoTunThresh	int16s
0x0140 0x0f41	CondadoFluThresh	int16s
0x0f42	CondadoDayOffsets	int16s[2]
0x0f43	CondadoTunOffsets	int16s[2]
0x0f44	CondadoFluOffsets	int16s[2]
0x0f5a	ERIMMToCRGB0Spline	no

0x0f5b	ERIMMToCRGB1Spline	no
0x0f5c	ERIMMToCRGB2Spline	no
0x0f5d	ERIMMToCRGB3Spline	no
0x0f5e	ERIMMToCRGB4Spline	no
0x0f5f	ERIMMToCRGB5Spline	no
0x0f60	ERIMMToCRGB6Spline	no
0x0f61	ERIMMToCRGB7Spline	no
0x0f62	ERIMMToCRGB8Spline	no
0x0f63	ERIMMToCRGB9Spline	
		no
0x0f64	CRGBToERIMM0Spline	no
0x0f65	CRGBToERIMM1Spline	no
0x0f66	CRGBToERIMM2Spline	no
0x0f67	CRGBToERIMM3Spline	no
0x0f68	CRGBToERIMM4Spline	no
0x0f69	CRGBToERIMM5Spline	
		no
0x0f6a	CRGBToERIMM6Spline	no
0x0f6b	CRGBToERIMM7Spline	no
0x0f6c	CRGBToERIMM8Spline	no
0x0f6d	CRGBToERIMM9Spline	no
0x0f6e	ERIMMNonLinearitySpline	no
0x0f6f	Delta12To8Spline	
		no
0x0f70	Delta8To12Spline	no
0x0f71	InverseMonitorMatrix	no
0x0f72	NifNonlinearityExt	no
0x0f73	InvNifNonLinearity	no
0x0f74	RIMM13ToERIMM12Spline	no
0x0f78	ToneScaleOSpline	no
0x0f79	ToneScale1Spline	no
0x0f7a	ToneScale2Spline	no
0x0f7b	ToneScale3Spline	no
0x0f7c	ToneScale4Spline	no
0x0f7d	ToneScale5Spline	no
0x0f7e		
	ToneScale6Spline	no
0x0f7f	ToneScale7Spline	no
0x0f80	ToneScale8Spline	no
0x0f81	ToneScale9Spline	no
0x0f82	ERIMMToneScaleOSpline	no
0x0f83	ERIMMToneScale1Spline	no
0x0f84	ERIMMToneScale2Spline	
		no
0x0f85	ERIMMToneScale3Spline	no
0x0f86	ERIMMToneScale4Spline	no
0x0f87	ERIMMToneScale5Spline	no
0x0f88	ERIMMToneScale6Spline	no
0x0f89	ERIMMToneScale7Spline	no
0x0f8a	ERIMMToneScale8Spline	
	<del>-</del>	no
0x0f8b	ERIMMToneScale9Spline	no
0x0f8c	RIMMToCRGB0Spline	no
0x0f8d	RIMMToCRGB1Spline	no
0x0f8e	RIMMToCRGB2Spline	no
0x0f8f	RIMMToCRGB3Spline	no
0x0f90	RIMMToCRGB4Spline	no
0x0f91	RIMMToCRGB5Spline	no
0x0f92	RIMMToCRGB6Spline	no
0x0f93	RIMMToCRGB7Spline	no
0x0f94	RIMMToCRGB8Spline	no
0x0f95	RIMMToCRGB9Spline	no
0x0fa0	QTableLarge25Pct	no
0x0fa0		
	QTableMedium25Pct	no
0x0fa2	QTableSmall25Pct	no
0x1130	NoiseReductionKernel	no
0x1388	UserMetaData	no
0x1389	InputProfile	undef
0x138a	KodakLookProfile	undef
		undef
0x138b	OutputProfile	
0x1390	SourceProfilePrefix	string
0x1391	ToneCurveProfileName	string
0x1392	InputProfile	ICC_Profile
0x1393	ProcessParametersV2	no
0x1394	ReservedBlob2	no
0x1394 0x1395	ReservedBlob3	
OAIJJJ	VCBCT ACMDIONO	no

	ExilTool 13.24 Tag Names	
0x1396	ReservedBlob4	no
0x1397	ReservedBlob5	no
0x1398	ReservedBlob6	no
0x1399	ReservedBlob7	no
0x139a	ReservedBlob8	no
0x139b	ReservedBlob9	no
$0 \times 1770$	ScriptVersion	int32u
0x177a	ImagerTimingData	no
0x1784	ISO	int32u
0x17a2	Scav11Cols	no
0x17a3	Scav12Cols	no
0x17a4	Scav21Cols	no
0x17a5	Scav22Cols	no
0x17a6	ActiveCTEMonitor1Cols	no
0x17a7	ActiveCTEMonitor2Cols	no
0x17a8	ActiveCTEMonitorRows	no
0x17a9	ActiveBuf1Cols	no
0x17aa	ActiveBuf2Cols	no
0x17ab	ActiveBuf1Rows	no
0x17ac	ActiveBuf2Rows	no
0x17c0	HRNoiseLines	no
0x17c1	RNoiseLines	no
0x17c2	ANoiseLines	no
0x17d4	ImagerCols	int16u
0x17de	ImagerRows	int16u
0x17e8	PartialActiveCols1	int32u
0x17f2	PartialActiveCols2	int32u
0x17fc	PartialActiveRows1	int32u
0x1806	PartialActiveRows2	int32u
0x1810	ElectricalBlackColumns	int32u
0x181a	ResetBlackSegRows	int32u
0x1838	CaptureWidthNormal	int32u
0x1839	CaptureHeightNormal	int32u
0x183a	CaptureWidthResetBlackSegNormal	no
0x183b	CaptureHeightResetBlackSegNormal	no
0x183c	DarkRefOffsetNormal	no
0x1842	CaptureWidthTest	int32u
0x1843	CaptureHeightTest	no
0x1844	CaptureWidthResetBlackSegTest	no
0x1845 0x1846	CaptureHeightResetBlackSegTest	no
	DarkRefOffsetTest	no int32u
0x184c 0x184d	ImageSegmentStartLine	int32u
0x184a 0x184e	ImageSegmentLines	
0x184e 0x1860	SkipLineTime FastResetLineTime	int32u int32u
0x186a	NormalLineTime	int32u
0x180a 0x1874	MinIntegrationRows	int32u
0x1874 0x187e	PreReadFastResetCount	int32u
0x187e	TransferTimeNormal	int32u
0x1889	TransferTimeTest	int32u
0x188a	QuietTime	int32u
0x189c	OverClockCols	int16u
0x18a6	H2ResetBlackPixels	int32u
0x18b0	H3ResetBlackPixels	int32u
0x18ba	BlackAcquireRows	int32u
0x18c4	OverClockRows	int16u
0x18ce	H3ResetBlackColumns	int32u
0x18d8	DarkBlackSegRows	int32u
0x1900	CrossbarEnable	no
0x1901	FifoenOnePixelDelay	int32u
0x1902	ReadoutTypeRequested	int32u
0x1903	ReadoutTypeActual	int32u
0x190a	OffsetDacValue	int32u
0x1914	TempAmpGainX100	int32u
0x191e	VarrayDacNominalValues	int32u[3]
0x1928	VddimDacNominalValues	no
0x1964	C14Configuration	int32u
0x196e	TDA10ffset	int32u[3]
0x196f	TDA1Bandwidth	int32u
0x1970	TDAlGain	int32u[3]

0x1971	TDA1EdgePolarity	int32u
0x1978	TDA2Offset	int32u[3]
0x1979	TDA2Bandwidth	int32u
0x197a	TDA2Gain	int32u[3]
0x197b	TDA2EdgePolarity	int32u
0x1982	TDA3Offset	int32u[3]
0x1983	TDA3Bandwidth	int32u
0x1984	TDA3Gain	int32u[3]
0x1985	TDA3EdgePolarity	int32u
0x198c	TDA4Offset	int32u[3]
0x198d	TDA4Bandwidth	int32u
0x198e	TDA4Gain	int32u[3]
0x198f	TDA4EdgePolarity	int32u
0xfde8	ComLenBlkSize	int16u

### Kodak TextualInfo Tags

Below is a list of tags which have been observed in the Kodak TextualInfo data, however ExifTool will extract information from any tags found here.

Tag ID	Tag Name	Writable
'AF Function'	AFMode	no
'Actual Compensation'		no
'Aperture'	Aperture	no
'Auto Bracket'	AutoBracket	no
'Brightness Value'	BrightnessValue	no
'Camera'	CameraModel	no
'Camera body'	CameraBody	no
'Compensation'	ExposureCompensation	no
'Date'	Date	no
'Exposure Bias'	ExposureBias	no
'Exposure Mode'	ExposureMode	no
'Firmware Version'	FirmwareVersion	no
'Flash Compensation'	FlashExposureComp	no
'Flash Fired'	FlashFired	no
'Flash Sync Mode'	FlashSyncMode	no
'Focal Length'	FocalLength	no
'Height'	KodakImageHeight	no
'ISO'	ISO	no
'ISO Speed'	ISO	no
'Image Number'	ImageNumber	no
'Lens'	Lens	no
'Max Aperture'	MaxAperture	no
'Meter Mode'	MeterMode	no
'Min Aperture'	MinAperture	no
'Popup Flash'	PopupFlash	no
'Serial Number'	SerialNumber	no
'Shooting Mode'	ShootingMode	no
'Shutter'	ShutterSpeed	no
'Temperature'	Temperature	no
'Time'	Time	no
'White balance'	WhiteBalance	no
'Width'	KodakImageWidth	no
'_other_info'	OtherInfo	no

#### Kodak Processing Tags

Index2	Tag Name	Writable
20	WB_RGBLevels	no

# Kodak Type2 Tags

These tags are used by the Kodak DC220, DC260, DC265 and DC290, Hewlett-Packard PhotoSmart 618, C500 and C912, Pentax EI-200 and EI-2000, and Minolta EX1500Z.

8	KodakMaker	string[32]
40	KodakModel	string[32]
108	KodakImageWidth	int32u
112	KodakImageHeight	int32u

#### Kodak Type3 Tags

These tags are used by the DC240, DC280, DC3400 and DC5000.

Index1	Tag Name	Writable
12	YearCreated	int16u
14	MonthDayCreated	int8u[2]
16	TimeCreated	int8u[4]
30	OpticalZoom	int16u
55	Sharpness	int8s
56	ExposureTime	int32u
60	FNumber	int16u
78	ISO	int16u

#### Kodak Type4 Tags

These tags are used by the DC200 and DC215.

Index1	Tag Name	Writable
32	OriginalFileName	string[12]

#### Kodak Type5 Tags

These tags are used by the CX4200, CX4210, CX4230, CX4300, CX4310, CX6200 and CX6230.

Index1	Tag Name	Writable
20	ExposureTime	int32u
26	WhiteBalance	int8u
28	FNumber	int16u
30	ISO	int16u
32	OpticalZoom	int16u
34	DigitalZoom	int16u
39	FlashMode	int8u
42	ImageRotated	int8u
43	Macro	int8u

#### Kodak Type6 Tags

These tags are used by the DX3215 and DX3700.

Index1	Tag Name	Writable
16	ExposureTime	int32u
20	ISOSetting?	int32u
24	FNumber	int16u
26	ISO	int16u
28	OpticalZoom	int16u
30	DigitalZoom	int16u
34	Flash	int16u

#### Kodak Type7 Tags

The maker notes of models such as the C340, C433, CC533, LS755, V803 and V1003 seem to start with the camera serial number. The C310, C315, C330, C643, C743, CD33, CD43, CX7220 and CX7300 maker notes are also decoded using this table, although the strings for these cameras don't conform to the usual Kodak serial number format, and instead have the model name followed by 8 digits.

Index1 Tag Name

0 SerialNumber string[16]

#### Kodak Type8 Tags

Kodak models such as the ZD710, P712, P850, P880, V1233, V1253, V1275, V1285, Z612, Z712, Z812, Z885 use standard TIFF IFD format for the maker notes. In keeping with Kodak's strategy of inconsistent makernotes, models such as the M380, M1033, M1093, V1073, V1273, Z1012, Z1085 and Z8612 also use these tags, but these makernotes begin with a TIFF header instead of an IFD entry count and use relative instead of absolute offsets. There is a large amount of information stored in these maker notes (apparently with much duplication), but relatively few tags have so far been decoded.

Tag ID	Tag Name	Writable
0xfc00	SubIFD0	Kodak SubIFD0
0xfc01	SubIFD1	Kodak SubIFD0 Kodak SubIFD1
0xfc02	SubIFD2	Kodak SubIFD1 Kodak SubIFD2
	<del></del>	Kodak SubIFD2
0xfc03	SubIFD3	Kodak SubIFD3 Kodak SubIFD3
0xfc04	SubIFD4	Kodak SubIFD4 Kodak SubIFD4
0xfc05	SubIFD5	Kodak SubIFD5
0xfc06	SubIFD6	Kodak SubIFD5 Kodak SubIFD6
0xfcff	SubIFD255	Kodak SubIFD6 Kodak SubIFD0
0xff00	CameraInfo	Kodak CameraInfo

#### Kodak SubIFD0 Tags

SubIFD0 through SubIFD5 tags are written a number of newer Kodak models.

Tag ID	Tag Name	Writable
0xfa02	SceneMode	int16u
0xfa19	SerialNumber	string
0xfa1d	KodakImageWidth	int16u
0xfa1e	KodakImageHeight	int16u
0xfa20	SensorWidth	int16u
0xfa21	SensorHeight	int16u
0xfa23	FNumber	int16u
0xfa24	ExposureTime	int32u
0xfa2e	ISO	int16u
0xfa3d	OpticalZoom	int16u
0xfa46	ISO	int16u
0xfa51	KodakImageWidth	int16u
0xfa52	KodakImageHeight	int16u
0xfa54	ThumbnailWidth	int16u
0xfa55	ThumbnailHeight	int16u
0xfa57	PreviewImageWidth	int16u
0xfa58	PreviewImageHeight	int16u

#### Kodak SubIFD1 Tags

Tag ID	Tag Name	Writable
0x0027	ISO	int16u
0x0028	ISO	int16u

### Kodak SubIFD2 Tags

Tag ID	Tag Name	Writable

0x6002	SceneModeUsed	int32u
0x6006	OpticalZoom	int32u
0x6103	MaxAperture	int32u
0xf002	SceneModeUsed	int32u
0xf006	OpticalZoom	int32u
0xf103	FNumber	int32u
0xf104	ExposureTime	int32u
0xf105	ISO	int32u

#### Kodak SubIFD3 Tags

Tag ID	Tag Name	Writable
0x1000	OpticalZoom	int16u

### <u>Kodak</u> <u>SubIFD4</u> <u>Tags</u>

Tag ID	Tag Name	Writable
[no tags	known]	

#### Kodak SubIFD5 Tags

Tag ID	Tag Name	Writable
0x000f	OpticalZoom	int16u

# Kodak SubIFD6 Tags

SubIFD6 is written by the M580.

Tag ID	Tag Name	Writable
[no tags	known]	

#### Kodak CameraInfo Tags

These tags are used by the P712, P850 and P880.

Tag ID	Tag Name	Writable
0xf900 0xf901 0xf902 0xf903 0xf904 0xf907 0xf908 0xfa00 0xfa04 0xfd05	SensorWidth SensorHeight BayerPattern SensorFullWidth SensorFullHeight KodakImageWidth KodakImageHeight KodakInfoType SerialNumber FNumber ExposureTime	int16u int16u string int16u int16u int16u int16u string string int16u int32u
0xfd06	ISO	int16u

### Kodak Type9 Tags

These tags are used by the Kodak C140, C180, C913, C1013, M320, M340 and M550, as well as various cameras marketed by other manufacturers.

Index1	Tag Name	Writable
12	FNumber	int16u
16	ExposureTime	int32u
20	DateTimeOriginal	string[20]
52	ISO	int16u
87	FirmwareVersion	string[16]
168	UnknownNumber	no
196	UnknownNumber	no

### Kodak Type10 Tags

Another variation of the IFD-format type, this time with just a byte order indicator instead of a full TIFF header. These tags are used by the  ${\tt Z980}$ .

Tag ID	Tag Name	Writable
0x0002	PreviewImageSize	int16u[2]
$0 \times 0012$	ExposureTime	int32u
0x0013	FNumber	int16u
$0 \times 0014$	ISO	int16u
0x001d	FocalLength	int32u

#### Kodak Typell Tags

These tags are found in models such as the PixPro S-1. They are not writable because the inconsistency of Kodak maker notes is beginning to get on my nerves.

Tag ID	Tag Name	Writable
$0 \times 0104$	FirmwareVersion	no
$0 \times 0203$	PictureEffect	no
$0 \times 0207$	KodakModel	no
0x0300	KodakMake	no
0x0308	LensSerialNumber	no
0x0309	LensModel	no
0x030d	LevelMeter?	no
0x0311	Pitch	no
0x0312	Yaw	no
0x0313	Roll	no
$0 \times 0314$	CX?	no
0x0315	CY?	no
0x0316	Rads?	no

#### Kodak Unknown Tags

Index1	Tag Name	Writable
[no tags	known]	

#### <u>Kodak</u> <u>Meta</u> <u>Tags</u>

These tags are found in the APP3 "Meta" segment of JPEG images from Kodak cameras such as the DC280, DC3400, DC5000, MC3, M580, Z950 and Z981. The structure of this segment is similar to the APP1 "Exif" segment, but a different set of tags is used.

0xc350 FilmProductCode no	
0xc351 ImageSourceEK no	
0xc352 CaptureConditionsPAR no	
0xc353 CameraOwner und	def
0xc354 SerialNumber und	def
0xc355 UserSelectGroupTitle no	
0xc356 DealerIDNumber no	
0xc357 CaptureDeviceFID no	
0xc358 EnvelopeNumber no	
0xc359 FrameNumber no	
0xc35a FilmCategory no	
0xc35b FilmGencode no	
0xc35c ModelAndVersion no	
0xc35d FilmSize no	
0xc35e SBA_RGBShifts no	
0xc35f SBAInputImageColorspace no	
0xc360 SBAInputImageBitDepth no	
0xc361 SBAExposureRecord no	
0xc362 UserAdjSBA_RGBShifts no	
0xc363 ImageRotationStatus no	

0xc364	RollGuidElements	no
0xc365	MetadataNumber	no
0xc366	EditTagArray	no
0xc367	Magnification	no
0xc36c	NativeXResolution	no
0xc36d	NativeYResolution	no
0xc36e	KodakEffectsIFD	Kodak SpecialEffects
0xc36f	KodakBordersIFD	Kodak Borders
0xc37a	NativeResolutionUnit	no
0xc418	SourceImageDirectory	no
0xc419	SourceImageFileName	no
0xc41a	SourceImageVolumeName	no
0xc46c	PrintQuality	no
0xc46e	ImagePrintStatus	no

#### Kodak SpecialEffects Tags

The Kodak SpecialEffects and Borders tags are found in sub-IFD's within the Kodak JPEG APP3 "Meta" segment.

Tag ID	Tag Name	Writable
0x0000	DigitalEffectsVersion	no
0x0001	DigitalEffectsName	no
0x0002	DigitalEffectsType	no

### <u>Kodak</u> <u>Borders</u> <u>Tags</u>

Tag ID	Tag Name	Writable
$0 \times 0 0 0 0$	BordersVersion	no
$0 \times 0001$	BorderName	no
$0 \times 0002$	BorderID	no
0x0003	BorderLocation	no
$0 \times 0 0 0 4$	BorderType	no
0x0008	WatermarkType	no

### Kodak KDC IFD Tags

These tags are found in a separate IFD of KDC images from some newer Kodak models such as the P880 and Z1015IS.

Tag ID	Tag Name	Writable
0xfa00	SerialNumber	string
0xfa0d	WhiteBalance	int8u
0xfa25	WB_RGBLevelsAuto	no
0xfa27	WB_RGBLevelsTungsten	no
0xfa28	WB_RGBLevelsFluorescent	no
0xfa29	WB_RGBLevelsDaylight	no
0xfa2a	WB_RGBLevelsShade	no

### Kodak frea Tags

Information stored in the "frea" atom of Kodak PixPro SP360 MP4 videos.

Tag Name	Writable
PreviewImage	no
ThumbnailImage	no
Duration	no
KodakVersion	no
	PreviewImage ThumbnailImage Duration

# Kodak Free Tags

Information stored in the "free" atom of Kodak MP4 videos. (VERY bad form for Kodak to store useful information in an atom intended for unused space!)

'AprV'	ApertureValue	no
'BrtV'	BrightnessValue	no
'Expc'	ExposureCompensation	no
'Expo'	ExposureTime	no
'FL35'	FocalLengthIn35mmFormat	no
'FNum'	FNumber	no
'FoLn'	FocalLength	no
'ISOS'	ISO	no
'SVer'	FirmwareVersion	no
'Scrn'	PreviewInfo	Kodak Scrn
'Seri'	SerialNumber	no
'StSV'	ShutterSpeedValue	no

### Kodak Scrn Tags

Tag Name	Writable
PreviewImageWidth	no
PreviewImageHeight	no
PreviewImageLength	no
PreviewImage	no
	PreviewImageWidth PreviewImageHeight PreviewImageLength

#### Kodak DcMD Tags

Metadata directory found in MOV and MP4 videos from some Kodak cameras.

Tag ID	Tag Name	Writable
'CMbo' 'Cmbo' 'DcEM' 'DcME'	CameraByteOrder CameraByteOrder DcEM DcME	no no Kodak DcEM Kodak DcME
Kodak DcEM	Tags	
Tag ID  [no tags	Tag Nameknown]	Writable
Kodak DcME	Tags	
Tag ID	Tag Name	Writable

# Kodak MOV Tags

[no tags known]

This information is found in the TAGS atom of MOV videos from Kodak models such as the P880.

Index1	Tag Name	Writable
0	Make	no
22	Model	no
64	ModelType	no
78	ExposureTime	no
82	FNumber	no
90	ExposureCompensation	no
112	FocalLength	no

#### Kodak pose Tags

Streamed orientation information from the PixPro 4KVR360, extracted as sub-documents when the Duplicates option is used.

Tag ID	Tag Name	Writable
'Accelerometer'	Accelerometer	no
'AngularVelocity'	AngularVelocity	no

### Leaf Tags

These tags are found in .MOS images from Leaf digital camera backs as written by Creo Leaf Capture. They exist within the Leaf-specific directory structure of EXIF tag 0x8606. The tables below list observed Leaf tags, however ExifTool will extract any tags found in the Leaf directories even if they don't appear in these tables.

Tag ID	Tag Name	Writable
'JPEG_preview_data'	PreviewImage	no
'JPEG_preview_info'	PreviewInfo	no
'PDA_histogram_data'	PDAHistogram	no
'back_serial_number'	BackSerial	no
'camera_profile'	CameraProfile	Leaf CameraProfile
'icc_camera_profile'	ICC_Profile	ICC_Profile
'icc_camera_to_tone_matrix'	ToneMatrix	no
'icc_camera_to_tone_space_flow'	ToneSpaceFlow	no
'icc_rgb_ws_profile'	RGB_Profile	ICC_Profile
'image_offset'	ImageOffset	no
'pattern_ratation_angle'	PatternAngle	no

#### <u>Leaf</u> <u>CameraProfile</u> <u>Tags</u>

All Tag ID's in the following table have a leading 'CamProf\_' which has been removed.

Tag ID	Tag Name	Writable
'back_type'	CameraBackType	no
'capture_profile'	CaptureProfile	Leaf CaptureProfile
'image_profile'	ImageProfile	Leaf ImageProfile
'name'	CameraName	no
'type'	CameraType	no
'version'	CameraProfileVersion	no

#### <u>Leaf</u> <u>CaptureProfile</u> <u>Tags</u>

All Tag ID's in the following table have a leading 'CaptProf\_' which has been removed.

Tag ID	Tag Name	Writable
'CCD_rect'	CCDRect	no
'CCD_valid_rect'	CCDValidRect	no
'CCD_video_rect'	CCDVideoRect	no
'back_type'	CaptProfBackType	no
<pre>'center_dark_rect'</pre>	CenterDarkRect	no
'color_averages'	ColorAverages	no
'color_matrix'	ColorMatrix	no
'dark_correction_type'	DarkCorrectionType	no
'image_bounds'	ImageBounds	no
'image_fields'	ImageFields	no
'image_offset'	ImageOffset	no
'left_dark_rect'	LeftDarkRect	no
'luminance_consts'	LuminanceConsts	no
'mosaic_pattern'	MosaicPattern	no
'name'	CaptProfName	no
'number_of_planes'	NumberOfPlanes	no
'raw_data_rotation'	RawDataRotation	no
'reconstruction_type'	ReconstructionType	no
'right_dark_rect'	RightDarkRect	no
'serial_number'	CaptureSerial	no
'type'	CaptProfType	no
'version'	CaptProfVersion	no
'xy_offset_info'	XYOffsetInfo	no

#### <u>Leaf ImageProfile Tags</u>

All Tag ID's in the following table have a leading 'ImgProf\_' which has

been removed.

Tag ID	Tag Name	Writable
'back_type'	ImgProfBackType	no
'image_status'	ImageStatus	no
'name'	ImgProfName	no
'rotation_angle'	RotationAngle	no
'shoot_setup'	ShootSetup	Leaf ShootSetup
'type'	ImgProfType	no
'version'	ImgProfVersion	no

#### <u>Leaf ShootSetup Tags</u>

All Tag ID's in the following table have a leading 'ShootObj\_' which has been removed.

Tag ID	Tag Name	Writable
'back_type'	ShootObjBackType	no
'camera_setup'	CameraSetup	Leaf CameraSetup
'capture_setup'	CaptureSetup	Leaf CaptureSetup
'color_setup'	ColorSetup	Leaf ColorSetup
'look_header'	LookHeader	Leaf LookHeader
'name'	ShootObjName	no
'save_setup'	SaveSetup	Leaf SaveSetup
'type'	ShootObjType	no
'version'	ShootObjVersion	no

### <u>Leaf CameraSetup Tags</u>

All Tag ID's in the following table have a leading 'CameraObj\_' which has been removed.

Tag ID	Tag Name	Writable
'ISO_speed'	ISOSpeed	no
'back_type'	CameraObjBackType	no
'camera_type'	CameraType	no
'lens_ID'	LensID	no
'lens_type'	LensType	no
'name'	CameraObjName	no
'strobe'	Strobe	no
'type'	CameraObjType	no
'version'	CameraObjVersion	no

#### <u>Leaf CaptureSetup Tags</u>

All Tag ID's in the following table have a leading 'CaptureObj\_' which has been removed.

Tag ID	Tag Name	Writable
'Multi_quality'	MultiQuality	no
'back_type'	CaptureObjBackType	no
'name'	CaptureObjName	no
'neutals'	Neutals	Leaf Neutrals
'selection'	Selection	Leaf Selection
'sharpness'	Sharpness	Leaf Sharpness
'single_quality'	SingleQuality	no
'tone_curve'	ToneCurve	Leaf ToneCurve
'type'	CaptureObjType	no
'version'	CaptureObjVersion	no

### <u>Leaf Neutrals Tags</u>

All Tag ID's in the following table have a leading 'NeutObj\_' which has been removed.

Tag ID Tag Name Writable

'back_type'	NeutObjBackType	no
'color_casts'	ColorCasts	no
'highlight_end_points'	${ t HighlightEndPoints}$	no
'name'	NeutObjName	no
'neutrals'	Neutrals	no
'shadow_end_points'	ShadowEndPoints	no
'type'	NeutObjType	no
'version'	NeutObjVersion	no

#### Leaf Selection Tags

All Tag ID's in the following table have a leading 'SelObj\_' which has been removed.

Tag ID	Tag Name	Writable
'back_type'	Sel0bjBackType	no
'locks'	Locks	no
'name'	SelObjName	no
'orientation'	Orientation	no
'rect'	Rect	no
'resolution'	Resolution	no
'scale'	Scale	no
'type'	SelObjType	no
'version'	SelObjVersion	no

### <u>Leaf Sharpness Tags</u>

All Tag ID's in the following table have a leading 'SharpObj\_' which has been removed.

Tag ID	Tag Name	Writable
'back_type'	SharpObjBackType	no
'data_len'	DataLen	no
'name'	SharpObjName	no
'sharp_info'	SharpInfo	no
'sharp_method'	SharpMethod	no
'type'	SharpObjType	no
'version'	SharpObjVersion	no

#### <u>Leaf ToneCurve Tags</u>

All Tag ID's in the following table have a leading 'ToneObj\_' which has been removed.

Tag ID	Tag Name	Writable
'back_type'	ToneObjBackType	no
'gamma'	Gamma	no
'name'	ToneObjName	no
'npts'	Npts	no
'tones'	Tones	no
'type'	ToneObjType	no
'version'	ToneObjVersion	no

### <u>Leaf ColorSetup Tags</u>

All Tag ID's in the following table have a leading 'ColorObj\_' which has been removed.

Tag ID	Tag Name	Writable
'back_type'	ColorObjBackType	no
'color_mode'	ColorMode	no
'color_type'	ColorType	no
'has_ICC'	HasICC	no
'input_profile'	InputProfile	no
'name'	ColorObjName	no

'output_profile'	OutputProfile	no
'type'	ColorObjType	no
'version'	ColorObjVersion	no

### <u>Leaf LookHeader Tags</u>

All Tag ID's in the following table have a leading 'LookHead\_' which has been removed.

Tag ID	Tag Name	Writable
'back_type'	LookHeadBackType	no
'name'	LookHeadName	no
'type'	LookHeadType	no
'version'	LookHeadVersion	no

#### Leaf SaveSetup Tags

All Tag ID's in the following table have a leading 'SaveObj\_' which has been removed.

Tag ID	Tag Name	Writable
'back_type'	SaveObjBackType	no
'leaf_auto_active'	LeafAutoActive	no
'leaf_auto_base_name'	LeafAutoBaseName	no
'leaf_hot_folder'	LeafHotFolder	no
'leaf_open_proc_HDR'	LeafOpenProcHDR	no
'leaf_output_file_type'	LeafOutputFileType	no
'leaf_save_selection'	LeafSaveSelection	no
'name'	SaveObjName	no
'std_auto_active'	StdAutoActive	no
'std_base_name'	StdBaseName	no
'std_hot_folder'	StdHotFolder	no
'std_open_in_photoshop'	StdOpenInPhotoshop	no
'std_output_bit_depth'	StdOutputBitDepth	no
'std_output_color_mode'	StdOutputColorMode	no
'std_output_file_type'	StdOutputFileType	no
'std_oxygen'	Std0xygen	no
'std_save_selection'	StdSaveSelection	no
'std_scaled_output'	StdScaledOutput	no
'std_sharpen_output'	StdSharpenOutput	no
'type'	SaveObjType	no
'version'	SaveObjVersion	no

### <u>Leaf SubIFD Tags</u>

Leaf writes a TIFF-format sub-IFD inside IFD0 of a MOS image. No tags in this sub-IFD are currently known, except for tags 0x8602 and 0x8606 which really shouldn't be here anyway (so they don't appear in the table below) because they duplicate references to the same data from tags with the same ID in IFD0.

Tag ID	Tag Name	Writable
Ino tags	known l	

#### Lytro Tags

Tag definitions for Lytro Light Field Picture (LFP) files. ExifTool extracts the full JSON metadata blocks, as well as breaking them down into individual tags. All available tags are extracted from the JSON metadata, even if they don't appear in the table below.

Tag Name	Writable
AccelerometerTime	no
AccelerometerX	no
AccelerometerY	no
AccelerometerZ	no
CameraType	no

DateTimeOriginal	no
EmbeddedImage	no
ExposureTime	no
FNumber	no
FirmwareVersion	no
FocalLength	no
FocalPlaneXResolution	no
FrameExposureTime	no
ISO	no
ImageLimitExposureBias	no
ImageModulationExposureBias	no
JSONMetadata	no-
LensTemperature	no
Make	no
Model	no
Orientation	no
SensorSerialNumber	no
SerialNumber	no
SocTemperature	no

#### Minolta Tags

These tags are used by Minolta, Konica/Minolta as well as some Sony cameras. Minolta doesn't make things easy for decoders because the meaning of some tags and the location where some information is stored is different for different camera models. (Take MinoltaQuality for example, which may be located in 5 different places.)

Tag ID	Tag Name	Writable
$0 \times 0000$	MakerNoteVersion	undef[4]
$0 \times 0001$	MinoltaCameraSettingsOld	Minolta CameraSettings
$0 \times 0003$	MinoltaCameraSettings	Minolta CameraSettings
$0 \times 0004$	MinoltaCameraSettings7D	Minolta CameraSettings7D
$0 \times 0010$	CameraInfoA100	Minolta CameraInfoA100
0x0018	ISInfoA100	Minolta ISInfoA100
0 0000	ImageStabilization	no
$0 \times 0020$	WBInfoA100	Minolta WBInfoA100
$0 \times 0040$	CompressedImageSize	int32u
0x0081	PreviewImage	undef
0x0088	PreviewImageStart	int32u*
0x0089	PreviewImageLength	int32u*
0x0100	SceneMode	int32u
0x0101	ColorMode	int32u
0x0102	MinoltaQuality	int32u
$0 \times 0103$	MinoltaQuality	int32u
	MinoltaImageSize	int32u
$0 \times 0104$	FlashExposureComp	rational64s
$0 \times 0105$	Teleconverter	int32u
$0 \times 0107$	ImageStabilization	int32u
$0 \times 0109$	RawAndJpgRecording	int32u
0x010a	ZoneMatching	int32u
0x010b	ColorTemperature	int32u
0x010c	LensType	int32u
$0 \times 0111$	ColorCompensationFilter	int32s
$0 \times 0112$	WhiteBalanceFineTune	int32u
$0 \times 0113$	ImageStabilization	int32u
$0 \times 0114$	MinoltaCameraSettings5D	Minolta CameraSettings5D
	CameraSettingsA100	Minolta CameraSettingsA100
$0 \times 0115$	WhiteBalance	int32u
0x0e00	PrintIM	PrintIM
0x0f00	MinoltaCameraSettings2	no

#### Minolta CameraSettings Tags

There is some variability in CameraSettings information between different models (and sometimes even between different firmware versions), so this information may not be as reliable as it should be. Because of this, tags in the following tables are set to lower priority to prevent them from superseding the values of same-named tags in other locations when duplicate tags are disabled.

Index4	Tag Name	Writable
1	ExposureMode	int32u
2	FlashMode	int32u
3	WhiteBalance	int32u~
4	MinoltaImageSize	int32u
5	MinoltaQuality	int32u
6	DriveMode	int32u
7	MeteringMode	int32u
8	ISO	int32u
9	ExposureTime	int32u
10	FNumber	int32u
11	MacroMode	int32u
12	DigitalZoom	int32u
13	ExposureCompensation	int32u
14	BracketStep	int32u
16	IntervalLength	int32u
17	IntervalNumber	int32u
18	FocalLength	int32u
19	FocusDistance	int32u
20	FlashFired	int32u
21	MinoltaDate	int32u
22	MinoltaTime	int32u
23	MaxAperture	int32u
26	FileNumberMemory	int32u
27	LastFileNumber	int32u
28	ColorBalanceRed	int32u
29	ColorBalanceGreen	int32u
30	ColorBalanceBlue	int32u
31	Saturation	int32u
32	Contrast	int32u
33	Sharpness	int32u
34	SubjectProgram	int32u
35	FlashExposureComp	int32u
36	ISOSetting	int32u
37	MinoltaModelID	int32u
38	IntervalMode	int32u
39	FolderName	int32u
40	ColorMode	int32u
41	ColorFilter	int32u
42	BWFilter	int32u
43	InternalFlash	int32u
44	Brightness	int32u
45	SpotFocusPointX	int32u
46	SpotFocusPointY	int32u
47	WideFocusZone	int32u
48	FocusMode	int32u
49	FocusArea	int32u
50	DECPosition	int32u
51	ColorProfile	int32u
52	DataImprint	int32u
63	FlashMetering	int32u

# Minolta CameraSettings7D Tags

Index2	Tag Name	Writable
0	ExposureMode	int16u
2	MinoltaImageSize	int16u
3	MinoltaQuality	int16u
4	WhiteBalance	int16u
14	FocusMode	int16u
16	AFPoints	int16u
21	Flash	int16u
22	FlashMode	int16u
28	ISOSetting	int16u
30	ExposureCompensation	int16s
37	ColorSpace	int16u
38	Sharpness	int16u

39 40 45	Contrast Saturation FreeMemoryCardImages	int16u int16u int16u
63	ColorTemperature	int16s
64	HueAdjustment	int16u
70	Rotation	int16u
71	FNumber	int16u
72	ExposureTime	int16u
74	FreeMemoryCardImages	int16u
94	ImageNumber	int16u
96	NoiseReduction	int16u
98	ImageNumber2	int16u
113	ImageStabilization	int16u
117	ZoneMatchingOn	int16u

# Minolta CameraInfoA100 Tags

Camera information for the Sony DSLR-A100.

Index1	Tag Name	Writable
1	AFSensorActive	int8u
2	AFStatusActiveSensor	int16s
4	AFStatusTop-right	int16s
6	AFStatusBottom-right	int16s
8	AFStatusBottom	int16s
10	AFStatusMiddleHorizontal	int16s
12	AFStatusCenterVertical	int16s
14	AFStatusTop	int16s
16	AFStatusTop-left	int16s
18	AFStatusBottom-left	int16s
20	FocusLocked	int8u
21	AFPoint	int8u
22	AFMode	int8u
45	AFStatusLeft	int16s
47	AFStatusCenterHorizontal	int16s
49	AFStatusRight	int16s
51	AFAreaMode	int8u

# Minolta ISInfoA100 Tags

Image stabilization information for the Sony DSLR-A100.

Index1	Tag Name	Writable
0	ImageStabilization	int16u

# Minolta WBInfoA100 Tags

White balance information for the Sony DSLR-A100.

Index1	Tag Name	Writable
14	DriveMode	int8u
16	Rotation	int8u
20	ImageStabilizationSetting	int8u
21	DynamicRangeOptimizerMode	int8u
42	ExposureCompensationMode	int8u
43	WBBracketShotNumber	int8u
44	WhiteBalanceBracketing	int8u
45	ExposureBracketShotNumber	int8u
49	FlashFunction	int16u
52	ExposureMode	int16u
54	ColorMode	int16u
56	AverageLV	int16u
60	FrameNumber	int8u
150	WB_RGBLevels	int16u[3]
174	WB_GBRGLevels	int16u[4]
192	WB_RedLevelsTungsten	int16u[7]
206	WB_BlueLevelsTungsten	int16u[7]

220	WB_RedLevelsDaylight	int16u[7]
234	WB_BlueLevelsDaylight	int16u[7]
248	WB_RedLevelsCloudy	int16u[7]
262	WB_BlueLevelsCloudy	int16u[7]
276	WB_RedLevelsFlash	int16u[7]
290	WB_BlueLevelsFlash	int16u[7]
332	WB_RedLevelsFluorescent	int16u[7]
346	WB_BlueLevelsFluorescent	int16u[7]
360	WB_RedLevelsShade	int16u[7]
374	WB_BlueLevelsShade	int16u[7]
392	WB_RedLevel6500K	int16u
394	WB_BlueLevel6500K	int16u
396	WB_RedLevelCustom	int16u
398	WB_BlueLevelCustom	int16u
408	WB_RedLevel3500K	int16u
410	WB_BlueLevel3500K	int16u
446	WB_RedLevelsKelvin	int16u[75]
596	WB_BlueLevelsKelvin	int16u[75]
772	WB_RBLevelsFlash	int16u[2]
776	WB_RBLevelsCoolWhiteF	int16u[2]
1000	WB_RBLevelsTungsten	int16u[2]
1004	WB_RBLevelsDaylight	int16u[2]
1008	WB_RBLevelsCloudy	int16u[2]
1012	WB_RBLevelsFlash	int16u[2]
1020	WB_RedLevelsFluorescent	int16u[7]
1034	WB_BlueLevelsFluorescent	int16u[7]
1048	WB_RBLevelsShade	int16u[2]
1056	WB_RBLevels6500K	int16u[2]
1060	WB_RBLevelsCustom	int16u[2]
1072	WB_RBLevels3500K	int16u[2]
1320	WB_RBLevelsDaylight	int16u[2]
1350	WB_RGBLevels	int16u[3]
1576	AEMeteringSegments	int8u[40]
1680	MeasuredLV	int8u
1681	BrightnessValue	int8u
4172	TiffMeteringImage	no
18872	ExposureTime	int8u
18874	ISO	int8u
18875	FocusDistance	int8u
18877	LensType	int16uRev
18880	ExposureCompensation	int8s
18881	FlashExposureComp	int8s
18882	ImageStabilization	int8u
18883	BrightnessValue	int8u
18885	MaxAperture	int8u
18887	FNumber	int8u
18908	InternalSerialNumber	string[12]

# Minolta CameraSettings5D Tags

Index2	Tag Name	Writable
10	ExposureMode	int16u
12	MinoltaImageSize	int16u
13	MinoltaQuality	int16u
14	WhiteBalance	int16u
31	Flash	int16u
32	FlashMode	int16u
37	MeteringMode	int16u
38	ISOSetting	int16u
47	ColorSpace	int16u
48	Sharpness	int16u
49	Contrast	int16u
50	Saturation	int16u
53	ExposureTime	int16u
54	FNumber	int16u
55	FreeMemoryCardImages	int16u
73	ColorTemperature	int16s
74	HueAdjustment	int16u
80	Rotation	int16u

83	ExposureCompensation	int16u
84	FreeMemoryCardImages	int16u
101	Rotation	int16u
110	ColorTemperature	int16s
113	PictureFinish	int16u
174	ImageNumber	int16u
176	NoiseReduction	int16u
189	ImageStabilization	int16u

# Minolta CameraSettingsA100 Tags

Camera settings information for the Sony DSLR-A100.

Index2	Tag Name	Writable
0	ExposureMode	int16u
1	ExposureCompensationSetting	int16u
5	HighSpeedSync	int16u
6	ShutterSpeedSetting	int16u
7	ApertureSetting	int16u
8	ExposureTime	int16u
9	FNumber	int16u
10	DriveMode2	int16u
11	WhiteBalance	int16u
12	FocusMode	int16u
13	AFPointSelected	int16u
14	AFAreaMode	int16u
15	FlashMode	int16u
16	FlashExposureCompSet	int16u
18	MeteringMode	int16u
19	ISOSetting	int16u
20	ZoneMatchingMode	int16u
21	DynamicRangeOptimizer	int16u
22	ColorMode	int16u
23	ColorSpace	int16u
24	Sharpness	int16u
25	Contrast	int16u
26 28	Saturation	int16u int16u
28 29	FlashMetering	int16u
30	PrioritySetupShutterRelease DriveMode	int16u
31	SelfTimerTime	int16u
32	ContinuousBracketing	int16u
33	SingleFrameBracketing	int16u
34	WhiteBalanceBracketing	int16u
35	WhiteBalanceSetting	int16u
36	PresetWhiteBalance	int16u
37	ColorTemperatureSetting	int16u
38	CustomWBSetting	int16u
39	DynamicRangeOptimizerSetting	int16u
50	FreeMemoryCardImages	int16u
52	CustomWBRedLevel	int16u
53	CustomWBGreenLevel	int16u
54	CustomWBBlueLevel	int16u
55	CustomWBError	int16u
56	WhiteBalanceFineTune	int16s
57	ColorTemperature	int16u
58	ColorCompensationFilter	int16s
59	SonyImageSize	int16u
60	SonyQuality	int16u
61	InstantPlaybackTime	int16u
62	InstantPlaybackSetup	int16u
63	NoiseReduction	int16u
64	EyeStartAF	int16u
65	RedEyeReduction	int16u
66	FlashDefault	int16u
67	AutoBracketOrder	int16u
68	FocusHoldButton	int16u
69	AELButton	int16u
70	ControlDialSet	int16u

71	ExposureCompensationMode	int16u
72	AFAssist	int16u
73	CardShutterLock	int16u
74	LensShutterLock	int16u
75	AFAreaIllumination	int16u
76	MonitorDisplayOff	int16u
77	RecordDisplay	int16u
78	PlayDisplay	int16u
80	ExposureIndicator	int16u
81	AELExposureIndicator	int16u
82	ExposureBracketingIndicatorLast	int16u
83	MeteringOffScaleIndicator	int16u
84	FlashExposureIndicator	int16u
85	FlashExposureIndicatorNext	int16u
86	FlashExposureIndicatorLast	int16u
87	ImageStabilization	int16u
88	FocusModeSwitch	int16u
89	FlashType	int16u
90	Rotation	int16u
91	AELock	int16u
94	ColorTemperature	int16u
95	ColorCompensationFilter	int16s
96	BatteryState	int16u

#### Minolta MMA Tags

This information is found in MOV videos from Minolta models such as the DiMAGE A2, S414 and 7Hi.

Index1	Tag Name	Writable
0	Make	no
20	SoftwareVersion	no

#### Minolta MOV1 Tags

This information is found in MOV videos from some Konica Minolta models such as the DiMage Z10 and X50.

Index1	Tag Name	Writable
0	Make	no
32	ModelType	no
46	ExposureTime	no
50	FNumber	no
58	ExposureCompensation	no
80	FocalLength	no

#### Minolta MOV2 Tags

This information is found in MOV videos from some Minolta models such as the DiMAGE X and Xt.

Index1	Tag Name	Writable
0	Make	no
24	ModelType	no
38	ExposureTime	no
42	FNumber	no
50	ExposureCompensation	no
72	FocalLength	no

#### Motorola Tags

ora rago		
Tag ID	Tag Name	Writable
0x5500	BuildNumber	string
0x5501	SerialNumber	string
0x6420	CustomRendered	string
0x64d0	DriveMode	string
0x665e	Sensor	string

	0 6505	Exilion 13.21 lag Names	_
	0x6705	ManufactureDate	string
Nikon	Tarre		
MIROH	Tag ID	Tag Name	Writable
	0x0001	MakerNoteVersion	undef[4]
	0x0002	ISO	int16u[2]
	0x0003	ColorMode	string
	$0 \times 0004$	Quality	string
	0x0005	WhiteBalance	string
	0x0006	Sharpness	string
	$0 \times 0007$	FocusMode	string
	$0 \times 0008$ $0 \times 0009$	FlashSetting FlashType	string string
	0x0009	WhiteBalanceFineTune	int16s[n]
	0x000c	WB_RBLevels	rational64u[4]
	0x000d	ProgramShift	undef[4]
	0x000e	ExposureDifference	undef[4]
	0x000f	ISOSelection	string
	0x0010	DataDump	no
	0x0011	PreviewIFD	Nikon PreviewIFD
	0x0012	FlashExposureComp	undef[4]
	0x0013	ISOSetting	int16u[2]
	0x0014	ColorBalanceA	Nikon ColorBalanceA Nikon ColorBalanceB
		NRWData	Nikon ColorBalanceC
	0x0016	ImageBoundary	int16u[4]
	0x0010 0x0017	ExternalFlashExposureComp	undef[4]
	0x0018	FlashExposureBracketValue	undef[4]
	0x0019	ExposureBracketValue	rational64s
	0x001a	ImageProcessing	string
	0x001b	CropHiSpeed	int16u[7]
	0x001c	ExposureTuning	undef[3]
	0x001d	SerialNumber	string!
	0x001e	ColorSpace	int16u Nikon VRInfo
	0x001f 0x0020	VRInfo ImageAuthentication	int8u
	0x0020 $0x0021$	FaceDetect	Nikon FaceDetect
	0x0021	ActiveD-Lighting	int16u
	0x0023	PictureControlData	Nikon PictureControl
			Nikon PictureControl2
			Nikon PictureControl3
			Nikon PictureControlUnknown
	$0 \times 0024$	WorldTime	Nikon WorldTime
	$0 \times 0025$	ISOInfo	Nikon ISOInfo
	0x002a 0x002b	VignetteControl DistortInfo	int16u Nikon DistortInfo
	0x002b	UnknownInfo	Nikon UnknownInfo
	0x0020	UnknownInfo2	Nikon UnknownInfo2
	0x0034	ShutterMode	int16u
	0x0035	HDRInfo	Nikon HDRInfo
		HDRInfo2	Nikon HDRInfo2
	0x0037	MechanicalShutterCount	int32u
	0x0039	LocationInfo	Nikon LocationInfo
	0x003d	BlackLevel	int16u[4]
	0x003e	ImageSizeRAW WhiteBalanceFineTune	yes rational64s[2]
	0x003f 0x0044	JPGCompression	yes
	0x0044	CropArea	int16u[4]
	0x004e	NikonSettings	NikonSettings
	0x004f	ColorTemperatureAuto	int16u
	0x0080	ImageAdjustment	string
	0x0081	ToneComp	string
	0x0082	AuxiliaryLens	string
	0x0083	LensType	int8u
	$0 \times 0084$	Lens	rational64u[4]
	0x0085 0x0086	ManualFocusDistance	rational64u rational64u
	0x0086 $0x0087$	DigitalZoom FlashMode	int8u
	0x0087 $0x0088$	AFInfo	Nikon AFInfo
	3110000	<del></del>	

		Nikon AFInfo
0x0089	ShootingMode	int16u~
0x008b	LensFStops	undef[4]
0x008c	ContrastCurve	undef!
0x008d	ColorHue	string
0x008f	SceneMode	string
0x0090	LightSource	string
$0 \times 0091$	ShotInfoD40	Nikon ShotInfoD40
	ShotInfoD80	Nikon ShotInfoD80
	ShotInfoD90	Nikon ShotInfoD90
	ShotInfoD3a ShotInfoD3b	Nikon ShotInfoD3a Nikon ShotInfoD3b
	ShotInfoD3X	Nikon ShotInfoD3X
	ShotInfoD3X ShotInfoD3S	Nikon ShotInfoD3X
	ShotInfoD300a	Nikon ShotInfoD300a
	ShotInfoD300b	Nikon ShotInfoD300b
	ShotInfoD300S	Nikon ShotInfoD300S
	ShotInfoD700	Nikon ShotInfoD700
	ShotInfoD780	Nikon ShotInfoD780
	ShotInfoD7500	Nikon ShotInfoD7500
	ShotInfoD800	Nikon ShotInfoD800
	ShotInfoD810	Nikon ShotInfoD810
	ShotInfoD850	Nikon ShotInfoD850
	ShotInfoD5000	Nikon ShotInfoD5000
	ShotInfoD5100	Nikon ShotInfoD5100
	ShotInfoD5200	Nikon ShotInfoD5200
	ShotInfoD7000	Nikon ShotInfoD7000 Nikon ShotInfoD4
	ShotInfoD4 ShotInfoD4S	Nikon ShotInfoD4 Nikon ShotInfoD4S
	ShotInfoD45 ShotInfoD500	Nikon ShotInfoD500
	ShotInfoD6	Nikon ShotInfoD6
	ShotInfoD610	Nikon ShotInfoD610
	ShotInfoZ6III	Nikon ShotInfoZ6III
	ShotInfoZ7II	Nikon ShotInfoZ7II
	ShotInfoZ8	Nikon ShotInfoZ8
	ShotInfoZ9	Nikon ShotInfoZ9
	ShotInfo02xx	Nikon ShotInfo
	ShotInfoUnknown	Nikon ShotInfo
$0 \times 0092$	HueAdjustment	int16s
0x0093	NEFCompression	int16u
$0 \times 0094$	SaturationAdj	int16s
$0 \times 0095$ $0 \times 0096$	NoiseReduction NEFLinearizationTable	string undef!
0x0096 0x0097	ColorBalance0100	Nikon ColorBalancel
0.0097	ColorBalance0100	Nikon ColorBalance2
	ColorBalance0103	Nikon ColorBalance3
	ColorBalance0205	Nikon ColorBalance2
	ColorBalance0209	Nikon ColorBalance4
	ColorBalance02	Nikon ColorBalance2
	ColorBalance0211	Nikon ColorBalance4
	ColorBalance0213	Nikon ColorBalance2
	ColorBalance0215	Nikon ColorBalance4
	ColorBalance0219	Nikon ColorBalance2
	ColorBalanceUnknown1	Nikon ColorBalanceUnknown
	ColorBalanceUnknown2	Nikon ColorBalanceUnknown2
	ColorBalanceUnknown	Nikon ColorBalanceUnknown
0x0098	LensData0100	Nikon LensData00
	LensData0101	Nikon LensData01 Nikon LensData01
	LensData0201 LensData0204	Nikon LensDataUI Nikon LensData0204
	LensData0400	Nikon LensData0400
	LensData0400	Nikon LensData0400
	LensData0402	Nikon LensData0403
	LensData0800	Nikon LensData0800
	LensDataUnknown	Nikon LensDataUnknown
0x0099	RawImageCenter	int16u[2]
0x009a	SensorPixelSize	rational64u[2]
0x009c	SceneAssist	string
0x009d		5
	DateStampMode	int16u
0x009e	DateStampMode RetouchHistory	

000-0	Carria laterrale and	
0x00a0	SerialNumber	string
0x00a2	ImageDataSize	int32u
0x00a5	ImageCount	int32u
0x00a6	DeletedImageCount	int32u
0x00a7	ShutterCount	int32u!
0x00a8	FlashInfo0100	Nikon FlashInfo0100
	FlashInfo0102	Nikon FlashInfo0102
	FlashInfo0103	Nikon FlashInfo0103
	FlashInfo0106	Nikon FlashInfo0106
	FlashInfo0107	Nikon FlashInfo0107
	FlashInfo0300	Nikon FlashInfo0300
	FlashInfoUnknown	Nikon FlashInfoUnknown
0x00a9	ImageOptimization	string
0x00aa	Saturation	string
0x00ab	VariProgram	string
0x00ac	ImageStabilization	string
0x00ad	AFResponse	string
0x00b0	MultiExposure	Nikon MultiExposure
	MultiExposure2	Nikon MultiExposure
	-	Nikon MultiExposure2
0x00b1	HighISONoiseReduction	int16u
0x00b3	ToningEffect	string
0x00b6	PowerUpTime	undef
0x00b7	AFInfo2	Nikon AFInfo2V0100
		Nikon AFInfo2V0101
		Nikon AFInfo2V0200
		Nikon AFInfo2V0300
		Nikon AFInfo2V0400
0x00b8	FileInfo	Nikon FileInfo
0110020	1 11011110	Nikon FileInfo
0x00b9	AFTune	Nikon AFTune
0x00bb	RetouchInfo	Nikon RetouchInfo
$0 \times 0.0 \text{ bd}$	PictureControlData	Nikon PictureControl
0x00bd 0x00bf	SilentPhotography	yes
0x00c3	BarometerInfo	Nikon BarometerInfo
0x0e00	PrintIM	PrintIM
0x0e00		NikonCapture
0x0e01 0x0e09	NikonCaptureData NikonCaptureVersion	string^
0x0e09 0x0e0e	-	Nikon CaptureOffsets
	NikonCaptureOffsets	
0x0e10	NikonScanIFD	Nikon Scan
0x0e13	NikonCaptureEditVersions	NikonCapture
0 0 1 1	NikonCaptureEditVersions	undef!^
0x0e1d	NikonICCProfile	ICC_Profile
0x0e1e	NikonCaptureOutput	Nikon CaptureOutput
0x0e22	NEFBitDepth	int16u[4]!

# Nikon ast Tags

Tags used by Nikon NX Studio in Nikon NKSC sidecar files and trailers.

These tags belong to the ExifTool XMP-ast family 1 group.

Tag Name	Writable
About	no
GPSAltitude	no
GPSAltitudeRef	no
GPSImgDirection	no
GPSImgDirectionRef	no
GPSLatitude	no
GPSLatitudeRef	no
GPSLongitude	no
GPSLongitudeRef	no
GPSMapDatum	no
GPSVersionID	no
IPTC	IPTC
Version	no
XMLPackets	XMP

These tags belong to the ExifTool XMP-nine family 1 group.

Tag Name	Writable
About	no
Label	no
NineEdits	Nikon NineEdits
Rating	no
Trim	no
Version	no

#### Nikon NineEdits Tags

XML-based tags used to store editing information.

Tag Name	Writable
FilterParametersBinary	no
FilterParametersCustomCustomData	no
FilterParametersExportExportData	no

### Nikon sdc Tags

These tags belong to the ExifTool XMP-sdc family 1 group.

Tag Name	Writable
About	no
AppName	no
AppVersion	no
Version	no

#### Nikon PreviewIFD Tags

Tag ID	Tag Name	Writable
0x00fe	SubfileType	no
0x0103	Compression	no
0x011a	XResolution	no
$0 \times 011b$	YResolution	no
0x0128	ResolutionUnit	no
0x0201	PreviewImageStart	int32u*
$0 \times 0202$	PreviewImageLength	int32u*
$0 \times 0213$	YCbCrPositioning	no

### Nikon ColorBalanceA Tags

Index2	Tag Name	Writable
624	WB_RBLevels	int16u[2]!
626	WB_RBLevelsAuto	int16u[2]!
628	WB_RBLevelsDaylight	int16u[14]!
642	WB_RBLevelsIncandescent	int16u[14]!
656	WB_RBLevelsFluorescent	int16u[6]!
662	WB_RBLevelsCloudy	int16u[14]!
676	WB_RBLevelsFlash	int16u[14]!
690	WB_RBLevelsShade	int16u[14]!

### Nikon ColorBalanceB Tags

Color balance tags used by the P6000.

Index1	Tag Name	Writable
4	ColorBalanceVersion	undef[4]
5096	WB_RGGBLevels	int32u[4]!
5112	WB_RGGBLevelsDaylight	int32u[4]!
5128	WB_RGGBLevelsCloudy	int32u[4]!
5160	WB_RGGBLevelsTungsten	int32u[4]!

5176	WB_RGGBLevelsFluorescentW	int32u[4]!
5192	WB_RGGBLevelsFlash	int32u[4]!
5224	WB_RGGBLevelsCustom	int32u[4]!
5240	WB_RGGBLevelsAuto	int32u[4]!

# Nikon ColorBalanceC Tags

Color balance tags used by the P1000, P7000, P7100 and B700.

Index1	Tag Name	Writable
4	ColorBalanceVersion	undef[4]
32	BlackLevel	int16u
56	WB_RGGBLevels	int32u[4]!
76	WB_RGGBLevelsDaylight	int32u[4]!
96	WB_RGGBLevelsCloudy	int32u[4]!
116	WB_RGGBLevelsShade	int32u[4]!
136	WB_RGGBLevelsTungsten	int32u[4]!
156	WB_RGGBLevelsFluorescentW	int32u[4]!
176	WB_RGGBLevelsFluorescentN	int32u[4]!
196	WB_RGGBLevelsFluorescentD	int32u[4]!
216	WB_RGGBLevelsHTMercury	int32u[4]!
256	WB_RGGBLevelsCustom	int32u[4]!
276	WB_RGGBLevelsAuto	int32u[4]!

# Nikon VRInfo Tags

Index1	Tag Name	Writable
0	VRInfoVersion	no
4	VibrationReduction	int8u
6	VRMode	int8u
8	VRType	int8u

# Nikon FaceDetect Tags

Index2	Tag Name	Writable
1	FaceDetectFrameSize	int16u[2]
3	FacesDetected	int16u
4	Face1Position	int16u[4]
8	Face2Position	int16u[4]
12	Face3Position	int16u[4]
16	Face4Position	int16u[4]
20	Face5Position	int16u[4]
24	Face6Position	int16u[4]
28	Face7Position	int16u[4]
32	Face8Position	int16u[4]
36	Face9Position	int16u[4]
40	Face10Position	int16u[4]
44	FacellPosition	int16u[4]
48	Face12Position	int16u[4]

# Nikon PictureControl Tags

Index1	Tag Name	Writable
0	PictureControlVersion	no
4	PictureControlName	string[20]
24	PictureControlBase	string[20]
48	PictureControlAdjust	int8u
49	PictureControlQuickAdjust	int8u
50	Sharpness	int8u
51	Contrast	int8u
52	Brightness	int8u
53	Saturation	int8u
54	HueAdjustment	int8u
55	FilterEffect	int8u
56	ToningEffect	int8u
57	ToningSaturation	int8u

# Nikon PictureControl2 Tags

Index1	Tag Name	Writable
0	PictureControlVersion	no
4	PictureControlName	string[20]
24	PictureControlBase	string[20]
48	PictureControlAdjust	int8u
49	PictureControlQuickAdjust	int8u
51	Sharpness	int8u
53	Clarity	int8u
55	Contrast	int8u
57	Brightness	int8u
59	Saturation	int8u
61	Hue	int8u
63	FilterEffect	int8u
64	ToningEffect	int8u
65	ToningSaturation	int8u

### Nikon PictureControl3 Tags

Index1	Tag Name	Writable
0	PictureControlVersion	no
8	PictureControlName	string[20]
28	PictureControlBase	string[20]
54	PictureControlAdjust	int8u
55	PictureControlQuickAdjust	int8u
57	Sharpness	int8u
59	MidRangeSharpness	int8u
61	Clarity	int8u
63	Contrast	int8u
65	Brightness	int8u
67	Saturation	int8u
69	Hue	int8u
71	FilterEffect	int8u
72	ToningEffect	int8u
73	ToningSaturation	int8u

# Nikon PictureControlUnknown Tags

Index1	Tag Name	Writable
0	PictureControlVersion	no

# Nikon WorldTime Tags

Index1	Tag Name	Writable
0	TimeZone	int16s
2	DaylightSavings	int8u
3	DateDisplayFormat	int8u

# Nikon ISOInfo Tags

Index1	Tag Name	Writable
0	ISO	int8u
4	ISOExpansion	int16u
6	ISO2	int8u
10	ISOExpansion2	int16u

# Nikon DistortInfo Tags

Index1	Tag Name	Writable
0	DistortionVersion?	no
4	AutoDistortionControl	int8u

### Nikon UnknownInfo Tags

Index4	Tag Name	Writable
0	UnknownInfoVersion?	no

### Nikon UnknownInfo2 Tags

Index4	Tag Name	Writable
0	UnknownInfo2Version?	no

### Nikon HDRInfo Tags

Index1	Tag Name	Writable
0	HDRInfoVersion	no
4	HDR	int8u
5	HDRLevel	int8u
6	HDRSmoothing	int8u
7	HDRLevel2	int8u

### Nikon HDRInfo2 Tags

Index1	Tag Name	Writable
0	HDRInfoVersion	no
4	HDR	int8u
5	HDRLevel	int8u

### Nikon LocationInfo Tags

Tags written by some Nikon GPS-equipped cameras like the AW100.

Index1	Tag Name	Writable
0	LocationInfoVersion	undef[4]
4	TextEncoding	int8u
5	CountryCode	undef[3]
8	POILevel	int8u
9	Location	undef[70]

### Nikon MakerNotes0x51 Tags

Index1	Tag Name	Writable
0	FirmwareVersion51	no
10	NEFCompression	int16u

# Nikon MakerNotes0x56 Tags

Index1	Tag Name	Writable
0	FirmwareVersion56	no
4	BurstGroupID	int16u

## Nikon AFInfo Tags

Index1	Tag Name	Writable
0	AFAreaMode	int8u
1	AFPoint	int8u
2	AFPointsInFocus	int16u

## Nikon ShotInfoD40 Tags

These tags are extracted from encrypted data in D40 and D40X images.

Index	Tag Name	Writable

0	ShotInfoVersion	no
582	ShutterCount	int32u
586.1	VibrationReduction	int8u & 0x08
729	CustomSettingsD40	NikonCustom SettingsD40

### Nikon ShotInfoD80 Tags

These tags are extracted from encrypted data in D80 images.

Index	Tag Name	Writable
0	ShotInfoVersion	no
586	ShutterCount	int32u
590.1	Rotation	int8u & 0x07
590.2	VibrationReduction	int8u & 0x18
590.3	FlashFired	int8u & 0xe0
708	NikonImageSize	int8u & 0xf0
708.1	ImageQuality	int8u & 0x0f
748	CustomSettingsD80	NikonCustom SettingsD80

#### Nikon ShotInfoD90 Tags

These tags are extracted from encrypted data in images from the D90 with firmware 1.00.

Index	Tag Name	Writable
0	ShotInfoVersion	no
4	FirmwareVersion	no
693	ISO2	int8u
725	ShutterCount	int32u
884	CustomSettingsD90	NikonCustom SettingsD90

#### Nikon ShotInfoD3a Tags

These tags are extracted from encrypted data in images from the D3 with firmware 1.00 and earlier.

Index	Tag Name	Writable
0	ShotInfoVersion	no
598	ISO2	int8u
630	ShutterCount	int32u
723.1	NikonImageSize	int8u & 0x18
723.2	ImageQuality	int8u & 0x07
769	CustomSettingsD3	NikonCustom SettingsD3

#### Nikon ShotInfoD3b Tags

These tags are extracted from encrypted data in images from the D3 with firmware 1.10, 2.00, 2.01 and 2.02.

Index	Tag Name	Writable
0	ShotInfoVersion	no
4	FirmwareVersion	no
16	ImageArea	int8u
605	ISO2	int8u
637	ShutterCount	int32u
639	ShutterCount	int32u
650	PreFlashReturnStrength	int8u
732.1	NikonImageSize	int8u & 0x18
732.2	ImageQuality	int8u & 0x07
778	CustomSettingsD3	NikonCustom SettingsD3

### Nikon ShotInfoD3X Tags

These tags are extracted from encrypted data in images from the D3X with firmware 1.00.

Index	Tag Name	Writable
0	ShotInfoVersion	no
4	FirmwareVersion	no
605	ISO2	int8u
640	ShutterCount	int32u
779	CustomSettingsD3X	NikonCustom SettingsD3

### Nikon ShotInfoD3S Tags

These tags are extracted from encrypted data in images from the D3S with firmware 1.00 and earlier.

Index	Tag Name	Writable
0	ShotInfoVersion	no
4	FirmwareVersion	no
16	ImageArea	int8u
545	ISO2	int8u
578	ShutterCount	int32u
671.1	JPGCompression	int8u & 0x40
718	CustomSettingsD3S	NikonCustom SettingsD3

#### Nikon ShotInfoD300a Tags

These tags are extracted from encrypted data in images from the  ${\tt D300}$  with firmware 1.00 and earlier.

Index	Tag Name	Writable
0	ShotInfoVersion	no
604	ISO2	int8u
633	ShutterCount	int32u
721	AFFineTuneAdj	int16u
790	CustomSettingsD300	NikonCustom SettingsD3

#### Nikon ShotInfoD300b Tags

These tags are extracted from encrypted data in images from the  ${\tt D300}$  with firmware 1.10.

Index	Tag Name	Writable
0	ShotInfoVersion	no
4	FirmwareVersion	no
613	ISO2	int8u
644	ShutterCount	int32u
732	AFFineTuneAdj	int16u
802	CustomSettingsD300	NikonCustom SettingsD3

### Nikon ShotInfoD300S Tags

These tags are extracted from encrypted data in images from the  ${\tt D300S}$  with firmware 1.00.

Index	Tag Name	Writable
0	ShotInfoVersion	no
4	FirmwareVersion	no
613	ISO2	int8u
646	ShutterCount	int32u
804	CustomSettingsD300S	NikonCustom SettingsD3

# Nikon ShotInfoD700 Tags

These tags are extracted from encrypted data in images from the D700 with firmware 1.02f.

Index	Tag Name	Writable

0	ShotInfoVersion	no
4	FirmwareVersion	no
613	ISO2	int8u
647	ShutterCount	int32u
804	CustomSettingsD700	NikonCustom SettingsD700

### Nikon ShotInfoD780 Tags

These tags are extracted from encrypted data in images from the D780.

Index	Tag Name	Writable
0	ShotInfoVersion	no
4	FirmwareVersion	no
156	OrientOffset	Nikon OrientationInfo

### Nikon OrientationInfo Tags

Index1	Tag Name	Writable
0	RollAngle	fixed32u
4	PitchAngle	fixed32u
8	YawAngle	fixed32u

### Nikon ShotInfoD7500 Tags

These tags are extracted from encrypted data in images from the D7500.

Index	Tag Name	Writable
0	ShotInfoVersion	no
4	FirmwareVersion	no
160	OrientOffset	Nikon OrientationInfo

## Nikon ShotInfoD800 Tags

These tags are extracted from encrypted data in images from the D800.

Index	Tag Name	Writable
0	ShotInfoVersion	no
4	FirmwareVersion	no
1216	RepeatingFlashOutputExternal	int8u
1218	RepeatingFlashRateExternal	int8u
1219	RepeatingFlashCountExternal	int8u
1234	FlashExposureComp2	int8s
1242	RepeatingFlashRateBuilt-in	int8u
1243	RepeatingFlashCountBuilt-in	int8u
1308	SequenceNumber	int8u
1531	ShutterCount	int32u
1772	CustomSettingsD800	NikonCustom SettingsD800

# Nikon ShotInfoD810 Tags

These tags are extracted from encrypted data in images from the D810.

Index	Tag Name	Writable
0	ShotInfoVersion	no
4	FirmwareVersion	no
16	SettingsOffset	Nikon SettingsInfoD810
36	BracketingOffset	Nikon BracketingInfoD810
56	ISOAutoOffset	Nikon ISOAutoInfoD810
64	CustomSettingsOffset	NikonCustom SettingsD810
132	OrientationOffset	Nikon OrientationInfo

# Nikon SettingsInfoD810 Tags

Index1	Tag Name	Writable

316 SecondarySlotFunction int8u & 0x03

## Nikon BracketingInfoD810 Tags

Index1	Tag Name	Writable
15	AEBracketingSteps	int8u & 0xff
16	WBBracketingSteps	int8u & 0xff
23	NikonMeteringMode	int8u & 0x03

### Nikon ISOAutoInfoD810 Tags

Index1	Tag Name	Writable
4	ISOAutoShutterTime	int8u & 0x3f
5	ISOAutoHiLimit	int8u & 0xff

## Nikon ShotInfoD850 Tags

These tags are extracted from encrypted data in images from the D850.

Index	Tag Name	Writable
0	ShotInfoVersion	no
4	FirmwareVersion	no
16	MenuSettingsOffset	Nikon MenuSettingsD850
76	MoreSettingsOffset	Nikon MoreSettingsD850
88	CustomSettingsOffset	NikonCustom SettingsD850
160	OrientationOffset	Nikon OrientationInfo

### Nikon MenuSettingsD850 Tags

Index1	Tag Name	Writable
1757	PhotoShootingMenuBankImageArea	int8u & 0x07

### Nikon MoreSettingsD850 Tags

Index1	Tag Name	Writable
36	PhotoShootingMenuBank	int8u & 0x03
37	PrimarySlot	int8u & 0x80

# Nikon ShotInfoD5000 Tags

These tags are extracted from encrypted data in images from the D5000 with firmware 1.00.

Index	Tag Name	Writable
0	ShotInfoVersion	no
4	FirmwareVersion	no
693	ISO2	int8u
726	ShutterCount	int32u
888	CustomSettingsD5000	NikonCustom SettingsD5000

#### Nikon ShotInfoD5100 Tags

Index	Tag Name	Writable
0	ShotInfoVersion	no
4	FirmwareVersion	no
801	ShutterCount	int32u
1031	CustomSettingsD5100	NikonCustom SettingsD5100

### Nikon ShotInfoD5200 Tags

Index	Tag Name	Writable
0	ShotInfoVersion	no

4	FirmwareVersion	no
3032	ShutterCount	int32u
3285	CustomSettingsD5200	NikonCustom SettingsD5200

## Nikon ShotInfoD7000 Tags

These tags are extracted from encrypted data in images from the  ${\tt D7000}$  with firmware 1.01b.

Index	Tag Name	Writable
0	ShotInfoVersion	no
4	FirmwareVersion	no
800	ShutterCount	int32u
1028	CustomSettingsD7000	NikonCustom SettingsD7000

## Nikon ShotInfoD4 Tags

These tags are extracted from encrypted data in images from the D4.

Index	Tag Name	Writable
0	ShotInfoVersion	no
4	FirmwareVersion	no
1873	CustomSettingsD4	NikonCustom SettingsD4

## Nikon ShotInfoD4S Tags

These tags are extracted from encrypted data in images from the D4S.

Index	Tag Name	Writable
0	ShotInfoVersion	no
4	FirmwareVersion	no
464	SecondarySlotFunction	int8u & 0x03
5964	AEBracketingSteps	int8u & 0xff
5965	WBBracketingSteps	int8u & 0xff
6221	ReleaseMode	int8u & 0xff
6301	CustomSettingsD4S	NikonCustom SettingsD4
6338	MultiSelectorLiveViewMode	int8u & 0xc0
6378	ISOAutoShutterTime	int8u & 0x3f
6379	ISOAutoHiLimit	int8u & 0xff
6461	CustomSettingsD4S	NikonCustom SettingsD4
13579	OrientationInfo	Nikon OrientationInfo
13971	Rotation	int8u & 0x30

### Nikon ShotInfoD500 Tags

These tags are extracted from encrypted data in images from the D5 and  $\mathsf{D500}$ .

Index	Tag Name	Writable
0	ShotInfoVersion	no
4	FirmwareVersion	no
16	RotationInfoOffset	Nikon RotationInfoD500
20	JPGInfoOffset	Nikon JPGInfoD500
44	BracketingOffset	Nikon BracketingInfoD500
80	ShootingMenuOffset	Nikon ShootingMenuD500
88	CustomSettingsOffset	Nikon CustomSettingsD500
160	OrientationOffset	Nikon OrientationInfo
168	OtherOffset	Nikon OtherInfoD500

# Nikon RotationInfoD500 Tags

Index1	Tag Name	Writable
26	Rotation	int8u & 0x03
32	Interval	int8u~
36	IntervalFrame	int8u~

1330 FlickerReductionIndicator int8u & 0x01

# $\underline{\texttt{Nikon}}\ \underline{\texttt{JPGInfoD500}}\ \underline{\texttt{Tags}}$

Index1	Tag Name	Writable
36	JPGCompression	int8u & 0x01

### Nikon BracketingInfoD500 Tags

Index1	Tag Name	Writable
15	AEBracketingSteps	int8u & 0xff
16	WBBracketingSteps	int8u & 0xff
23	ADLBracketingStep	int8u & 0xf0
24	ADLBracketingType	int8u & 0x0f

## Nikon ShootingMenuD500 Tags

Index1	Tag Name	Writable
0	PhotoShootingMenuBank	int8u & 0x03
2	PrimarySlot	int8u & 0x80
4	ISOAutoShutterTime	int8u & 0x3f
5	ISOAutoHiLimit	int8u & 0xff
7	FlickerReduction	int8u & 0x20
7.1	PhotoShootingMenuBankImageArea	int8u & 0x07

## Nikon CustomSettingsD500 Tags

Index1	Tag Name	Writable
0	CustomSettingsD5	NikonCustom SettingsD5
	CustomSettingsD500	NikonCustom SettingsD500

# $\underline{\text{Nikon}}$ $\underline{\text{OtherInfoD500}}$ $\underline{\text{Tags}}$

Index1	Tag Name	Writable
532	NikonMeteringMode	int8u & 0x03

## Nikon ShotInfoD6 Tags

These tags are extracted from encrypted data in images from the D6.

Inc	lex	Tag Name	Writable
	0	ShotInfoVersion	no
	4	FirmwareVersion	no
4	18	SequenceOffset	Nikon SeqInfoD6
15	6	OrientationOffset	Nikon OrientationInfo
16	54	IntervalOffset	Nikon IntervalInfoD6

## Nikon SeqInfoD6 Tags

Index1	Tag Name	Writable
36	IntervalShooting	int16u~
43	ImageArea	int8u

### Nikon IntervalInfoD6 Tags

Tag Name	Writable
Intervals	int32u
ShotsPerInterval	int32u
IntervalExposureSmoothing	int8u
IntervalPriority	int8u
FocusShiftNumberShots	int8u
FocusShiftStepWidth	int8u
	Intervals ShotsPerInterval IntervalExposureSmoothing IntervalPriority FocusShiftNumberShots

432	FocusShiftInterval	int8u~
436	FocusShiftExposureLock	int8u
526	DiffractionCompensation	int8u
532	FlashControlMode	int8u
538	FlashGNDistance?	no
542	FlashOutput?	int8u
552	FlashRemoteControl?	int8u
556	FlashMasterControlMode	int8u
558	FlashMasterCompensation?	int8s
562	FlashMasterOutput?	int8u
564	FlashWirelessOption?	int8u
714	MovieType?	int8u

## Nikon ShotInfoD610 Tags

These tags are extracted from encrypted data in images from the D610.

Index	Tag Name	Writable
0	ShotInfoVersion	no
4	FirmwareVersion	no
1999	CustomSettingsD610	NikonCustom SettingsD610

## Nikon ShotInfoZ6III Tags

These tags are extracted from encrypted data in images from the Z6III.

Index	Tag Name	Writable
0	ShotInfoVersion	no
4	FirmwareVersion	no
136	OrientationOffset	Nikon OrientationInfo
144	MenuOffset	Nikon MenuSettingsZ6III

# Nikon MenuSettingsZ6III Tags

These tags are used by the Z6III.

364 HighFrameRate int8u 444 MultipleExposureMode int8u 446 MultiExposureShots int8u 476 IntervalDurationHours int32u 480 IntervalDurationSeconds int32u 484 IntervalDurationSeconds int32u 492 Intervals int32u 496 ShotsPerInterval int32u 500 IntervalExposureSmoothing int8u 502 IntervalPriority int8u 536 FocusShiftNumberShots int8u 540 FocusShiftStepWidth int8u 544 FocusShiftInterval int8u 548 FocusShiftExposureLock int8u 648 AutoISO int8u 650 ISOAutoHiLimit? int16u 718 DiffractionCompensation int8u 720 FlickerReductionShooting int8u 721 NikonMeteringMode int8u 722 NikonMeteringMode int8u 723 FlashControlMode
446 MultiExposureShots int8u 476 IntervalDurationHours int32u 480 IntervalDurationMinutes int32u 484 IntervalDurationSeconds int32u 492 Intervals int32u 496 ShotsPerInterval int32u 500 IntervalExposureSmoothing int8u 502 IntervalPriority int8u 536 FocusShiftNumberShots int8u 540 FocusShiftStepWidth int8u 544 FocusShiftInterval int8u 548 FocusShiftExposureLock int8u 648 AutoISO int8u 650 ISOAutoHiLimit? int16u 718 DiffractionCompensation int8u 719 AutoDistortionControl int8u 720 FlickerReductionShooting int8u 722 NikonMeteringMode int8u
476 IntervalDurationHours int32u 480 IntervalDurationMinutes int32u 484 IntervalDurationSeconds int32u 492 Intervals int32u 496 ShotsPerInterval int32u 500 IntervalExposureSmoothing int8u 502 IntervalPriority int8u 536 FocusShiftNumberShots int8u 540 FocusShiftStepWidth int8u 544 FocusShiftInterval int8u 548 FocusShiftExposureLock int8u 648 AutoISO int8u 650 ISOAutoHiLimit? int16u 718 DiffractionCompensation int8u 719 AutoDistortionControl int8u 720 FlickerReductionShooting int8u 722 NikonMeteringMode int8u
480 IntervalDurationMinutes int32u 484 IntervalDurationSeconds int32u 492 Intervals int32u 496 ShotsPerInterval int32u 500 IntervalExposureSmoothing int8u 502 IntervalPriority int8u 536 FocusShiftNumberShots int8u 540 FocusShiftStepWidth int8u 544 FocusShiftInterval int8u 548 FocusShiftExposureLock int8u 648 AutoISO int8u 650 ISOAutoHiLimit? int16u 718 DiffractionCompensation int8u 719 AutoDistortionControl int8u 720 FlickerReductionShooting int8u 722 NikonMeteringMode int8u
484 IntervalDurationSeconds int32u 492 Intervals int32u 496 ShotsPerInterval int32u 500 IntervalExposureSmoothing int8u 502 IntervalPriority int8u 536 FocusShiftNumberShots int8u 540 FocusShiftStepWidth int8u 544 FocusShiftInterval int8u 548 FocusShiftExposureLock int8u 648 AutoISO int8u 650 ISOAutoHiLimit? int16u 718 DiffractionCompensation int8u 719 AutoDistortionControl int8u 720 FlickerReductionShooting int8u 722 NikonMeteringMode int8u
492 Intervals int32u 496 ShotsPerInterval int32u 500 IntervalExposureSmoothing int8u 502 IntervalPriority int8u 536 FocusShiftNumberShots int8u 540 FocusShiftStepWidth int8u 544 FocusShiftInterval int8u 548 FocusShiftExposureLock int8u 648 AutoISO int8u 650 ISOAutoHiLimit? int16u 718 DiffractionCompensation int8u 719 AutoDistortionControl int8u 720 FlickerReductionShooting int8u 722 NikonMeteringMode int8u
496 ShotsPerInterval int32u 500 IntervalExposureSmoothing int8u 502 IntervalPriority int8u 536 FocusShiftNumberShots int8u 540 FocusShiftStepWidth int8u 544 FocusShiftInterval int8u 548 FocusShiftExposureLock int8u 648 AutoISO int8u 650 ISOAutoHiLimit? int16u 718 DiffractionCompensation int8u 719 AutoDistortionControl int8u 720 FlickerReductionShooting int8u 722 NikonMeteringMode int8u
500 IntervalExposureSmoothing int8u 502 IntervalPriority int8u 536 FocusShiftNumberShots int8u 540 FocusShiftStepWidth int8u 544 FocusShiftInterval int8u 548 FocusShiftExposureLock int8u 648 AutoISO int8u 650 ISOAutoHiLimit? int16u 718 DiffractionCompensation int8u 719 AutoDistortionControl int8u 720 FlickerReductionShooting int8u 722 NikonMeteringMode int8u
502 IntervalPriority int8u 536 FocusShiftNumberShots int8u 540 FocusShiftStepWidth int8u 544 FocusShiftInterval int8u 548 FocusShiftExposureLock int8u 648 AutoISO int8u 650 ISOAutoHiLimit? int16u 718 DiffractionCompensation int8u 719 AutoDistortionControl int8u 720 FlickerReductionShooting int8u 722 NikonMeteringMode int8u
536 FocusShiftNumberShots int8u 540 FocusShiftStepWidth int8u 544 FocusShiftInterval int8u~ 548 FocusShiftExposureLock int8u 648 AutoISO int8u 650 ISOAutoHiLimit? int16u 718 DiffractionCompensation int8u 719 AutoDistortionControl int8u 720 FlickerReductionShooting int8u 722 NikonMeteringMode int8u
540 FocusShiftStepWidth int8u 544 FocusShiftInterval int8u~ 548 FocusShiftExposureLock int8u 648 AutoISO int8u 650 ISOAutoHiLimit? int16u 718 DiffractionCompensation int8u 719 AutoDistortionControl int8u 720 FlickerReductionShooting int8u 722 NikonMeteringMode int8u
544 FocusShiftInterval int8u° 548 FocusShiftExposureLock int8u 648 AutoISO int8u 650 ISOAutoHiLimit? int16u 718 DiffractionCompensation int8u 719 AutoDistortionControl int8u 720 FlickerReductionShooting int8u 722 NikonMeteringMode int8u
548 FocusShiftExposureLock int8u 648 AutoISO int8u 650 ISOAutoHiLimit? int16u 718 DiffractionCompensation int8u 719 AutoDistortionControl int8u 720 FlickerReductionShooting int8u 722 NikonMeteringMode int8u
648 AutoISO int8u 650 ISOAutoHiLimit? int16u 718 DiffractionCompensation int8u 719 AutoDistortionControl int8u 720 FlickerReductionShooting int8u 722 NikonMeteringMode int8u
650 ISOAutoHiLimit? int16u 718 DiffractionCompensation int8u 719 AutoDistortionControl int8u 720 FlickerReductionShooting int8u 722 NikonMeteringMode int8u
718 DiffractionCompensation int8u 719 AutoDistortionControl int8u 720 FlickerReductionShooting int8u 722 NikonMeteringMode int8u
719 AutoDistortionControl int8u 720 FlickerReductionShooting int8u 722 NikonMeteringMode int8u
720 FlickerReductionShooting int8u 722 NikonMeteringMode int8u
722 NikonMeteringMode int8u
5
724 FlashControlMode int8u
730 FlashGNDistance? no
734 FlashOutput? int8u
742 FlashWirelessOption? int8u
744 FlashRemoteControl? int8u
748 FlashMasterControlMode int8u
750 FlashMasterCompensation? int8s
754 FlashMasterOutput? int8u
832 AFAreaMode int8u
834 VRMode int8u

		1
838	BracketSet	int8u
840	BracketProgram	int8u
842	BracketIncrement	int8u
852	HDR	int8u
858	SecondarySlotFunction	int8u
864	HDRLevel	int8u
868	Slot2JpgSize?	int8u
878	SubjectDetection	int8u
880	DynamicAFAreaSize	int8u
884	ToneMap?	int8u
888	PortraitImpressionBalance	int8u
902	HighFrequencyFlickerReduction?	int8u
904	PixelShiftShooting	int8u
906	PixelShiftNumberShots	int8u
908	PixelShiftDelay	int8u~
910	PixelShiftInterval	int8u~
1002	SubjectDetectionAreaMF	int8u
1004	LinkVRToFocusPoint?	int8u
1046	MovieSlowMotion?	int8u
1050	MovieType	int8u
1162	MovieFrameSize?	int8u
1164	MovieFrameRate?	int8u
1255	CustomSettingsZ6III	NikonCustom SettingsZ6III
2300	Language?	int8u
2302	TimeZone	int8u
2308	MonitorBrightness?	int8u
2444	EmptySlotRelease?	int8u
2450	EnergySavingMode?	int8u
2476	USBPowerDelivery?	int8u
2480	SaveFocusPosition?	int8u
2487	SilentPhotography?	int8u
2496	AirplaneMode?	int8u

### Nikon ShotInfoZ7II Tags

These tags are extracted from encrypted data in images from the Z7II.

Index	Tag Name	Writable
0	ShotInfoVersion	no
4	FirmwareVersion	no
48	IntervalOffset	Nikon IntervalInfoZ7II
56	PortraitOffset	Nikon PortraitInfoZ7II
136	OrientationOffset	Nikon OrientationInfo
152	OrientationOffset	Nikon OrientationInfo
160	MenuOffset	Nikon MenuInfoZ7II

## Nikon IntervalInfoZ7II Tags

Index1	Tag Name	Writable
36	IntervalShooting	int16u~
43	TmageArea	int.8u

# Nikon PortraitInfoZ7II Tags

Index1	Tag Name	Writable
160	PortraitImpressionBalance	int8u[2]~

# Nikon MenuInfoZ7II Tags

Index1	Tag Name	Writable
16	MenuSettingsOffsetZ7II	Nikon MenuSettingsZ7II

# Nikon MenuSettingsZ7II Tags

These tags are used by the Z5, Z6, Z7, Z6II, Z7II, Z50, Zfc and Zf.

Index1	Tag Name	Writable
92	ReleaseMode	no
160	IntervalDurationHours	int32u
164	IntervalDurationMinutes	int32u
168	IntervalDurationSeconds	int32u
176	Intervals	int32u
180	ShotsPerInterval	int32u
184	IntervalExposureSmoothing	int8u
186	IntervalPriority	int8u
220	FocusShiftNumberShots	int8u
224	FocusShiftStepWidth	int8u
228	FocusShiftInterval	int8u~
232	FocusShiftExposureLock	int8u
322	DiffractionCompensation	int8u
323	AutoDistortionControl	int8u
326	NikonMeteringMode	int8u
328	FlashControlMode	int8u
334	FlashGNDistance?	no
338	FlashOutput?	int8u
346	FlashWirelessOption?	int8u
348	FlashRemoteControl?	int8u
352	FlashMasterControlMode	int8u
354	FlashMasterCompensation?	int8s
358	FlashMasterOutput?	int8u
502	MovieFrameSize?	int8u
504	MovieFrameRate?	int8u
506	MovieSlowMotion?	int8u
510	MovieType?	int8u
516	MovieISOAutoManualMode?	int16u
568	MovieActiveD-Lighting?	int8u
572	MovieHighISONoiseReduction?	int8u
574	MovieVignetteControl?	int8u
576	MovieVignetteControlSameAsPhoto?	int8u
577	MovieDiffractionCompensation?	int8u
578	MovieAutoDistortionControl?	int8u
584	MovieFocusMode?	int8u
590	MovieVibrationReduction?	int8u
591	MovieVibrationReductionSameAsPhoto?	int8u
858	HDMIOutputN-Log?	int8u

# Nikon ShotInfoZ8 Tags

These tags are extracted from encrypted data in images from the Z8.

Index	Tag Name	Writable
0	ShotInfoVersion	no
4	FirmwareVersion	no
48	SequenceOffset	Nikon SeqInfoZ9
128	AutoCaptureOffset	Nikon AutoCaptureInfo
132	OrientOffset	Nikon OrientationInfo
140	MenuOffset	Nikon MenuInfoZ8

# Nikon SeqInfoZ9 Tags

Index1	Tag Name	Writable
32	FocusShiftShooting	int8u~
40	IntervalShooting	int16u~

# Nikon AutoCaptureInfo Tags

Index1	Tag Name	Writable
0	AutoCapturedFrame	int8u
1	AutoCaptureCriteria	int8u~
55	AutoCaptureRecordingTime	int8u
56	AutoCaptureWaitTime	int8u
74	AutoCaptureDistanceFar	int8u~

78	AutoCaptureDistanceNear	int8u~
95	AutoCaptureCriteriaMotionDirection	int8u~
99	AutoCaptureCriteriaMotionSpeed	int8u
100	AutoCaptureCriteriaMotionSize	int8u
105	AutoCaptureCriteriaSubjectSize	int8u
106	AutoCaptureCriteriaSubjectType	int8u

## Nikon MenuInfoZ8 Tags

Index1	Tag Name	Writable
16	MenuSettingsOffsetZ8v1	Nikon MenuSettingsZ8v1
	MenuSettingsOffsetZ8v2	-
		Nikon MenuSettingsZ8v2

# Nikon MenuSettingsZ8vl Tags

These tags are used by the Z8 firmware 1.00 and 1.10.

Index1	Tag Name	Writable
0	MenuSettingsZ8	Nikon MenuSettingsZ8
943	CustomSettingsZ8	NikonCustom SettingsZ8
1684	TimeZone	int8u
1690	MonitorBrightness?	int8u
1698	Language?	int8u
1712	AFFineTune?	int8u
1716	NonCPULens1FocalLength?	int16u~
1718	NonCPULens2FocalLength?	int16u~
1720	NonCPULens3FocalLength?	int16u~
1722	NonCPULens4FocalLength?	int16u~
1724	NonCPULens5FocalLength?	int16u~
1726	NonCPULens6FocalLength?	int16u~
1728	NonCPULens7FocalLength?	int16u~
1730	NonCPULens8FocalLength?	int16u~
1732	NonCPULens9FocalLength?	int16u~
1734	NonCPULens10FocalLength?	int16u~
1736	NonCPULens11FocalLength?	int16u~
1738	NonCPULens12FocalLength?	int16u~
1740	NonCPULens13FocalLength?	int16u~
1742	NonCPULens14FocalLength?	int16u~
1744	NonCPULens15FocalLength?	int16u~
1746	NonCPULens16FocalLength?	int16u~
1748	NonCPULens17FocalLength?	int16u~
1750	NonCPULens18FocalLength?	int16u~
1752	NonCPULens19FocalLength?	int16u~
1754	NonCPULens20FocalLength?	int16u~
1756	NonCPULens1MaxAperture?	int16u
1758	NonCPULens2MaxAperture?	int16u
1760	NonCPULens3MaxAperture?	int16u
1762	NonCPULens4MaxAperture?	int16u
1764	NonCPULens5MaxAperture?	int16u
1766	NonCPULens6MaxAperture?	int16u
1768	NonCPULens7MaxAperture?	int16u
1770	NonCPULens8MaxAperture?	int16u
1772	NonCPULens9MaxAperture?	int16u
1774	NonCPULens10MaxAperture?	int16u
1776	NonCPULens11MaxAperture?	int16u
1778	NonCPULens12MaxAperture?	int16u
1780	NonCPULens13MaxAperture?	int16u
1782	NonCPULens14MaxAperture?	int16u
1784	NonCPULens15MaxAperture?	int16u
1786	NonCPULens16MaxAperture?	int16u
1788	NonCPULens17MaxAperture?	int16u
1790	NonCPULens18MaxAperture?	int16u
1792	NonCPULens19MaxAperture?	int16u
1794	NonCPULens20MaxAperture?	int16u
1808	HDMIOutputResolution	int8u
1826	AirplaneMode?	int8u
1827	EmptySlotRelease?	int8u

1862	EnergySavingMode?	int8u
1890	USBPowerDelivery?	int8u
1899	SensorShield?	int8u

# Nikon MenuSettingsZ8 Tags

These tags are common to all Z8 firmware versions.

Index1	Tag Name	Writable
72	HighFrameRate	int8u
152	MultipleExposureMode	int8u
154	MultiExposureShots	int8u
184	IntervalDurationHours	int32u
188	IntervalDurationMinutes	int32u
192	IntervalDurationSeconds	int32u
200	Intervals	int32u
204	ShotsPerInterval	int32u
208	IntervalExposureSmoothing	int8u
210	IntervalPriority	int8u
244	FocusShiftNumberShots	int8u int8u
248 252	FocusShiftStepWidth FocusShiftInterval	int8u~
256	FocusShiftExposureLock?	int8u
286	PhotoShootingMenuBank	int8u
288	ExtendedMenuBanks	int8u
324	PhotoShootingMenuBankImageArea	int8u
338	AutoISO	int8u
340	ISOAutoHiLimit?	int16u
342	ISOAutoFlashLimit?	int16u
350	ISOAutoShutterTime	no
432	MovieVignetteControl?	int8u
434	DiffractionCompensation	int8u
436	FlickerReductionShooting	int8u
440	FlashControlMode	int8u
548	AFAreaMode	int8u
550	VRMode	int8u
554	BracketSet	int8u
556 558	BracketProgram BracketIncrement	int8u int8u
556 570	HDR	int8u
576	SecondarySlotFunction	int8u
582	HDRLevel	int8u
586	Slot2JpgSize?	int8u
592	DXCropAlert	int8u
594	SubjectDetection	int8u
596	DynamicAFAreaSize	int8u
618	ToneMap?	int8u
622	PortraitImpressionBalance	int8u
636	HighFrequencyFlickerReduction?	int8u
730	MovieImageArea?	int8u & 0x01
740	MovieType?	int8u
742	MovieISOAutoHiLimit?	int16u
744	MovieISOAutoControlManualMode?	int8u
746	MovieISOAutoManualMode?	int16u
820 822	MovieActiveD-Lighting?	int8u int8u
828	MovieHighISONoiseReduction? MovieFlickerReduction	int8u
830	MovieMeteringMode?	int8u
832	MovieFocusMode?	int8u
834	MovieAFAreaMode	int8u
836	MovieVRMode?	int8u
840	MovieElectronicVR?	int8u
842	MovieSoundRecording?	int8u
844	MicrophoneSensitivity?	int8u
846	MicrophoneAttenuator?	int8u
848	MicrophoneFrequencyResponse?	int8u
850	WindNoiseReduction?	int8u
882	MovieFrameSize?	int8u
884	MovieFrameRate?	int8u

886	MicrophoneJackPower?	int8u
887	MovieDXCropAlert?	int8u
888	MovieSubjectDetection?	int8u
896	MovieHighResZoom?	int8u

# Nikon MenuSettingsZ8v2 Tags

These tags are used by the Z8 firmware 2.00 and 2.10.

Index1	Tag Name	Writable
0	MenuSettingsZ8	Nikon MenuSettingsZ8
943	CustomSettingsZ8	NikonCustom SettingsZ8
1698	Language?	int8u
1700	TimeZone	int8u
1706	MonitorBrightness?	int8u
1728	AFFineTune?	int8u
1732	NonCPULens1FocalLength?	int16u~
1734	NonCPULens2FocalLength?	int16u~
1736	NonCPULens3FocalLength?	int16u~
1738	NonCPULens4FocalLength?	int16u~
1740	NonCPULens5FocalLength?	int16u~
1742	NonCPULens6FocalLength?	int16u~
1744	NonCPULens7FocalLength?	int16u~
1746	NonCPULens8FocalLength?	int16u~
1748	NonCPULens9FocalLength?	int16u~
1750	NonCPULens10FocalLength?	int16u~
1752	NonCPULens11FocalLength?	int16u~
1754	NonCPULens12FocalLength?	int16u~
1756	NonCPULens13FocalLength?	int16u~
1758 1760	NonCPULens14FocalLength?	int16u~ int16u~
1760	NonCPULens15FocalLength?	int16u~
1764	NonCPULens16FocalLength? NonCPULens17FocalLength?	int16u~
1764	NonCPULens18FocalLength?	int16u~
1768	NonCPULens19FocalLength?	int16u~
1770	NonCPULens20FocalLength?	int16u~
1812	NonCPULens1MaxAperture?	int32u~
1816	NonCPULens2MaxAperture?	int32u~
1820	NonCPULens3MaxAperture?	int32u~
1824	HDMIOutputResolution	int8u
1828	NonCPULens5MaxAperture?	int32u~
1832	NonCPULens6MaxAperture?	int32u~
1836	NonCPULens7MaxAperture?	int32u~
1840	NonCPULens8MaxAperture?	int32u~
1842	AirplaneMode?	int8u
1843	EmptySlotRelease?	int8u
1844	NonCPULens9MaxAperture?	int32u~
1848	NonCPULens10MaxAperture?	int32u~
1852	NonCPULens11MaxAperture?	int32u~
1856	NonCPULens12MaxAperture?	int32u~
1860	NonCPULens13MaxAperture?	int32u~
1864	NonCPULens14MaxAperture?	int32u~
1868	NonCPULens15MaxAperture?	int32u~
1872	NonCPULens16MaxAperture?	int32u~
1876 1878	NonCPULens17MaxAperture? EnergySavingMode?	int32u~
1880	NonCPULens18MaxAperture?	int8u int32u~
1884	NonCPULens19MaxAperture?	int32u~
1888	NonCPULens20MaxAperture?	int32u~
1906	USBPowerDelivery?	int8u
1915	SensorShield?	int8u
2046	PixelShiftShooting	int8u
2048	PixelShiftNumberShots	int8u
2050	PixelShiftDelay	int8u
2052	PlaybackButton	int8u
2054	WBButton	int8u
2056	BracketButton	int8u
2058	LensFunc1ButtonPlaybackMode	int8u
2060	LensFunc2ButtonPlaybackMode	int8u

2062	PlaybackButtonPlaybackMode	int8u
2064	BracketButtonPlaybackMode	int8u

# Nikon ShotInfoZ9 Tags

These tags are extracted from encrypted data in images from the Z9.

Index	Tag Name	Writable
0	ShotInfoVersion	no
4	FirmwareVersion	no
48	SequenceOffset	Nikon SeqInfoZ9
88	Offset13	Nikon Offset13InfoZ9
128	AutoCaptureOffset	Nikon AutoCaptureInfo
132	OrientOffset	Nikon OrientationInfo
140	MenuOffset	Nikon MenuInfoZ9

## Nikon Offset13InfoZ9 Tags

Index1	Tag Name	Writable
3048	AFAreaInitialXPosition	int8s~
3049	AFAreaInitialYPosition	int8s~
3050	AFAreaInitialWidth	int8u
3051	AFAreaInitialHeight	int8u

## Nikon MenuInfoZ9 Tags

Index1	Tag Name	Writable
16	MenuSettingsOffsetZ9 MenuSettingsOffsetZ9v3	Nikon MenuSettingsZ9 -
	MenuSettingsOffsetZ9v4	Nikon MenuSettingsZ9v3 -
		Nikon MenuSettingsZ9v4

# Nikon MenuSettingsZ9 Tags

These tags are used by the Z9.

Index1	Tag Name	Writable
140	MultipleExposureMode	int8u
142	MultiExposureShots	int8u
188	Intervals	int32u
192	ShotsPerInterval	int32u
232	FocusShiftNumberShots	int8u
236	FocusShiftStepWidth	int8u
240	FocusShiftInterval	int8u~
244	FocusShiftExposureLock?	int8u
274	PhotoShootingMenuBank	int8u
276	ExtendedMenuBanks	int8u
308	PhotoShootingMenuBankImageArea	int8u
322	AutoISO	int8u
324	ISOAutoHiLimit?	int16u
326	ISOAutoFlashLimit?	int16u
334	ISOAutoShutterTime	no
416	MovieVignetteControl?	int8u
418	DiffractionCompensation	int8u
420	FlickerReductionShooting	int8u
424	FlashControlMode	int8u
426	FlashMasterCompensation?	int8s
430	FlashGNDistance?	no
434	FlashOutput?	int8u
444	FlashRemoteControl?	int8u
456	FlashWirelessOption?	int8u
528	AFAreaMode	int8u
530	VRMode	int8u
534	BracketSet	int8u
536	BracketProgram	int8u

538	BracketIncrement	int8u
556	SecondarySlotFunction	int8u
572	DXCropAlert	int8u
574	SubjectDetection	int8u
576	DynamicAFAreaSize	int8u
604	MovieImageArea?	int8u & 0x01
614	MovieType?	int8u
616	MovieISOAutoHiLimit?	int16u
618	MovieISOAutoControlManualMode?	int8u
620	MovieISOAutoManualMode?	int16u
696	MovieActiveD-Lighting?	int8u
698	MovieHighISONoiseReduction?	int8u
704	MovieFlickerReduction	int8u
706	MovieMeteringMode?	int8u
708	MovieFocusMode?	int8u
710	MovieAFAreaMode	int8u
712	MovieVRMode?	int8u
716	MovieElectronicVR?	int8u
718	MovieSoundRecording?	int8u
720	MicrophoneSensitivity?	int8u
722	MicrophoneAttenuator?	int8u
724	MicrophoneFrequencyResponse?	int8u
726	WindNoiseReduction?	int8u
748	MovieToneMap?	int8u
754	MovieFrameSize?	int8u
756	MovieFrameRate?	int8u
762	MicrophoneJackPower?	int8u
763	MovieDXCropAlert?	int8u
764	MovieSubjectDetection?	int8u
799	CustomSettingsZ9	NikonCustom SettingsZ9
1426	Language?	int8u
1428	TimeZone	int8u
1434	MonitorBrightness?	no
1456	AFFineTune?	int8u
1552	HDMIOutputResolution	int8u
1565	SetClockFromLocationData?	int8u
1572	AirplaneMode?	int8u
1573	EmptySlotRelease?	int8u
1608	EnergySavingMode?	int8u
1632	RecordLocationData?	int8u
1636	USBPowerDelivery?	int8u
1645	SensorShield?	int8u

# Nikon MenuSettingsZ9v3 Tags

These tags are used by the Z9 firmware 3.00.

Index1	Tag Name	Writable
72	HighFrameRate	int8u
154	MultipleExposureMode	int8u
156	MultiExposureShots	int8u
204	Intervals	int32u
208	ShotsPerInterval	int32u
248	FocusShiftNumberShots	int8u
252	FocusShiftStepWidth	int8u
256	FocusShiftInterval	int8u~
260	FocusShiftExposureLock?	int8u
290	PhotoShootingMenuBank	int8u
292	ExtendedMenuBanks	int8u
328	PhotoShootingMenuBankImageArea	int8u
342	AutoISO	int8u
344	ISOAutoHiLimit?	int16u
346	ISOAutoFlashLimit?	int16u
354	ISOAutoShutterTime	no
436	MovieVignetteControl?	int8u
438	DiffractionCompensation	int8u
440	FlickerReductionShooting	int8u
444	FlashControlMode	int8u
446	FlashMasterCompensation?	int8s

450	FlashGNDistance?	no
		no
454	FlashOutput?	int8u
548	AFAreaMode	int8u
550	VRMode	int8u
554	BracketSet	int8u
556	BracketProgram	int8u
558	BracketIncrement	int8u
576	SecondarySlotFunction	int8u
592	DXCropAlert	int8u
594	SubjectDetection	int8u
596	DynamicAFAreaSize	int8u
636	HighFrequencyFlickerReduction?	int8u
646	MovieImageArea?	int8u & 0x01
656	MovieType?	int8u
658	MovieISOAutoHiLimit?	int16u
660	MovieISOAutoControlManualMode?	int8u
662	MovieISOAutoManualMode?	int16u
736	MovieActiveD-Lighting?	int8u
738	MovieHighISONoiseReduction?	int8u
744	MovieFlickerReduction	int8u
746	MovieMeteringMode?	int8u
748	MovieFocusMode?	int8u
750	MovieAFAreaMode	int8u
752	MovieVRMode?	int8u
756	MovieElectronicVR?	int8u
758	MovieSoundRecording?	int8u
760	MicrophoneSensitivity?	int8u
762	MicrophoneAttenuator?	int8u
764	MicrophoneFrequencyResponse?	int8u
766	WindNoiseReduction?	int8u
788	MovieToneMap?	int8u
794	MovieFrameSize?	int8u
796	MovieFrameRate?	int8u
802	MicrophoneJackPower?	int8u
803	MovieDXCropAlert?	int8u
804	MovieSubjectDetection?	int8u
812	MovieHighResZoom?	int8u
847	CustomSettingsZ9	NikonCustom SettingsZ9
1474	Language?	int8u
1476	TimeZone	int8u
1482	MonitorBrightness?	int8u
1504	AFFineTune?	int8u
1600	HDMIOutputResolution	int8u
1613	SetClockFromLocationData?	int8u
	AirplaneMode?	int8u
1620 1621	EmptySlotRelease?	int8u
1656	EnergySavingMode?	int8u
1680 1684	RecordLocationData?	int8u
	USBPowerDelivery?	int8u int8u
1693	SensorShield?	
1754	FocusShiftAutoReset?	int8u
1810	PreReleaseBurstLength	int8u
1812	PostReleaseBurstLength	int8u

# Nikon MenuSettingsZ9v4 Tags

These tags are used by the Z9 firmware 4.00, 4.10, 5.00 and 5.10.

Index1	Tag Name	Writable
72	HighFrameRate	int8u
154	MultipleExposureMode	int8u
156	MultiExposureShots	int8u
204	Intervals	int32u
208	ShotsPerInterval	int32u
248	FocusShiftNumberShots	int8u
252	FocusShiftStepWidth	int8u
256	FocusShiftInterval	int8u~
260	FocusShiftExposureLock?	int8u
290	PhotoShootingMenuBank	int8u

	ExifTool 13.24 Tag Names	
292	ExtendedMenuBanks	int8u
328	PhotoShootingMenuBankImageArea	int8u
342	AutoISO	int8u
344	ISOAutoHiLimit?	int16u
346	ISOAutoFlashLimit?	int16u
354	ISOAutoShutterTime	no
436	MovieVignetteControl?	int8u
438 440	DiffractionCompensation FlickerReductionShooting	int8u int8u
444	FlashControlMode	int8u
446	FlashMasterCompensation?	int8s
450	FlashGNDistance?	no
454	FlashOutput?	int8u
548	AFAreaMode	int8u
550	VRMode	int8u
554	BracketSet	int8u
556	BracketProgram	int8u
558	BracketIncrement	int8u
570	HDR	int8u
576	SecondarySlotFunction	int8u
582	HDRLevel	int8u
586	Slot2JpgSize?	int8u
592 594	DXCropAlert	int8u int8u
59 <del>4</del> 596	SubjectDetection DynamicAFAreaSize	int8u
636	HighFrequencyFlickerReduction?	int8u
646	MovieImageArea?	int8u & 0x01
656	MovieType?	int8u
658	MovieISOAutoHiLimit?	int16u
660	MovieISOAutoControlManualMode?	int8u
662	MovieISOAutoManualMode?	int16u
736	MovieActiveD-Lighting?	int8u
738	MovieHighISONoiseReduction?	int8u
744	MovieFlickerReduction	int8u
746	MovieMeteringMode?	int8u
748	MovieFocusMode?	int8u
750	MovieAFAreaMode	int8u
752 756	MovieVRMode? MovieElectronicVR?	int8u int8u
758	MovieSoundRecording?	int8u
760	MicrophoneSensitivity?	int8u
762	MicrophoneAttenuator?	int8u
764	MicrophoneFrequencyResponse?	int8u
766	WindNoiseReduction?	int8u
788	MovieToneMap?	int8u
794	MovieFrameSize?	int8u
796	MovieFrameRate?	int8u
802	MicrophoneJackPower?	int8u
803	MovieDXCropAlert?	int8u
804	MovieSubjectDetection?	int8u
812	MovieHighResZoom?	int8u
847 1498	CustomSettingsZ9v4 Language?	NikonCustom SettingsZ9v4 int8u
1500	TimeZone	int8u
1506	MonitorBrightness?	int8u
1528	AFFineTune?	int8u
1532	NonCPULens1FocalLength?	int16s~
1536	NonCPULens2FocalLength?	int16s~
1540	NonCPULens3FocalLength?	int16s~
1544	NonCPULens4FocalLength?	int16s~
1548	NonCPULens5FocalLength?	int16s~
1552	NonCPULens6FocalLength?	int16s~
1556	NonCPULens7FocalLength?	int16s~
1560	NonCPULens8FocalLength?	int16s~
1564	NonCPULens9FocalLength?	int16s~
1568	NonCPULens10FocalLength?	int16s~
1572 1576	NonCPULens11FocalLength?	int16s~
1576	NonCPULens12FocalLength? NonCPULens13FocalLength?	int16s~ int16s~
1584	NonCPULens14FocalLength?	int16s~

	_	
1588	NonCPULens15FocalLength?	int16s~
1592	NonCPULens16FocalLength?	int16s~
1596	NonCPULens17FocalLength?	int16s~
1600	NonCPULens18FocalLength?	int16s~
1604	NonCPULens19FocalLength?	int16s~
1608	NonCPULens20FocalLength?	int16s~
1612	NonCPULens1MaxAperture?	int16s~
1616	NonCPULens2MaxAperture?	int16s~
1620	NonCPULens3MaxAperture?	int16s~
1624	NonCPULens4MaxAperture?	int16s~
1628	NonCPULens5MaxAperture?	int16s~
1632	NonCPULens6MaxAperture?	int16s~
1636	NonCPULens7MaxAperture?	int16s~
1640	NonCPULens8MaxAperture?	int16s~
1644	NonCPULens9MaxAperture?	int16s~
1648	NonCPULens10MaxAperture?	int16s~
1652	NonCPULens11MaxAperture?	int16s~
1656	NonCPULens12MaxAperture?	int16s~
1660	NonCPULens13MaxAperture?	int16s~
1664	NonCPULens14MaxAperture?	int16s~
1668	NonCPULens15MaxAperture?	int16s~
1672	NonCPULens16MaxAperture?	int16s~
1676	NonCPULens17MaxAperture?	int16s~
1680	NonCPULens18MaxAperture?	int16s~
1684	NonCPULens19MaxAperture?	int16s~
1688	NonCPULens20MaxAperture?	int16s~
1704	HDMIOutputResolution	int8u
1717	SetClockFromLocationData?	int8u
1724	AirplaneMode?	int8u
1725	EmptySlotRelease?	int8u
1760	EnergySavingMode?	int8u
1784	RecordLocationData?	int8u
1788	USBPowerDelivery?	int8u
1797	SensorShield?	int8u
1862	AutoCapturePreset	int8u
1864	<u>-</u>	int8u
1922	FocusShiftAutoReset?	
1922	PreReleaseBurstLength	int8u
	PostReleaseBurstLength	int8u
1938	VerticalISOButton	int8u
1940	ExposureCompensationButton	int8u
1942	ISOButton	int8u
2002	ViewModeShowEffectsOfSettings?	int8u
2004	DispButton	int8u
2048	ExposureDelay	fixed32u~
2052	CommandDialFrameAdvanceZoom?	int8u
2054	SubCommandDialFrameAdvanceZoom?	int8u
2056	PlaybackButton	int8u
2058	WBButton	int8u
2060	BracketButton	int8u
2062	FlashModeButton	int8u
2064	LensFunc1ButtonPlaybackMode	int8u
2066	LensFunc2ButtonPlaybackMode	int8u
2068	PlaybackButtonPlaybackMode	int8u
2070	BracketButtonPlaybackMode	int8u
2072	FlashModeButtonPlaybackMode	int8u

# Nikon ShotInfo Tags

This information is encrypted for  $ShotInfoVersion\ 02xx$ , and some tags are only valid for specific models.

Index1	Tag Name	Writable
0	ShotInfoVersion	no
4	FirmwareVersion	no
16	DistortionControl	int8u
102	VR_0x66?	int8u
106	ShutterCount	int32u
110	DeletedImageCount	int32u
117	VibrationReduction	int8u

130	VibrationReduction	int8u
343	ShutterCount	undef[2]
430	VibrationReduction	int8u
589	ShutterCount	int32u

### Nikon ColorBalancel Tags

Index2	Tag Name	Writable
0	WB_RBGGLevels	int16u[4]!

# Nikon ColorBalance2 Tags

This information is encrypted for most camera models.

Index2	Tag Name	Writable
0	WB RGGBLevels	int16u[4]!

### Nikon ColorBalance3 Tags

Index2	Tag Name	Writable
0	WB_RGBGLevels	int16u[4]!

## Nikon ColorBalance4 Tags

Index2	Tag Name	Writable
0	WB GRBGLevels	int16u[4]!

#### Nikon ColorBalanceUnknown Tags

Index1	Tag Name	Writable
0	ColorBalanceVersion	undef[4]

# Nikon ColorBalanceUnknown2 Tags

Index2	Tag Name	Writable
0	ColorBalanceVersion	undef[4]

### Nikon LensData00 Tags

This structure is used by the D100, and D1X with firmware version 1.1.

Index1	Tag Name	Writable
0	LensDataVersion	no
6	LensIDNumber	int8u
7	LensFStops	int8u
8	MinFocalLength	int8u
9	MaxFocalLength	int8u
10	MaxApertureAtMinFocal	int8u
11	MaxApertureAtMaxFocal	int8u
12	MCUVersion	int8u

#### Nikon LensData01 Tags

Nikon encrypts the LensData information below if LensDataVersion is 0201 or higher, but the decryption algorithm is known so the information can be extracted.

Index1	Tag Name	Writable
0	LensDataVersion	no
4	ExitPupilPosition	int8u
5	AFAperture	int8u
8	FocusPosition	int8u

9 10	FocusDistance FocalLength	int8u int8u
11	LensIDNumber	int8u
12	LensFStops	int8u
13	MinFocalLength	int8u
14	MaxFocalLength	int8u
15	MaxApertureAtMinFocal	int8u
16	MaxApertureAtMinFocal MaxApertureAtMaxFocal	int8u
17	MCUVersion	int8u
18	EffectiveMaxAperture	int8u

#### Nikon LensData0204 Tags

Nikon encrypts the LensData information below if LensDataVersion is 0201 or higher, but the decryption algorithm is known so the information can be extracted.

Index1	Tag Name	Writable
0	LensDataVersion	no
4	ExitPupilPosition	int8u
5	AFAperture	int8u
8	FocusPosition	int8u
10	FocusDistance	int8u
11	FocalLength	int8u
12	LensIDNumber	int8u
13	LensFStops	int8u
14	MinFocalLength	int8u
15	MaxFocalLength	int8u
16	MaxApertureAtMinFocal	int8u
17	MaxApertureAtMaxFocal	int8u
18	MCUVersion	int8u
19	EffectiveMaxAperture	int8u

### Nikon LensData0400 Tags

Tags extracted from the encrypted lens data of the Nikon 1J1/1V1/1J2.

Index1	Tag Name	Writable
0	LensDataVersion	no
394	LensModel	string[64]

### Nikon LensData0402 Tags

Tags extracted from the encrypted lens data of the Nikon 1J3/1S1/1V2.

Index1	Tag Name	Writable
0	LensDataVersion	no
395	LensModel	string[64]

### Nikon LensData0403 Tags

Tags extracted from the encrypted lens data of the Nikon 1J4/1J5.

Index1	Tag Name	Writable
0	LensDataVersion	no
684	LensModel	string[64]

#### Nikon LensData0800 Tags

Tags found in the encrypted LensData from cameras such as the  ${\tt Z6}$  and  ${\tt Z7}$ .

Index1	Tag Name	Writable
0	LensDataVersion	no
4	ExitPupilPosition	int8u

5	AFAperture	int8u
11	FocusDistance	int8u
12	FocalLength	int8u
13	LensIDNumber	int8u
14	LensFStops	int8u
15	MinFocalLength	int8u
16	MaxFocalLength	int8u
17	MaxApertureAtMinFocal	int8u
18	MaxApertureAtMaxFocal	int8u
19	MCUVersion	int8u
20	EffectiveMaxAperture	int8u
47	NewLensData	undef[17]
48	LensID	int16u
52	LensFirmwareVersion	int16u~
54	MaxAperture	int16u
56	FNumber	int16u
60	FocalLength	int16u
76	FocusDistanceRangeWidth?	int8u
78	FocusDistance	int16u~
86	LensDriveEnd?	int8u
88	FocusStepsFromInfinity?	int8u
90	LensPositionAbsolute	int32s
95	LensMountType	int8u & 0x01

### Nikon LensDataUnknown Tags

Index1	Tag Name	Writable
Ο	LensDataVersion	no

## Nikon FlashInfo0100 Tags

These tags are used by the D2H, D2Hs, D2X, D2Xs, D50, D70, D70s, D80 and D200.

Index1	Tag Name	Writable
0	FlashInfoVersion	no
4	FlashSource	int8u
6	ExternalFlashFirmware	int8u[2]
8	ExternalFlashFlags	int8u
9.1	FlashCommanderMode	int8u & 0x80
9.2	FlashControlMode	int8u & 0x7f
10	FlashOutput	int8u
	FlashCompensation	int8s
11	FlashFocalLength	int8u
12	RepeatingFlashRate	int8u
13	RepeatingFlashCount	int8u
14	FlashGNDistance	int8u
15	FlashGroupAControlMode	int8u & 0x0f
16	FlashGroupBControlMode	int8u & 0x0f
17	FlashGroupAOutput	int8u
	FlashGroupACompensation	int8s
18	FlashGroupBOutput	int8u
	FlashGroupBCompensation	int8s

## Nikon FlashInfo0102 Tags

These tags are used by the D3 (firmware 1.x), D40, D40X, D60 and D300 (firmware 1.00).

Index1	Tag Name	Writable
0	FlashInfoVersion	no
4	FlashSource	int8u
6	ExternalFlashFirmware	int8u[2]
8	ExternalFlashFlags	int8u
9.1	FlashCommanderMode	int8u & 0x80
9.2	FlashControlMode	int8u & 0x7f
10	FlashOutput	int8u

	FlashCompensation	int8s
12	FlashFocalLength	int8u
13	RepeatingFlashRate	int8u
14	RepeatingFlashCount	int8u
15	FlashGNDistance	int8u
16.1	FlashGroupAControlMode	int8u & 0x0f
17.1	FlashGroupBControlMode	int8u & 0xf0
17.2	FlashGroupCControlMode	int8u & 0x0f
18	FlashGroupAOutput	int8u
	FlashGroupACompensation	int8s
19	FlashGroupBOutput	int8u
	FlashGroupBCompensation	int8s
20	FlashGroupCOutput	int8u
	FlashGroupCCompensation	int8s

## Nikon FlashInfo0103 Tags

These tags are used by the D3 (firmware 2.x), D3X, D3S, D4, D90, D300 (firmware 1.10), D300S, D600, D700, D800, D3000, D3100, D3200, D5000, D5100, D5200, D7000.

Index1	Tag Name	Writable
0	FlashInfoVersion	no
4	FlashSource	int8u
6	ExternalFlashFirmware	int8u[2]
8	ExternalFlashFlags	int8u
9.1	FlashCommanderMode	int8u & 0x80
9.2	FlashControlMode	int8u & 0x7f
10	FlashOutput	int8u
	FlashCompensation	int8s
12	FlashFocalLength	int8u
13	RepeatingFlashRate	int8u
14	RepeatingFlashCount	int8u
15	FlashGNDistance	int8u
16	FlashColorFilter	int8u
17.1	FlashGroupAControlMode	int8u & 0x0f
18.1	FlashGroupBControlMode	int8u & 0xf0
18.2	FlashGroupCControlMode	int8u & 0x0f
19	FlashGroupAOutput	int8u
	FlashGroupACompensation	int8s
20	FlashGroupBOutput	int8u
	FlashGroupBCompensation	int8s
21	FlashGroupCOutput	int8u
	FlashGroupCCompensation	int8s
27	ExternalFlashCompensation	int8s
29	FlashExposureComp3	int8s
39	FlashExposureComp4	int8s

## Nikon FlashInfo0106 Tags

These tags are used by the Df, D610, D3300, D5300, D7100 and Coolpix A.

Index1	Tag Name	Writable
0	FlashInfoVersion	no
4	FlashSource	int8u
6	ExternalFlashFirmware	int8u[2]
8	ExternalFlashFlags	int8u
9.1	FlashCommanderMode	int8u & 0x80
9.2	FlashControlMode	int8u & 0x7f
12	FlashFocalLength	int8u
13	RepeatingFlashRate	int8u
14	RepeatingFlashCount	int8u
15	FlashGNDistance	int8u
16	FlashColorFilter	int8u
17.1	FlashGroupAControlMode	int8u & 0x0f
18.1	FlashGroupBControlMode	int8u & 0xf0
18.2	FlashGroupCControlMode	int8u & 0x0f
39	FlashOutput	int8u

	FlashCompensation	int8s
40	FlashGroupAOutput	int8u
	FlashGroupACompensation	int8s
41	FlashGroupBOutput	int8u
	FlashGroupBCompensation	int8s
42	FlashGroupCOutput	int8u
	FlashGroupCCompensation	int8s

### Nikon FlashInfo0107 Tags

These tags are used by the D4S, D750, D810, D5500, D7200 (FlashInfoVersion 0107) and the D5, D500, D850 and D3400 (FlashInfoVersion 0108).

Index1	Tag Name	Writable
0	FlashInfoVersion	no
4	FlashSource	int8u
6	ExternalFlashFirmware	int8u[2]
8.1	ExternalFlashZoomOverride	int8u & 0x80
8.2	ExternalFlashStatus	int8u & 0x01
9.1	ExternalFlashReadyState	int8u & 0x07
10	FlashCompensation	int8s
12	FlashFocalLength	int8u
13	RepeatingFlashRate	int8u
14	RepeatingFlashCount	int8u
15	FlashGNDistance	int8u
17.1	FlashGroupAControlMode	int8u & 0x0f
18.1	FlashGroupBControlMode	int8u & 0xf0
18.2	FlashGroupCControlMode	int8u & 0x0f
40	FlashGroupAOutput	int8u
	FlashGroupACompensation	int8s
41	FlashGroupBOutput	int8u
	FlashGroupBCompensation	int8s
42	FlashGroupCOutput	int8u
	FlashGroupCCompensation	int8s

# Nikon FlashInfo0300 Tags

Index1	Tag Name	Writable
0	FlashInfoVersion	no
4	FlashSource	int8u
6	ExternalFlashFirmware	int8u[2]
8	ExternalFlashFlags	int8u
9.1	FlashCommanderMode	int8u & 0x80
9.2	FlashControlMode	int8u & 0x7f
10	FlashCompensation	int8s
13	RepeatingFlashRate	int8u
14	RepeatingFlashCount	int8u
15	FlashGNDistance	int8u
16	FlashColorFilter	int8u
17.1	FlashGroupAControlMode	int8u & 0x0f
18.1	FlashGroupBControlMode	int8u & 0xf0
18.2	FlashGroupCControlMode	int8u & 0x0f
33	FlashOutput	int8u
37	FlashIlluminationPattern	int8u
38	FlashFocalLength	int8u
40	FlashGroupAOutput	int8u
	FlashGroupACompensation	int8s
41	FlashGroupBOutput	int8u
	FlashGroupBCompensation	int8s
42	FlashGroupCOutput	int8u
	FlashGroupCCompensation	int8s

# Nikon FlashInfoUnknown Tags

Index1	Tag Name	Writable
0	FlashInfoVersion	no

# Nikon MultiExposure Tags

Index4	Tag Name	Writable
0	MultiExposureVersion	no
1	MultiExposureMode	int32u
2	MultiExposureShots	int32u
3	MultiExposureAutoGain	int32u

## Nikon MultiExposure2 Tags

Index4	Tag Name	Writable
0	MultiExposureVersion	no
1	MultiExposureMode	int32u
2	MultiExposureShots	int32u
3	MultiExposureOverlayMode	int32u

### Nikon AFInfo2V0100 Tags

AF information for Nikon cameras with LiveView that were introduced 2007 thru 2015 (and the D5600 in 2016), including D3, D4, D3000, D3100-D3300, D5000-D5600, D6x0, D7000, D7000, D7100, D810

Index1	Tag Name	Writable
0	AFInfo2Version	no
4	AFDetectionMethod	int8u
5	AFAreaMode	int8u
7	PrimaryAFPoint	int8u
8	AFPointsUsed	undef[7]
	AFPointsUsed	undef[2]
	AFPointsUsed	undef[5]
	AFPointsUsed	int8u
16	AFImageWidth	int16u
18	AFImageHeight	int16u
20	AFAreaXPosition	int16u
22	AFAreaYPosition	int16u
24	AFAreaWidth	int16u
26	AFAreaHeight	int16u
28	ContrastDetectAFInFocus	int8u
	AFPointsSelected	undef[20]

#### Nikon AFInfo2V0101 Tags

AF information for Nikon cameras D5, D500, D850, D3400, D3500 and D7500  $\,$ 

Index1	Tag Name	Writable
0	AFInfo2Version	no
4	AFDetectionMethod	int8u
5	AFAreaMode	int8u
8	AFPointsUsed	undef[7]
	AFPointsUsed	undef[2]
	AFPointsUsed	undef[20]
	AFPointsUsed	int8u
28	ContrastDetectAFInFocus	int8u
	AFPointsUsed	undef[7]
	AFPointsSelected	undef[20]
48	AFPointsInFocus	undef[7]
	AFPointsInFocus	undef[20]
68	PrimaryAFPoint	int8u
70	AFImageWidth	int16u
72	AFImageHeight	int16u
74	AFAreaXPosition	int16u
76	AFAreaYPosition	int16u
78	AFAreaWidth	int16u
80	AFAreaHeight	int16u
82	ContrastDetectAFInFocus	int8u

## Nikon AFInfo2V0200 Tags

AF information for Nikon 1 series cameras: Nikon 1 V1, V2, V3, J1, J2, J3, S1, S2 AW1.

Index1	Tag Name	Writable
0	AFInfo2Version	no
5	AFAreaMode	int8u
6	PhaseDetectAF	int8u
7	PrimaryAFPoint	int8u
8	AFPointsUsed	undef[17]
	AFPointsUsed	undef[21]
	AFPointsUsed	undef[29]

## Nikon AFInfo2V0300 Tags

AF information for Nikon cameras with the Expeed 6 processor: D6, D780, Z5, Z6, Z6ii, Z7, Z7ii, Z50 and Zfc.

Index1	Tag Name	Writable
0	AFInfo2Version	no
4	AFDetectionMethod	int8u
5	AFAreaMode	int8u
7	AFCoordinatesAvailable	int8u
10	AFPointsUsed	undef[7]
	AFPointsUsed	undef[11]
	AFPointsUsed	undef[14]
42	AFImageWidth	int16u
44	AFImageHeight	int16u
46	AFAreaXPosition	int16u
47	FocusPositionHorizontal	no
48	AFAreaYPosition	int16u
49	FocusPositionVertical	no
50	AFAreaWidth	int16u
52	AFAreaHeight	int16u
56	PrimaryAFPoint	int8u

# Nikon AFInfo2V0400 Tags

AF information for Nikon cameras with the Expeed 7 processor: The Zf,  $Z6\_3$ , Z8, Z9 and  $Z50\_3$ .

Index1	Tag Name	Writable
0	AFInfo2Version	no
4	AFDetectionMethod	int8u
5	AFAreaMode	int8u
7	AFCoordinatesAvailable	int8u
10	AFPointsUsed	undef[51]
	AFPointsUsed	undef[38]
	AFPointsUsed	undef[29]
62	AFImageWidth	int16u
64	AFImageHeight	int16u
66	AFAreaXPosition	int16u
67	FocusPositionHorizontal	no
68	AFAreaYPosition	int16u
69	FocusPositionVertical	no
70	AFAreaWidth	int16u
72	AFAreaHeight	int16u
74	FocusResult	int8u

## Nikon FileInfo Tags

Tag Name	Writable
FileInfoVersion	no
MemoryCardNumber	int16u
	 FileInfoVersion

3	DirectoryNumber	int16u
4	FileNumber	int16u

# Nikon AFTune Tags

Index1	Tag Name	Writable
0	AFFineTune	int8u
1	AFFineTuneIndex	int8u
2	AFFineTuneAdj	int8s
3	AFFineTuneAdjTele	int8s

### Nikon RetouchInfo Tags

Index1	Tag Name	Writable
0	RetouchInfoVersion	no
5	RetouchNEFProcessing	int8s

### Nikon BarometerInfo Tags

Index1	Tag Name	Writable
0	BarometerInfoVersion	no
6	Altitude	int32s

## Nikon CaptureOffsets Tags

Tag ID	Tag Name	Writable
$0 \times 0001$	IFD0_Offset	no
$0 \times 0002$	PreviewIFD_Offset	no
$0 \times 0003$	SubIFD_Offset	no

# Nikon Scan Tags

This information is written by the Nikon Scan software.

Tag ID	Tag Name	Writable
0x0002	FilmType	string
$0 \times 0040$	MultiSample	string
$0 \times 0041$	BitDepth	int16u
$0 \times 0050$	MasterGain	rational64s
0x0051	ColorGain	rational64s[3]
0x0060	ScanImageEnhancer	int32u
$0 \times 0100$	DigitalICE	string
0x0110	ROCInfo	Nikon ROC
0x0120	GEMInfo	Nikon GEM
0x0200	DigitalDEEShadowAdj	int32u
0x0201	DigitalDEEThreshold	int32u
0x0202	DigitalDEEHighlightAdj	int32u

# Nikon ROC Tags

Index4	Tag Name	Writable
0	DigitalROC	int32u

## Nikon GEM Tags

Index4	Tag Name	Writable
0	DigitalGEM	int32u

# Nikon CaptureOutput Tags

Index4	Tag Name	Writable
2	OutputImageWidth	int32u

3	OutputImageHeight	int32u
4	OutputResolution	int32u

### Nikon Type2 Tags

Tag ID	Tag Name	Writable
0x0003	Quality	yes
$0 \times 0 0 0 4$	ColorMode	yes
$0 \times 0005$	ImageAdjustment	yes
$0 \times 0006$	CCDSensitivity	yes
$0 \times 0007$	WhiteBalance	yes
8000x0	Focus	yes
0x000a	DigitalZoom	yes
0x000b	Converter	yes

## Nikon NEFInfo Tags

As-yet unknown information found in SubIFD1 tag 0xc7d5 of NEF images from cameras such as the Z6 and Z7, and NRW images from some Coolpix cameras.

Tag ID	Tag Name	Writable
	DistortionInfo VignetteInfo	Nikon DistortionInfo Nikon VignetteInfo

### Nikon DistortionInfo Tags

Index1	Tag Name	Writable
0	DistortionCorrectionVersion	string[4]
4	DistortionCorrection	int8u
20	RadialDistortionCoefficient1	rational64s~
28	RadialDistortionCoefficient2	rational64s~
36	RadialDistortionCoefficient3	rational64s~

# Nikon VignetteInfo Tags

Index1	Tag Name	Writable
0	VignetteCorrectionVersion	string[4]
36	VignetteCoefficient1	rational64s~
52	VignetteCoefficient2	rational64s~
68	VignetteCoefficient3	rational64s~

### Nikon AVI Tags

Nikon-specific RIFF tags found in AVI videos.

Tag ID	Tag Name	Writable
'nctg'	NikonTags	Nikon AVITags
'ncth'	ThumbnailImage	no
'ncvr'	NikonVers	Nikon AVIVers
'ncvw'	PreviewImage	no

### Nikon AVITags Tags

These tags and the AVIVer tags below are found in proprietary-format records of Nikon AVI videos.

Tag ID	Tag Name	Writable
0x0003	Make	no
$0 \times 0004$	Model	no
0x0005	Software	no
0x0006	Equipment	no
$0 \times 0007$	Orientation	no
8000x0	ExposureTime	no

$0 \times 0009$	FNumber	no
0x000a	ExposureCompensation	no
0x000b	MaxApertureValue	no
0x000c	MeteringMode	no
0x000f	FocalLength	no
$0 \times 0010$	XResolution	no
$0 \times 0011$	YResolution	no
$0 \times 0012$	ResolutionUnit	no
$0 \times 0013$	DateTimeOriginal	no
$0 \times 0014$	CreateDate	no
$0 \times 0016$	Duration	no
0x0018	FocusMode	no
0x001b	DigitalZoom	no
0x001d	ColorMode	no
0x001e	Sharpness	no
0x001f	WhiteBalance	no
$0 \times 0020$	NoiseReduction	no

### Nikon AVIVers Tags

Tag ID	Tag Name	Writable
0x0001	MakerNoteType	no
$0 \times 0002$	MakerNoteVersion	no

# Nikon NCDT Tags

Nikon-specific QuickTime tags found in the NCDT atom of MOV videos from various Nikon models.

Tag ID	Tag Name	Writable
'NCDB'	NikonNCDB	Nikon NCDB
'NCHD'	MakerNoteVersion	no
'NCM1'	PreviewImage1	no
'NCM2'	PreviewImage2	no
'NCTG'	NikonTags	Nikon NCTG
'NCTH'	ThumbnailImage	no
'NCVW'	PreviewImage	no

# Nikon NCDB Tags

Tag ID	Tag Name	Writable
[no tags	known]	

## Nikon NCTG Tags

These tags are found in proprietary-format records of the NCTG atom in  $\mbox{MOV}$  videos from some Nikon cameras.

Tag ID	Tag Name	Writable
0x0001	Make	no
0x0002	Model	no
0x0003	Software	no
$0 \times 0011$	CreateDate	no
0x0012	DateTimeOriginal	no
$0 \times 0013$	FrameCount	no
$0 \times 0016$	FrameRate	no
0x0019	TimeZone	no
0x0022	FrameWidth	no
0x0023	FrameHeight	no
0x0032	AudioChannels	no
0x0033	AudioBitsPerSample	no
$0 \times 0034$	AudioSampleRate	no
0x1002	NikonDateTime	no
0x1013	ElectronicVR	no
0x110829a	ExposureTime	no
0x110829d	FNumber	no

	EXILIOOI 13.24	rag Names	
0x1108822	ExposureProgram		no
0x1109204	ExposureCompensation		no
0x1109207	MeteringMode		no
0x110920a	FocalLength		no
0x110a431	SerialNumber		no
0x110a432	LensInfo		no
0x110a433	LensMake		no
0x110a434	LensModel		no
0x110a435	LensSerialNumber		no
0x1200000	GPSVersionID		no
0x1200001	GPSLatitudeRef		no
0x1200002	GPSLatitude		no
0x1200003	GPSLongitudeRef		no
0x1200004	GPSLongitude		no
0x1200005	GPSAltitudeRef		no
0x1200006	GPSAltitude		no
0x1200007	GPSTimeStamp		no
0x1200008	GPSSatellites		no
0x1200010	GPSImgDirectionRef		no
0x1200011	GPSImgDirection		no
0x1200012	GPSMapDatum		no
0x120001d	GPSDateStamp		no
0x2000001	MakerNoteVersion		no
0x2000005	WhiteBalance		no
0x2000007	FocusMode		no
0x200000b	WhiteBalanceFineTune		no
0x200001b	CropHiSpeed		no
0x200001e	ColorSpace		no
0x200001f	VRInfo		Nikon VRInfo
0x2000022	ActiveD-Lighting		no
0x2000023	PictureControlData		Nikon PictureControl
			Nikon PictureControl2
			Nikon PictureControl3
			Nikon PictureControlUnknown
0x2000024	WorldTime		Nikon WorldTime
$0 \times 2000025$	ISOInfo		Nikon ISOInfo
0x200002a	VignetteControl		no
0x200002c	UnknownInfo		Nikon UnknownInfo
0x2000032	UnknownInfo2		Nikon UnknownInfo2
0x2000039	LocationInfo		Nikon LocationInfo
0x200003f	WhiteBalanceFineTune		no
0x200004e	NikonSettings		NikonSettings
0x2000083	LensType		no
0x2000084	Lens		no
0x2000087	FlashMode		no
0x2000098	LensData0100		Nikon LensData00
	LensData0101		Nikon LensData01
	LensData0201		Nikon LensData01
	LensData0204		Nikon LensData0204
	LensData0400		Nikon LensData0400
	LensData0402		Nikon LensData0402
	LensData0403		Nikon LensData0403
	LensData0800		Nikon LensData0800
	LensDataUnknown		Nikon LensDataUnknown
0x20000a7	ShutterCount		no
0x20000a8	FlashInfo0100		Nikon FlashInfo0100
0112000000	FlashInfo0102		Nikon FlashInfo0102
	FlashInfo0103		Nikon FlashInfo0103
	FlashInfo0106		Nikon FlashInfo0106
	FlashInfo0107		Nikon FlashInfo0107
	FlashInfoUnknown		Nikon FlashInfoUnknown
0x20000ab	VariProgram		no
0x20000b1	HighISONoiseReduction		no
0x20000b1	AFInfo2		Nikon AFInfo2V0100
			Nikon AFInfo2V0101
			Nikon AFInfo2V0200
			Nikon AFInfo2V0300
			Nikon AFInfo2V0400
0x20000c3	BarometerInfo		Nikon BarometerInfo

## Nikon MOV Tags

This information is found in MOV and QT videos from some Nikon cameras.

Index1	Tag Name	Writable
0	Make	no
24	Model	no
38	ExposureTime	no
42	FNumber	no
50	ExposureCompensation	no
68	WhiteBalance	no
72	FocalLength	no
175	Software	no
223	ISO	no

## NikonCapture Tags

This information is written by the Nikon Capture software in tag 0x0e01 of the maker notes of NEF images.

Tag ID	Tag Name	Writable
0x8ae85e	LCHEditor	int8u
0x83a1a25	HistogramXML	undef
0xc89224b	ColorAberrationControl	int8u
0x116fea21	HighlightData	NikonCapture HighlightData
0x2175eb78	D-LightingHQ	int8u
0x2fc08431	StraightenAngle	double
0x374233e0	CropData	NikonCapture CropData
0x39c456ac	PictureCtrl	NikonCapture PictureCtrl
0x3cfc73c6	RedEyeData	NikonCapture RedEyeData
0x3d136244	EditVersionName	string
0x416391c6	QuickFix	int8u
0x56a54260	Exposure	NikonCapture Exposure
0x5f0e7d23	ColorBooster	int8u
0x6a6e36b6	D-LightingHQSelected	int8u
0x753dcbc0	NoiseReduction	int8u
0x76a43200	UnsharpMask	int8u
0x76a43201	Curves	int8u
0x76a43202	ColorBalanceAdj	int8u
0x76a43203	AdvancedRaw	int8u
0x76a43204	WhiteBalanceAdj	int8u
0x76a43205	VignetteControl	int8u
0x76a43206	FlipHorizontal	int8u
0x76a43207	Rotation	int16u
0x84589434	BrightnessData	NikonCapture Brightness
0x890ff591	D-LightingHQData	NikonCapture DLightingHQ
0x926f13e0	NoiseReductionData	NikonCapture NoiseReduction
0x9ef5f6e0	IPTCData	IPTC
0xab5eca5e	PhotoEffects	int8u
0xac6bd5c0	VignetteControlIntensity	int16s
0xb0384e1e	PhotoEffectsData	NikonCapture PhotoEffects
0xb999a36f	ColorBoostData	NikonCapture ColorBoost
0xbf3c6c20	WBAdjData	NikonCapture WBAdjData
0xce5554aa	D-LightingHS	int8u
0xe2173c47	PictureControl	int8u
0xe37b4337	D-LightingHSData	NikonCapture DLightingHS
0xe42b5161	UnsharpData	NikonCapture UnsharpData
0xe9651831	PhotoEffectHistoryXML	undef
0xfe28a44f	AutoRedEye	int8u
0xfe443a45	ImageDustOff	int8u

## NikonCapture HighlightData Tags

Index1	Tag Name	Writable
0	ShadowProtection	int8s
1	SaturationAdj	int8s
6	HighlightProtection	int8s

## NikonCapture CropData Tags

Index1	Tag Name	Writable
30	CropLeft	double
38	CropTop	double
46	CropRight	double
54	CropBottom	double
142	CropOutputWidthInches	double
150	CropOutputHeightInches	double
158	CropScaledResolution	double
174	CropSourceResolution	double
182	CropOutputResolution	double
190	CropOutputScale	double
198	CropOutputWidth	double
206	CropOutputHeight	double
214	CropOutputPixels	double

## NikonCapture PictureCtrl Tags

Index1	Tag Name	Writable
0	PictureControlActive	int8u
19	PictureControlMode	string[16]
42	QuickAdjust	int8u
43	SharpeningAdj	int8u
44	ContrastAdj	int8u
45	BrightnessAdj	int8u
46	SaturationAdj	int8u
47	HueAdj	int8u

### NikonCapture RedEyeData Tags

Index1	Tag Name	Writable
0	RedEyeCorrection	int8u

# NikonCapture Exposure Tags

Index1	Tag Name	Writable
0	ExposureAdj	int16s
18	ExposureAdj2	double
36	ActiveD-Lighting	int8u
37	ActiveD-LightingMode	int8u

# NikonCapture Brightness Tags

Index1	Tag Name	Writable
0	BrightnessAdj	double
8	EnhanceDarkTones	int8u

# NikonCapture DLightingHQ Tags

	Writable
HQShadow	int32u
HQHighlight	int32u
HQColorBoost	int32u
	~ IQHighlight

## NikonCapture NoiseReduction Tags

Index1	Tag Name	Writable
4	EdgeNoiseReduction	int8u
5	ColorMoireReductionMode	int8u
9	NoiseReductionIntensity	int32u
13	NoiseReductionSharpness	int32u
17	NoiseReductionMethod	int16u

21	ColorMoireReduction	int8u
23	NoiseReduction	int8u
24	ColorNoiseReductionIntensity	int32u
28	ColorNoiseReductionSharpness	int32u

### NikonCapture PhotoEffects Tags

Tag Name	Writable
PhotoEffectsType	int8u
PhotoEffectsRed	int16s
PhotoEffectsGreen	int16s
PhotoEffectsBlue	int16s
	PhotoEffectsRed PhotoEffectsGreen

### NikonCapture ColorBoost Tags

Index1	Tag Name	Writable
0	ColorBoostType	int8u
1	ColorBoostLevel	int32u

#### NikonCapture WBAdjData Tags

Index1	Tag Name	Writable
0	WBAdjRedBalance	double
8	WBAdjBlueBalance	double
16	WBAdjMode	int8u
20	WBAdjLighting	int16u
24	WBAdjTemperature	int16u
37	WBAdjTint	int32s

#### NikonCapture DLightingHS Tags

Index4	Tag Name	Writable
0	D-LightingHSAdjustment	int32u
1	D-LightingHSColorBoost	int32u

### NikonCapture UnsharpData Tags

Index1	Tag Name	Writable
0	UnsharpCount	int8u
19	Unsharp1Color	int16u
23	Unsharp1Intensity	int16u
25	Unsharp1HaloWidth	int16u
27	Unsharp1Threshold	int8u
46	Unsharp2Color	int16u
50	Unsharp2Intensity	int16u
52	Unsharp2HaloWidth	int16u
54	Unsharp2Threshold	int8u
73	Unsharp3Color	int16u
77	Unsharp3Intensity	int16u
79	Unsharp3HaloWidth	int16u
81	Unsharp3Threshold	int8u
100	Unsharp4Color	int16u
104	Unsharp4Intensity	int16u
106	Unsharp4HaloWidth	int16u
108	Unsharp4Threshold	int8u

#### NikonCustom Tags

Unfortunately, the NikonCustom settings are stored in a binary data block which changes from model to model. This means that significant effort must be spent in decoding these for each model, usually requiring hundreds of test images from a dedicated Nikon owner. For this reason, the NikonCustom settings have not been decoded for all models. The tables below list the custom settings for the currently supported models.

# NikonCustom SettingsD40 Tags

Custom settings for the Nikon D40.

Index1	dex1 Tag Name Writa	
0.1	Beep	int8u & 0x80
0.2	AFAssist	int8u & 0x40
0.3	NoMemoryCard	int8u & 0x20
0.4	ImageReview	int8u & 0x10
1.1	AutoISO	int8u & 0x80
1.2	AutoISOMax	int8u & 0x30
1.3	AutoISOMinShutterSpeed	int8u & 0x07
2.1	ImageReviewTime	int8u & 0x07
3.1	MonitorOffTime	int8u & 0xe0
3.2	MeteringTime	int8u & 0x1c
3.3	SelfTimerTime	int8u & 0x03
3.4	RemoteOnDuration	int8u & 0xc0
4.1	AELockButton	int8u & 0x0e
4.2	AELock	int8u & 0x01
5.1	ShootingModeSetting	int8u & 0x70
5.2	TimerFunctionButton	int8u & 0x07
6.1	Metering	int8u & 0x03
8.1	InternalFlash	int8u & 0x10
8.2	ManualFlashOutput	int8u & 0x07
9	FlashLevel	int8s
10.1	FocusModeSetting	int8u & 0xc0
11.1	AFAreaModeSetting	int8u & 0x30

# NikonCustom SettingsD80 Tags

Custom settings for the Nikon D80.

Index1	Tag Name		Writable		
0.1	Beep	int8u			
0.2	AFAssist	int8u	&	0x40	
0.3	NoMemoryCard	int8u	&	0x20	
0.4	ImageReview	int8u	&	0x10	
0.5	Illumination	int8u	&	0x08	
0.6	MainDialExposureComp	int8u	&	0x04	
0.7	EVStepSize	int8u	&	0x01	
1.1	AutoISO	int8u	&	0x40	
1.2	AutoISOMax	int8u	&	0x30	
1.3	AutoISOMinShutterSpeed	int8u			
2.1	AutoBracketSet	int8u	&	0xc0	
2.2	AutoBracketOrder	int8u	&	0x20	
3.1	MonitorOffTime	int8u	&	0xe0	
3.2	MeteringTime	int8u	&	0x1c	
3.3	SelfTimerTime	int8u	&	0x03	
4.1	AELockButton	int8u	&	0x1e	
4.2	AELock	int8u	&	0x01	
4.3	RemoteOnDuration	int8u	&	0xc0	
5.1	CommandDials	int8u	&	0x80	
5.2	FunctionButton	int8u	&	0x78	
6.1	GridDisplay	int8u	&	0x80	
6.2	ViewfinderWarning	int8u	&	0x40	
6.3	${\tt CenterWeightedAreaSize}$	int8u	&	0x0c	
6.4	ExposureDelayMode	int8u	&	0x20	
6.5	MB-D80Batteries	int8u	&	0x03	
7.1	FlashWarning	int8u	&	0x80	
7.2	FlashShutterSpeed	int8u	&	0x78	
7.3	AutoFP	int8u			
7.4	ModelingFlash	int8u			
8.1	InternalFlash	int8u	&	0xc0	
8.2	ManualFlashOutput	int8u	&	0x07	
9.1	RepeatingFlashOutput	int8u	&	0x70	
9.2	RepeatingFlashCount	int8u			
10.1	RepeatingFlashRate	int8u			
10.2	CommanderChannel	int8u	&	0x03	

11.1	CommanderInternalFlash	int8u	&	0xc0
11.2	CommanderGroupAMode	int8u	&	0x30
11.3	CommanderGroupBMode	int8u	&	0x0c
12.1	CommanderInternalTTLComp	int8u	&	0x1f
12.2	CommanderInternalManualOutput	int8u	&	0xe0
13.1	CommanderGroupA_TTL-AAComp	int8u	&	0x1f
13.2	CommanderGroupAManualOutput	int8u	&	0xe0
14.1	CommanderGroupB_TTL-AAComp	int8u	&	0x1f
14.2	CommanderGroupBManualOutput	int8u	&	0xe0
15.1	CenterAFArea	int8u	&	08x0
15.2	FocusAreaSelection	int8u	&	$0 \times 04$
15.3	AFAreaIllumination	int8u	&	0x03
16.1	AFAreaModeSetting	int8u	&	0xc0

# NikonCustom SettingsD90 Tags

Custom settings for the D90.

Index1	Tag Name	Writable
0.1	LightSwitch	int8u & 0x08
2.1	AFAreaModeSetting	int8u & 0x60
2.2	CenterFocusPoint	int8u & 0x10
2.3	AFAssist	int8u & 0x01
2.4	AFPointIllumination	int8u & 0x06
2.5	FocusPointWrap	int8u & 0x08
3.1	AELockForMB-D80	int8u & 0x1c
3.2	MB-D80BatteryType	int8u & 0x03
4.1	Beep	int8u & 0x40
4.2	GridDisplay	int8u & 0x02
4.3	ISODisplay	int8u & 0x0c
4.4	ViewfinderWarning	int8u & 0x01
4.5	NoMemoryCard	int8u & 0x20
5.1	ScreenTips	int8u & 0x04
5.2	FileNumberSequence	int8u & 0x08
5.3	ShootingInfoDisplay	int8u & 0xc0
5.4	LCDIllumination	int8u & 0x20
6.1	EasyExposureComp	int8u & 0x01
6.2	ReverseIndicators	int8u & 0x80
7.1	ExposureControlStepSize	int8u & 0x40
8.1	CenterWeightedAreaSize	int8u & 0x60
8.2	FineTuneOptMatrixMetering	int8u & 0x0f
9.1	FineTuneOptCenterWeighted	int8u & 0xf0
9.2	FineTuneOptSpotMetering	int8u & 0x0f
11.1	CLModeShootingSpeed	int8u & 0x07
11.2	ExposureDelayMode	int8u & 0x40
13.1	AutoBracketSet	int8u & 0xe0
13.2	AutoBracketOrder	int8u & 0x10
14.1	FuncButton	int8u & 0x78
16.1	OKButton	int8u & 0x18
17.1	AELockButton	int8u & 0x38
18.1	CommandDialsReverseRotation	int8u & 0x80
18.2	ShutterReleaseButtonAE-L	int8u & 0x02
19.1	MeteringTime	int8u & 0xf0
19.2	RemoteOnDuration	int8u & 0x03
20.1	SelfTimerTime	int8u & 0xc0
20.2	SelfTimerShotCount	int8u & 0x1e
21.1	PlaybackMonitorOffTime	int8u & 0x1c
21.2	ImageReviewTime	int8u & 0xe0
22.1	MenuMonitorOffTime	int8u & 0xe0
22.2	ShootingInfoMonitorOffTime	int8u & 0x1c
23.1	FlashShutterSpeed	int8u & 0x0f
24.1	InternalFlash	int8u & 0xc0
24.2	ManualFlashOutput	int8u & 0x1f
25.1	RepeatingFlashOutput	int8u & 0x70
25.2	RepeatingFlashCount	int8u & 0x0f
26.1	RepeatingFlashRate	int8u & 0xf0
31.1	FlashWarning	int8u & 0x80
31.2	CommanderInternalTTLComp	int8u & 0x1f
31.3	ModelingFlash	int8u & 0x20

31.4	AutoFP	int8u	&	0x40
32.1	CommanderGroupA_TTLComp	int8u	&	0x1f
33.1	CommanderGroupB_TTLComp	int8u	&	0x1f
34.1	LiveViewAF	int8u	&	0xc0

# NikonCustom SettingsD3 Tags

Custom settings for the D3, D3S, D3X, D300 and D300S.

Index1	Tag Name	Writable
0.1	CustomSettingsBank	int8u & 0x03
0.1	CustomSettingsAllDefault	int8u & 0x80
1.1	AF-CPrioritySelection	int8u & 0xc0
1.2	AF-SPrioritySelection	int8u & 0x20
1.3	AFPointSelection	int8u & 0x20
1.4	DynamicAFArea	int8u & 0x10
1.5	FocusTrackingLockOn	int8u & 0x00
2.1	AFActivation	int8u & 0x03
2.1	FocusPointWrap	int8u & 0x80
2.3	AFPointIllumination	int8u & 0x08
2.3	AFPointIllumination	int8u & 0x00
2.4	AFPointBrightness	int8u & 0x06
2.5	AFAssist	int8u & 0x00
3.1	AFOnButton	int8u & 0x01
3.2	VerticalAFOnButton	int8u & 0x07
3.3	AF-OnForMB-D10	int8u & 0x70
4.1	FocusTrackingLockOn	int8u & 0x70
4.2	AssignBktButton	int8u & 0x07
4.3	MultiSelectorLiveView	int8u & 0xc0
4.4	InitialZoomLiveView	int8u & 0x00
6.1	ISOStepSize	int8u & 0x30
6.2	ExposureControlStepSize	int8u & 0x30
6.3	ExposureCompStepSize	int8u & 0x30
6.4	EasyExposureCompensation	int8u & 0x00
7.1	CenterWeightedAreaSize	int8u & 0xe0
7.1	FineTuneOptCenterWeighted	int8u & 0xe0
8.1	FineTuneOptMatrixMetering	int8u & 0xf0
8.2	FineTuneOptSpotMetering	int8u & 0x10
9.1	MultiSelectorShootMode	int8u & 0xc0
9.2	MultiSelectorPlaybackMode	int8u & 0x30
9.3	InitialZoomSetting	int8u & 0x0c
9.4	MultiSelector	int8u & 0x01
10.1	ExposureDelayMode	int8u & 0x40
10.2	CLModeShootingSpeed	int8u & 0x07
10.3	CHModeShootingSpeed	int8u & 0x30
11	MaxContinuousRelease	int8u
12.1	ReverseIndicators	int8u & 0x20
12.2	FileNumberSequence	int8u & 0x02
	FileNumberSequence	int8u & 0x08
12.3	RearDisplay	int8u & 0x80
12.4	ViewfinderDisplay	int8u & 0x40
12.5	BatteryOrder	int8u & 0x04
12.6	MB-D10Batteries	int8u & 0x03
12.7	ScreenTips	int8u & 0x10
13.1	Веер	int8u & 0xc0
13.2	ShootingInfoDisplay	int8u & 0x30
13.3	GridDisplay	int8u & 0x02
13.4	ViewfinderWarning	int8u & 0x01
13.5	MultiSelectorPlaybackMode	int8u & 0x03
14.1	PreviewButton	int8u & 0xf8
	FuncButton	int8u & 0xf8
14.2	PreviewButtonPlusDials	int8u & 0x07
	FuncButtonPlusDials	int8u & 0x07
15.1	FuncButton	int8u & 0xf8
	PreviewButton	int8u & 0xf8
15.2	FuncButtonPlusDials	int8u & 0x07
	PreviewButtonPlusDials	int8u & 0x07
16.1	AELockButton	int8u & 0xf8
16.2	AELockButtonPlusDials	int8u & 0x07

17.1	CommandDialsReverseRotation	int8u	&	0x80
17.2	CommandDialsChangeMainSub	int8u	&	0x40
17.3	CommandDialsApertureSetting	int8u	&	0x20
17.4	CommandDialsMenuAndPlayback	int8u	&	0x10
17.5	LCDIllumination	int8u	&	0x08
17.6	PhotoInfoPlayback	int8u	&	$0 \times 04$
17.7	ShutterReleaseButtonAE-L	int8u	&	$0 \times 02$
17.8	ReleaseButtonToUseDial	int8u	&	0x01
18.1	SelfTimerTime	int8u	&	0x18
18.2	MonitorOffTime	int8u	&	$0 \times 07$
20.1	FlashSyncSpeed	int8u	&	0xe0
	FlashSyncSpeed	int8u	&	0xf0
20.2	FlashShutterSpeed	int8u	&	0x0f
21.1	AutoBracketSet	int8u	&	0xc0
	AutoBracketSet	int8u	&	0xe0
21.2	AutoBracketModeM	int8u	&	0x30
	AutoBracketModeM	int8u	&	0x18
21.3	AutoBracketOrder	int8u	&	0x08
	AutoBracketOrder	int8u	&	$0 \times 04$
21.4	ModelingFlash	int8u	&	0x01
22.1	NoMemoryCard	int8u	&	0x80
22.2	MeteringTime	int8u	&	0x0f
23.1	InternalFlash	int8u	&	0xc0
25.1	ImageReviewTime	int8u	&	0xe0
25.2	PlaybackMonitorOffTime	int8u	&	0x1c
26.1	MenuMonitorOffTime	int8u	&	0xe0
26.2	ShootingInfoMonitorOffTime	int8u	&	0x1c

# NikonCustom SettingsD700 Tags

Custom settings for the D700.

Index1	Tag Name	Writak	16	=
0.1	CustomSettingsBank	int8u	&	0x03
0.2	CustomSettingsAllDefault	int8u	&	0x80
1.1	AF-CPrioritySelection	int8u	&	0xc0
1.2	AF-SPrioritySelection	int8u	&	0x20
1.3	AFPointSelection	int8u	&	0x10
1.4	DynamicAFArea	int8u	&	0x0c
2.1	AFActivation	int8u	&	08x0
2.2	FocusPointWrap	int8u	&	80x0
2.3	AFPointIllumination	int8u	&	0x06
2.4	AFAssist	int8u	&	0x01
3.1	FocusTrackingLockOn	int8u	&	0x07
3.2	AF-OnForMB-D10	int8u	&	0x70
4.1	ISOStepSize	int8u	&	0xc0
4.2	ExposureControlStepSize	int8u	&	0x30
4.3	ExposureCompStepSize	int8u		
4.4	EasyExposureCompensation	int8u		
5.1	CenterWeightedAreaSize	int8u		
6.1	FineTuneOptMatrixMetering	int8u		
6.2	FineTuneOptSpotMetering	int8u		
7.1	ShutterReleaseButtonAE-L	int8u		
7.2	SelfTimerTime	int8u		
7.3	MeteringTime	int8u		
8.1	PlaybackMonitorOffTime	int8u		
8.2	MenuMonitorOffTime	int8u		
9.1	ShootingInfoMonitorOffTime	int8u		
9.2	ImageReviewTime	int8u		
10.1	Beep	int8u		
10.2	ShootingInfoDisplay	int8u		
10.3	LCDIllumination	int8u		
10.4	ExposureDelayMode	int8u		
10.5	GridDisplay	int8u		
11.1	FileNumberSequence	int8u		
11.2	CLModeShootingSpeed	int8u	&	0x07
12	MaxContinuousRelease	int8u		
13.1	ScreenTips	int8u		
13.2	BatteryOrder	int8u	&	$0 \times 04$

	_			
13.3	MB-D10BatteryType	int8u	&	0x03
15.1	FlashSyncSpeed	int8u	&	0xf0
15.2	FlashShutterSpeed	int8u	&	0x0f
16.1	FlashControlBuilt-in	int8u	&	0xc0
16.2	ManualFlashOutput	int8u	&	0x1f
17.1	RepeatingFlashOutput	int8u	&	0x70
17.2	RepeatingFlashCount	int8u	&	0x0f
18.1	RepeatingFlashRate	int8u	&	0xf0
18.2	CommanderInternalTTLChannel	int8u	&	0x03
20.1	CommanderInternalTTLCompBuiltin	int8u	&	0x1f
21.1	CommanderInternalTTLCompGroupA	int8u	&	0x1f
22.1	CommanderInternalTTLCompGroupB	int8u	&	0x1f
26.1	AutoBracketSet	int8u	&	0xc0
26.2	AutoBracketModeM	int8u	&	0x30
26.3	AutoBracketOrder	int8u	&	0x08
26.4	ModelingFlash	int8u	&	0x01
27.1	MultiSelectorShootMode	int8u	&	0xc0
27.2	MultiSelectorPlaybackMode	int8u	&	0x30
27.3	InitialZoomSetting	int8u	&	0x0c
27.4	MultiSelector	int8u	&	0x01
28.1	FuncButton	int8u	&	0xf8
29.1	PreviewButton	int8u	&	0xf8
30.1	AELockButton	int8u	&	0xf8
31.1	FuncButtonPlusDials	int8u	&	0x70
31.2	PreviewButtonPlusDials	int8u	&	$0 \times 07$
32.1	AELockButtonPlusDials	int8u	&	0x70
33.1	CommandDialsReverseRotation	int8u	&	0x80
33.2	CommandDialsChangeMainSub	int8u	&	0x40
33.3	CommandDialsApertureSetting	int8u	&	0x20
33.4	CommandDialsMenuAndPlayback	int8u	&	0x10
33.5	ReverseIndicators	int8u	&	0x08
33.6	PhotoInfoPlayback	int8u	&	$0 \times 04$
33.7	NoMemoryCard	int8u	&	0x02
33.8	ReleaseButtonToUseDial	int8u	&	0x01

## NikonCustom SettingsD800 Tags

Custom settings for the D800 and D800E.

Index1	Tag Name	Writable
12.1	AutoBracketingSet	int8u & 0xe0
12.2	AutoBracketOrder	int8u & 0x10
12.3	AutoBracketingMode	int8u & 0x0c
22.1	FlashSyncSpeed	int8u & 0xf0
22.2	FlashShutterSpeed	int8u & 0x0f
23.1	FlashControlBuilt-in	int8u & 0xc0
23.2	ManualFlashOutput	int8u & 0x1f
24.1	RepeatingFlashOutput	int8u & 0x70
24.2	RepeatingFlashCount	int8u & 0x0f
25.1	RepeatingFlashRate	int8u & 0xf0
25.2	CommanderChannel	int8u & 0x03
27.1	CommanderInternalFlash	int8u & 0xc0
27.2	CommanderInternalManualOutput	int8u & 0x1f
28.1	CommanderGroupAMode	int8u & 0xc0
28.2	CommanderGroupAManualOutput	int8u & 0x1f
29.1	CommanderGroupBMode	int8u & 0xc0
29.2	CommanderGroupBManualOutput	int8u & 0x1f
30.1	ModelingFlash	int8u & 0x20
30.2	CommanderInternalTTLComp	int8u & 0x1f
31.1	CommanderGroupA_TTL-AAComp	int8u & 0x1f
32.1	CommanderGroupB_TTL-AAComp	int8u & 0x1f

## NikonCustom SettingsD810 Tags

Custom settings for the  ${\tt D810}$ .

Index1	Tag Name	Writable
0.1	LightSwitch	int8u & 0x08

	ExifTool 13.24 Tag Names			
0.2	CustomSettingsBank	int8u	&	$0 \times 03$
1.1	AF-CPrioritySelection	int8u	&	0xc0
1.2	AF-SPrioritySelection	int8u	&	0x20
1.3	AFPointSelection	int8u	&	0x10
1.4	FocusTrackingLockOn	int8u	&	$0 \times 07$
2.1	AFActivation	int8u	&	0x80
2.2	FocusPointWrap	int8u		
2.3	AFPointBrightness	int8u		
2.4	AFAssist	int8u		
3.1	BatteryOrder	int8u		
3.2	MB-D12BatteryType	int8u		
$4.1 \\ 4.2$	Pitch	int8u int8u		
4.2	NoMemoryCard ISODisplay	int8u int8u		
4.3	GridDisplay	int8u		
5.1	ShootingInfoDisplay	int8u		
5.2	LCDIllumination	int8u		
5.3	ElectronicFront-CurtainShutter	int8u		
5.4	ScreenTips	int8u		
5.5	Beep	int8u		
6.1	ReverseIndicators	int8u	&	0x80
6.2	CommandDialsReverseRotation	int8u	&	0x18
6.3	EasyExposureCompensation	int8u	&	0x03
7.1	ExposureControlStepSize	int8u	&	0xc0
7.2	ISOStepSize	int8u	&	0x30
7.3	ExposureCompStepSize	int8u	&	0x0c
8.1	CenterWeightedAreaSize	int8u	&	0xe0
8.2	FineTuneOptMatrixMetering	int8u		
9.1	FineTuneOptCenterWeighted	int8u	&	0xf0
9.2	FineTuneOptSpotMetering	int8u		
10.1	MultiSelectorShootMode	int8u		
10.2	MultiSelectorPlaybackMode	int8u		
10.3	MultiSelector	int8u		
11.1 11.2	ExposureDelayMode	int8u		
12.1	CLModeShootingSpeed MaxContinuousRelease	int8u int8u	ÒΣ	UXUL
13.1	AutoBracketSet	int8u	۲-	0.200
13.1	AutoBracketOrder	int8u		
13.3	AutoBracketModeM	int8u		
	FuncButton	int8u		
15.1	PreviewButton	int8u		
16.1	AssignBktButton	int8u		
17.1	AELockButton	int8u	&	0x1f
18.1	CommandDialsChangeMainSub	int8u	&	0xe0
18.2	CommandDialsMenuAndPlayback	int8u	&	0x18
18.3	CommandDialsApertureSetting	int8u	&	$0 \times 04$
18.4	ShutterReleaseButtonAE-L	int8u	&	0x02
18.5	ReleaseButtonToUseDial	int8u		
19.1	StandbyTimer	int8u		
20.1	SelfTimerTime	int8u		
20.2	SelfTimerShotInterval	int8u		
20.3	SelfTimerShotCount	int8u		
21.1	ImageReviewMonitorOffTime	int8u		
21.2 22.1	LiveViewMonitorOffTime MenuMonitorOffTime	int8u int8u		
22.1	ShootingInfoMonitorOffTime	int8u		
23.1	FlashSyncSpeed	int8u		-
23.2	FlashShutterSpeed	int8u		
24.1	FlashControlBuilt-in	int8u		
31.1	ModelingFlash	int8u		
36.1	PlaybackMonitorOffTime	int8u		
37.1	MultiSelectorLiveView	int8u		
38.1	ShutterSpeedLock	int8u		
38.2	ApertureLock	int8u	&	0x40
38.3	MovieShutterButton	int8u	&	0x20
38.4	FlashExposureCompArea	int8u		
40.1	MovieAELockButtonAssignment	int8u		
41.1	MovieFunctionButton	int8u		
41.2	MoviePreviewButton	int8u		
42.1	FuncButtonPlusDials	int8u	&	0x0f

43.1	PreviewButtonPlusDials	int8u	&	0x0f
44.1	AELockButtonPlusDials	int8u	&	0x0f
45.1	AssignMovieRecordButton	int8u	&	0x0f
46.1	FineTuneOptHighlightWeighted	int8u	&	0x0f
47.1	DynamicAreaAFDisplay	int8u	&	0x80
47.2	AFPointIllumination	int8u	&	0x40
47.3	StoreByOrientation	int8u	&	0x18
47.4	GroupAreaAFIllumination	int8u	&	$0 \times 04$
48.1	MatrixMetering	int8u	&	0x80
48.2	LiveViewButtonOptions	int8u	&	0x30
48.3	AFModeRestrictions	int8u	&	0x03
49.1	LimitAFAreaModeSelection	int8u	&	0x7e
50.1	AF-OnForMB-D12	int8u	&	0x07
51.1	AssignRemoteFnButton	int8u	&	0x1f
52.1	LensFocusFunctionButtons	int8u	&	0x3f

# NikonCustom SettingsD850 Tags

Custom settings for the D850.

Index1	Tag Name	Writable
0.2	CustomSettingsBank	int8u & 0x03
1.1	AF-CPrioritySelection	int8u & 0xc0
1.2	AF-SPrioritySelection	int8u & 0x20
1.3	AFPointSelection	int8u & 0x10
1.4	Three-DTrackingFaceDetection	int8u & 0x08
1.5	BlockShotAFResponse	int8u & 0x07
2.1	FocusPointWrap	int8u & 0x08
2.2	AFPointBrightness	int8u & 0x06
4.1	ISODisplay	int8u & 0x08
4.2	GridDisplay	int8u & 0x02
5.1	LCDIllumination	int8u & 0x20
5.2	ElectronicFront-CurtainShutter	int8u & 0x08
6.1	ReverseIndicators	int8u & 0x80
6.2	CommandDialsReverseRotation	int8u & 0x18
6.3	EasyExposureCompensation	int8u & 0x03
7.1	ExposureControlStepSize	int8u & 0xc0
7.2	ISOStepSize	int8u & 0x30
7.3	ExposureCompStepSize	int8u & 0x0c
8.1	CenterWeightedAreaSize	int8u & 0xe0
8.2	FineTuneOptMatrixMetering	int8u & 0x0f
9.1	FineTuneOptCenterWeighted	int8u & 0xf0
9.2	FineTuneOptSpotMetering	int8u & 0x0f
10.1	MultiSelectorShootMode	int8u & 0xe0
10.2	MultiSelectorPlaybackMode	int8u & 0x0c
10.3	MultiSelector	int8u & 0x01
11.1	ExposureDelayMode	int8u & 0xe0
11.2	CLModeShootingSpeed	int8u & 0x0f
12.1	MaxContinuousRelease	int8u
13.1 13.2	AutoBracketOrder AutoBracketModeM	int8u & 0x10 int8u & 0x0c
14.1	Func1Button	int8u & 0x3f
15.1	PreviewButton	int8u & 0x3f
16.1	AssignBktButton	int8u & 0x31
18.1	CommandDialsChangeMainSub	int8u & 0xe0
18.2	CommandDialsMenuAndPlayback	int8u & 0xe0
18.3	CommandDialsApertureSetting	int8u & 0x10
18.4	ReleaseButtonToUseDial	int8u & 0x01
19.1	StandbyTimer	int8u & 0xf0
20.1	SelfTimerTime	int8u & 0xc0
20.2	SelfTimerShotInterval	int8u & 0x30
20.3	SelfTimerShotCount	int8u & 0x0f
21.1	ImageReviewMonitorOffTime	int8u & 0xe0
21.2	LiveViewMonitorOffTime	int8u & 0x1c
22.1	MenuMonitorOffTime	int8u & 0xe0
22.2	ShootingInfoMonitorOffTime	int8u & 0x1c
23.1	FlashSyncSpeed	int8u & 0xf0
23.2	FlashShutterSpeed	int8u & 0x0f
31.1	ModelingFlash	int8u & 0x20

36.1	PlaybackMonitorOffTime	int8u	&	0xe0
37.1	MultiSelectorLiveView	int8u	&	0xc0
38.1	ShutterSpeedLock	int8u	&	08x0
38.2	ApertureLock	int8u	&	0x40
38.3	MovieShutterButton	int8u	&	0x10
38.4	FlashExposureCompArea	int8u	&	$0 \times 04$
38.5	AutoFlashISOSensitivity	int8u	&	0x02
41.1	MovieFunc1Button	int8u	&	0xf0
41.2	MoviePreviewButton	int8u	&	0x0f
42.1	Func1ButtonPlusDials	int8u	&	0x0f
43.1	PreviewButtonPlusDials	int8u	&	0x0f
45.1	AssignMovieRecordButtonPlusDials	int8u	&	0x0f
46.1	FineTuneOptHighlightWeighted	int8u	&	0x0f
47.1	DynamicAreaAFDisplay	int8u	&	08x0
47.2	AFPointIllumination	int8u	&	0x40
47.3	StoreByOrientation	int8u	&	0x18
48.1	MatrixMetering	int8u	&	08x0
48.2	LiveViewButtonOptions	int8u	&	0x30
48.3	AFModeRestrictions	int8u	&	0x03
49.1	LimitAFAreaModeSelection	int8u	&	0x7e
52.1	LensFocusFunctionButtons	int8u	&	0x3f
66.1	VerticalMultiSelector	int8u	&	0xff
67.1	AssignMB-D18FuncButton	int8u	&	0x3f
68.1	AssignMB-D18FuncButtonPlusDials	int8u	&	0x0f
70.1	AF-OnButton	int8u	&	0x3f
71.1	SubSelector	int8u	&	$0 \times 80$
72.1	SubSelectorCenter	int8u	&	0x3f
73.1	SubSelectorPlusDials	int8u	&	0x0f
74.1	AssignMovieSubselector	int8u	&	0xf0
75.1	AssignMovieFunc1ButtonPlusDials	int8u	&	0x10
75.2	AssignMoviePreviewButtonPlusDials	int8u	&	$0 \times 01$
76.1	AssignMovieSubselectorPlusDials	int8u	&	0x10
77.1	SyncReleaseMode	int8u	&	08x0
77.2	ContinuousModeLiveView	int8u	&	0x40
78.1	Three-DTrackingWatchArea	int8u	&	$0 \times 80$
78.2	SubjectMotion	int8u	&	0x60
78.3	AFActivation	int8u	&	0x08
78.4	ShutterReleaseButtonAE-L	int8u	&	$0 \times 03$
79.1	AssignMB-D18AF-OnButton	int8u	&	0x7f
80.1	Func2Button	int8u	&	0x3f
82.1	AssignMovieFunc2Button	int8u	&	0x70

# $\underline{\texttt{NikonCustom}} \ \underline{\texttt{SettingsD5000}} \ \underline{\texttt{Tags}}$

Custom settings for the D5000.

Index1	Tag Name	Writable
0.1	AFAreaModeSetting	int8u & 0x60
0.2	AFAssist	int8u & 0x01
2.1	Beep	int8u & 0xc0
2.2	GridDisplay	int8u & 0x02
2.3	ISODisplay	int8u & 0x08
2.4	NoMemoryCard	int8u & 0x20
3.1	FileNumberSequence	int8u & 0x08
4.1	RangeFinder	int8u & 0x10
4.2	DateImprint	int8u & 0x08
4.3	ReverseIndicators	int8u & 0x80
5.1	EVStepSize	int8u & 0x40
9.1	ExposureDelayMode	int8u & 0x40
11.1	AutoBracketSet	int8u & 0xc0
12.1	TimerFunctionButton	int8u & 0x38
15.1	AELockButton	int8u & 0x38
16.1	ShutterReleaseButtonAE-L	int8u & 0x02
16.2	CommandDialsReverseRotation	int8u & 0x80
17.1	MeteringTime	int8u & 0x70
17.2	RemoteOnDuration	int8u & 0x03
18.1	SelfTimerTime	int8u & 0xc0
18.2		int8u & 0x1e
19.1	ImageReviewTime	int8u & 0xe0

20.1	PlaybackMenusTime	int8u	&	0xe0
22.1	InternalFlash	int8u	&	0xc0
22.2	ManualFlashOutput	int8u	&	0x1f
32.1	LiveViewAF	int8u	&	0x60

## NikonCustom SettingsD5100 Tags

Custom settings for the D5100.

Index1	Tag Name	Writable
0.1	AF-CPrioritySelection	int8u & 0x80
1.1	AFAssist	int8u & 0x01
3.1	Beep	int8u & 0xc0
3.2	NoMemoryCard	int8u & 0x20
3.3	ISODisplay	int8u & 0x08
4.1	FileNumberSequence	int8u & 0x08
5.1	RangeFinder	int8u & 0x10
5.2	ReverseIndicators	int8u & 0x80
6.1	EVStepSize	int8u & 0x40
10.1	ExposureDelayMode	int8u & 0x40
12.1	AutoBracketSet	int8u & 0xc0
13.1	TimerFunctionButton	int8u & 0x38
16.1	AELockButton	int8u & 0x38
17.1	ShutterReleaseButtonAE-L	int8u & 0x02
17.2	CommandDialsReverseRotation	int8u & 0x80
18.1	MeteringTime	int8u & 0x70
18.2	RemoteOnDuration	int8u & 0x03
19.1	SelfTimerTime	int8u & 0xc0
19.2	SelfTimerShotCount	int8u & 0x0f
20.1	ImageReviewTime	int8u & 0xe0
20.2	LiveViewMonitorOffTime	int8u & 0x1c
21.1	PlaybackMenusTime	int8u & 0xe0
23.1	ManualFlashOutput	int8u & 0x1f

## NikonCustom SettingsD5200 Tags

Custom settings for the D5200.

Index1	Tag Name	Writable
0.1	AF-CPrioritySelection	int8u & 0x8(
0.2	NumberOfFocusPoints	int8u & 0x10
1.1	AFAssist	int8u & 0x01
3.1	Beep	int8u & 0xc(
3.2	NoMemoryCard	int8u & 0x20
3.3	ISODisplay	int8u & 0x08
4.1	FileNumberSequence	int8u & 0x08
5.1	RangeFinder	int8u & 0x04
5.2	ReverseExposureCompDial	int8u & 0x10
5.3	ReverseShutterSpeedAperture	int8u & 0x08
5.4	ReverseIndicators	int8u & 0x8(
6.1	EVStepSize	int8u & 0x40
10.1	ExposureDelayMode	int8u & 0x4(
12.1	AutoBracketSet	int8u & 0xc(
13.1	FunctionButton	int8u & 0x1f
16.1	AELockButton	int8u & 0x0f
17.1	ShutterReleaseButtonAE-L	int8u & 0x02
18.1	StandbyTimer	int8u & 0xe(
18.2	RemoteOnDuration	int8u & 0x03
19.1	SelfTimerTime	int8u & 0xc(
19.2	SelfTimerShotCount	int8u & 0x0f
20.1	ImageReviewTime	int8u & 0xe(
20.2	LiveViewMonitorOffTime	int8u & 0x10
21.1	PlaybackMenusTime	int8u & 0xe(
23.1	InternalFlash	int8u & 0xc(
23.2	ManualFlashOutput	int8u & 0x1f

Custom settings for the D7000.

Index1	Tag Name	Writable
0.1	AF-CPrioritySelection	int8u & 0x80
0.2	AF-SPrioritySelection	int8u & 0x20
0.3	NumberOfFocusPoints	int8u & 0x10
0.4	FocusTrackingLockOn	int8u & 0x07
1.1 1.2	FocusPointWrap AFPointIllumination	int8u & 0x08 int8u & 0x06
1.3	AFAssist	int8u & 0x06
2.1	BatteryOrder	int8u & 0x01
2.2	AF-OnForMB-D11	int8u & 0x1c
2.3	MB-D11BatteryType	int8u & 0x03
3.1	BeepPitch	int8u & 0xc0
3.2	NoMemoryCard	int8u & 0x20
3.3	ISODisplay	int8u & 0x0c
3.4	GridDisplay	int8u & 0x02
3.5	ViewfinderWarning	int8u & 0x01
4.1	ShootingInfoDisplay	int8u & 0xc0
4.2 4.3	LCDIllumination	int8u & 0x20 int8u & 0x08
4.3	FileNumberSequence ScreenTips	int8u & 0x08
4.5	BeepVolume	int8u & 0x04
5.1	ReverseIndicators	int8u & 0x80
5.2	EasyExposureCompensation	int8u & 0x03
6.1	ExposureControlStep	int8u & 0x40
6.2	ISOSensitivityStep	int8u & 0x10
7.1	CenterWeightedAreaSize	int8u & 0xe0
10.1	ExposureDelayMode	int8u & 0x40
10.2	CLModeShootingSpeed	int8u & 0x07
11	MaxContinuousRelease	int8u
$12.1 \\ 12.2$	AutoBracketSet AutoBracketOrder	int8u & 0xe0 int8u & 0x10
13.1	FuncButton	int8u & 0x10
14.1	PreviewButton	int8u & 0xf8
15.1	OKButton	int8u & 0x18
16.1		int8u & 0x38
17.1	CommandDialsReverseRotation	int8u & 0x80
17.2	CommandDialsChangeMainSub	int8u & 0x60
17.3	CommandDialsApertureSetting	int8u & 0x04
17.4	CommandDialsMenuAndPlayback	int8u & 0x18
17.5	ShutterReleaseButtonAE-L	int8u & 0x02
17.6	ReleaseButtonToUseDial	int8u & 0x01
18.1 18.2	MeteringTime RemoteOnDuration	int8u & 0xf0 int8u & 0x03
19.1	SelfTimerTime	int8u & 0xc0
19.2	SelfTimerInterval	int8u & 0x30
19.3	SelfTimerShotCount	int8u & 0x0f
20.1	ImageReviewTime	int8u & 0xe0
20.2	LiveViewMonitorOffTime	int8u & 0x1c
21.1	MenuMonitorOffTime	int8u & 0xe0
21.2	ShootingInfoMonitorOffTime	int8u & 0x1c
22.1	FlashSyncSpeed	int8u & 0xf0
22.2	FlashShutterSpeed	int8u & 0x0f
23.1 23.2	FlashControlBuilt-in ManualFlashOutput	int8u & 0xc0 int8u & 0x1f
24.1	RepeatingFlashOutput	int8u & 0x11
24.2	RepeatingFlashCount	int8u & 0x70
25.1	RepeatingFlashRate	int8u & 0xf0
26.1	CommanderInternalTTLCompBuiltin	int8u & 0x1f
27.1	CommanderInternalTTLCompGroupA	int8u & 0x1f
28.1	CommanderInternalTTLCompGroupB	int8u & 0x1f
30.1	FlashWarning	int8u & 0x80
30.2	ModelingFlash	int8u & 0x20
34.1	LiveViewAFAreaMode	int8u & 0x60
34.2	LiveViewAFMode	int8u & 0x02
35.1	PlaybackMonitorOffTime	int8u & 0xe0

Custom settings for the D4 and D4S.

Index1	Tag Name	Writable
0.1	CustomSettingsBank	int8u & 0x03
1.1	AF-CPrioritySelection	int8u & 0xc0
1.2	AF-SPrioritySelection	int8u & 0x20
1.3	AFPointSelection	int8u & 0x10
1.4	FocusTrackingLockOn	int8u & 0x07
2.1	AFActivation	int8u & 0x80
2.2	FocusPointWrap	int8u & 0x08
4.1	Pitch	int8u & 0x40
4.2	NoMemoryCard	int8u & 0x20
4.3	GridDisplay	int8u & 0x02
5.1	ShootingInfoDisplay	int8u & 0xc0
5.2	LCDIllumination	int8u & 0x20
5.3 5.4	ScreenTips	int8u & 0x04 int8u & 0x03
6.1	Beep ReverseIndicators	int8u & 0x03
6.2	RearDisplay	int8u & 0x40
6.3	ViewfinderDisplay	int8u & 0x10
6.4	CommandDialsReverseRotation	int8u & 0x18
6.5	EasyExposureCompensation	int8u & 0x03
7.1	ExposureControlStepSize	int8u & 0xc0
7.2	ISOStepSize	int8u & 0x30
7.3	ExposureCompStepSize	int8u & 0x0c
8.1	CenterWeightedAreaSize	int8u & 0xe0
8.2	FineTuneOptMatrixMetering	int8u & 0x0f
9.1	FineTuneOptCenterWeighted	int8u & 0xf0
9.2	FineTuneOptSpotMetering	int8u & 0x0f
10.1	MultiSelectorShootMode	int8u & 0xc0
10.2	MultiSelectorPlaybackMode	int8u & 0x30
10.3 11.1	MultiSelector ExposureDelayMode	int8u & 0x01 int8u & 0xc0
11.2	CHModeShootingSpeed	int8u & 0xc0
11.3	CLModeShootingSpeed	int8u & 0x10
12	MaxContinuousRelease	int8u
13.1	AutoBracketSet	int8u & 0xe0
13.2	AutoBracketOrder	int8u & 0x10
13.3	AutoBracketModeM	int8u & 0x0c
14.1	FuncButton	int8u & 0xf8
14.2	FuncButtonPlusDials	int8u & 0x07
15.1	PreviewButton	int8u & 0xf8
15.2	PreviewButtonPlusDials	int8u & 0x07
16.1 18.1	AssignBktButton	int8u & 0x07 int8u & 0xe0
18.2	CommandDialsChangeMainSub CommandDialsMenuAndPlayback	int8u & 0xe0
18.3	CommandDialsApertureSetting	int8u & 0x18
18.4	ShutterReleaseButtonAE-L	int8u & 0x02
18.5	ReleaseButtonToUseDial	int8u & 0x01
19.1	StandbyTimer	int8u & 0xf0
20.1	SelfTimerTime	int8u & 0xc0
20.2	SelfTimerShotCount	int8u & 0x0f
20.3	SelfTimerShotInterval	int8u & 0x30
21.1	ImageReviewMonitorOffTime	int8u & 0xe0
21.2	LiveViewMonitorOffTime	int8u & 0x1c
22.1	MenuMonitorOffTime	int8u & 0xe0
22.2	ShootingInfoMonitorOffTime	int8u & 0x1c
23.1	FlashSyncSpeed	int8u & 0xf0
23.2 31.1	FlashShutterSpeed	int8u & 0x0f
31.1 36.1	ModelingFlash PlaybackMonitorOffTime	int8u & 0x20 int8u & 0xe0
37.1	PlaybackMonitorOfffine	int8u & 0xe0
38.1	ShutterSpeedLock	int8u & 0x01
38.2	ApertureLock	int8u & 0x40
38.3	MovieShutterButton	int8u & 0x30
38.4	FlashExposureCompArea	int8u & 0x04
41.1	MovieFunctionButton	int8u & 0x70
41.2	MoviePreviewButton	int8u & 0x07

42.1	VerticalMultiSelector	int8u	&	0x60
42.2	VerticalFuncButton	int8u	&	0x1f
43.1	VerticalFuncButtonPlusDials	int8u	&	0xf0
43.2	AssignMovieRecordButton	int8u	&	0x07
46.1	DynamicAreaAFDisplay	int8u	&	0x80
46.2	AFPointIllumination	int8u	&	0x60
46.3	StoreByOrientation	int8u	&	0x18
46.4	GroupAreaAFIllumination	int8u	&	$0 \times 04$
46.5	AFPointBrightness	int8u	&	0x03
47.1	AFOnButton	int8u	&	0x70
47.2	VerticalAFOnButton	int8u	&	0x07
48.1	SubSelectorAssignment	int8u	&	0x80
48.2	MovieSubSelectorAssignment	int8u	&	0x07
49.1	SubSelector	int8u	&	0xf8
49.2	SubSelectorPlusDials	int8u	&	$0 \times 07$
50.1	MatrixMetering	int8u	&	0x80
50.2	LiveViewButtonOptions	int8u	&	0x30
50.3	AFModeRestrictions	int8u	&	0x03
51.1	LimitAFAreaModeSelection	int8u	&	0x7e
52.1	MovieFunctionButtonPlusDials	int8u	&	0x10
52.2	MoviePreviewButtonPlusDials	int8u	&	0x01
53.1	MovieSubSelectorAssignmentPlusDials	int8u	&	0x10
54.1	AssignRemoteFnButton	int8u	&	0x1f
55.1	LensFocusFunctionButtons	int8u	&	0x3f

# NikonCustom SettingsD5 Tags

Custom settings for the D5.

Index1	Tag Name	Writak	16	9
0.1	 CustomSettingsBank	 int8u	۔ ۔ د	- ∩√∩3
1.1	AF-CPrioritySelection	int8u		
1.2	AF-SPrioritySelection	int8u		
1.3	NumberOfFocusPoints	int8u		
1.4	Three-DTrackingFaceDetection	int8u		
1.5	BlockShotAFResponse	int8u		
2.1	FocusPointWrap	int.8u		
2.2	AFPointBrightness	int8u	&	0×06
4.1	ISODisplay	int8u	&	0x08
4.2	GridDisplay	int8u	&	0x02
5.1	LCDIllumination	int8u	&	0x20
5.2	ElectronicFront-CurtainShutter	int8u	&	0x08
6.1	ReverseIndicators	int8u	&	0x80
6.2	CommandDialsReverseRotation	int8u	&	0x18
6.3	EasyExposureCompensation	int8u	&	0x03
7.1	ExposureControlStepSize	int8u	&	0xc0
7.2	ISOStepSize	int8u	&	0x30
7.3	ExposureCompStepSize	int8u	&	0x0c
8.1	CenterWeightedAreaSize	int8u	&	0xe0
8.2	FineTuneOptMatrixMetering	int8u	&	0x0f
9.1	FineTuneOptCenterWeighted	int8u		
9.2	FineTuneOptSpotMetering	int8u	&	0x0f
10.1	MultiSelectorShootMode	int8u	&	0xe0
10.3	MultiSelector	int8u	&	0x01
11.1	ExposureDelayMode	int8u		
11.2	CLModeShootingSpeed	int8u	&	0x0f
12.1	MaxContinuousRelease	int8u		
13.1	AutoBracketOrder	int8u		
13.2	AutoBracketModeM	int8u		
14.1	Func1Button	int8u		-
15.1	PreviewButton	int8u		-
16.1	AssignBktButton	int8u		
18.1	CommandDialsChangeMainSub	int8u		
18.2	CommandDialsMenuAndPlayback	int8u		-
18.3	CommandDialsApertureSetting	int8u		
18.4	ReleaseButtonToUseDial	int8u		
19.1	StandbyTimer	int8u		
20.1	SelfTimerTime	int8u		
20.2	SelfTimerShotInterval	int8u	&	0x30

20.3	SelfTimerShotCount	int8u	&	0x0f
21.1	ImageReviewMonitorOffTime	int8u	&	0xe0
21.2	LiveViewMonitorOffTime	int8u	&	0x1c
22.1	MenuMonitorOffTime	int8u	&	0xe0
22.2	ShootingInfoMonitorOffTime	int8u	&	0x1c
23.1	FlashSyncSpeed	int8u	&	0xf0
23.2	FlashShutterSpeed	int8u	&	0x0f
31.1	ModelingFlash	int8u	&	0x20
36.1	PlaybackMonitorOffTime	int8u	&	0xe0
37.1	MultiSelectorLiveView	int8u	&	0xc0
38.1	ShutterSpeedLock	int8u	&	$0 \times 80$
38.2	ApertureLock	int8u	&	0x40
38.3	MovieShutterButton	int8u	&	0x10
38.4	FlashExposureCompArea	int8u	&	$0 \times 04$
38.5	AutoFlashISOSensitivity	int8u	&	0x02
41.1	MovieFunc1Button	int8u	&	0xf0
41.2	MoviePreviewButton	int8u	&	0x0f
42.1	FunclButtonPlusDials	int8u	&	0x0f
43.1	PreviewButtonPlusDials	int8u	&	0x0f
45.1	AssignMovieRecordButtonPlusDials	int8u	&	0x0f
46.1	FineTuneOptHighlightWeighted	int8u	&	0x0f
47.1	DynamicAreaAFDisplay	int8u	&	0x80
47.2	AFPointIllumination	int8u	&	0x40
47.3	StoreByOrientation	int8u	&	0x18
48.1	MatrixMetering	int8u	&	0x80
48.2	LiveViewButtonOptions	int8u	&	0x30
48.3	AFModeRestrictions	int8u	&	0x03
49.1	LimitAFAreaModeSelection	int8u	&	0x7e
52.1	LensFocusFunctionButtons	int8u	&	0x3f
66.1	VerticalMultiSelector	int8u	&	0xff
67.1	VerticalFuncButton	int8u	&	0x3f
68.1	VerticalFuncPlusDials	int8u	&	0x0f
70.1	AF-OnButton	int8u	&	0x3f
71.1	SubSelector	int8u	&	0x80
72.1	SubSelectorCenter	int8u	&	0x3f
73.1	SubSelectorPlusDials	int8u	&	0x0f
74.1	AssignMovieSubselector	int8u	&	0xf0
75.1	AssignMovieFunclButtonPlusDials	int8u	&	0x10
75.2	AssignMoviePreviewButtonPlusDials	int8u	&	$0 \times 01$
76.1	AssignMovieSubselectorPlusDials	int8u	&	0x10
77.1	SyncReleaseMode	int8u	&	0x80
78.1	Three-DTrackingWatchArea	int8u		
78.2	SubjectMotion	int8u	&	0x60
78.3	AFActivation	int8u		
78.4	ShutterReleaseButtonAE-L	int8u	&	0x03
79.1	VerticalAFOnButton	int8u		
80.1	Func2Button	int8u		
81.1	Func2ButtonPlusDials	int8u		
82.1	AssignMovieFunc2Button	int8u		
83.1	Func3Button	int8u		

# NikonCustom SettingsD500 Tags

Custom settings for the D500.

Index1 Tag Name	Writable
0.1 CustomSettingsBank	int8u & 0x03
1.1 AF-CPrioritySelection	int8u & 0xc0
1.2 AF-SPrioritySelection	int8u & 0x20
1.3 NumberOfFocusPoints	int8u & 0x10
1.4 Three-DTrackingFaceDetection	int8u & 0x08
1.5 BlockShotAFResponse	int8u & 0x07
2.1 FocusPointWrap	int8u & 0x08
2.2 AFPointBrightness	int8u & 0x06
4.1 ISODisplay	int8u & 0x08
4.2 GridDisplay	int8u & 0x02
5.1 LCDIllumination	int8u & 0x20
5.2 ElectronicFront-CurtainShutter	int8u & 0x08
6.1 ReverseIndicators	int8u & 0x80

	ExifTool 13.24 Tag Names			
6.2	CommandDialsReverseRotation	int8u	&	0x18
6.3	EasyExposureCompensation	int8u		
7.1	ExposureControlStepSize	int8u	&	0xc0
7.2	ISOStepSize	int8u	&	0x30
7.3	ExposureCompStepSize	int8u	&	0x0c
8.1	CenterWeightedAreaSize	int8u	&	0xe0
8.2	FineTuneOptMatrixMetering	int8u		
9.1	FineTuneOptCenterWeighted	int8u		
9.2	FineTuneOptSpotMetering	int8u		
10.1	MultiSelectorShootMode	int8u		
10.2	MultiSelectorPlaybackMode	int8u		
10.3	MultiSelector	int8u		
11.1 11.2	ExposureDelayMode	int8u int8u		
12.1	CLModeShootingSpeed MaxContinuousRelease	int8u	œ	UXUL
13.1	AutoBracketOrder	int8u	۲-	0~10
13.2	AutoBracketModeM	int8u		
14.1	Func1Button	int8u		
15.1	PreviewButton	int8u		-
16.1	AssignBktButton	int8u		
18.1	CommandDialsChangeMainSub	int8u		
18.2	CommandDialsMenuAndPlayback	int8u	&	0x18
18.3	CommandDialsApertureSetting	int8u	&	$0 \times 04$
18.4	ReleaseButtonToUseDial	int8u	&	0x01
19.1	StandbyTimer	int8u	&	0xf0
20.1	SelfTimerTime	int8u	&	0xc0
20.2	SelfTimerShotInterval	int8u		
20.3	SelfTimerShotCount	int8u		
21.1	ImageReviewMonitorOffTime	int8u		
21.2	LiveViewMonitorOffTime	int8u		-
22.1	MenuMonitorOffTime	int8u		
22.2	ShootingInfoMonitorOffTime	int8u int8u		
23.2	FlashSyncSpeed FlashShutterSpeed	int8u		
31.1	ModelingFlash	int8u		
36.1	PlaybackMonitorOffTime	int8u		
37.1	MultiSelectorLiveView	int8u		
38.1	ShutterSpeedLock	int8u		
38.2	ApertureLock	int8u		
	MovieShutterButton	int8u	&	0x10
38.4	FlashExposureCompArea	int8u	&	0x04
38.5	AutoFlashISOSensitivity	int8u	&	0x02
41.1	MovieFunc1Button	int8u	&	0xf0
41.2	MoviePreviewButton	int8u		
42.1	FunclButtonPlusDials	int8u		
43.1	PreviewButtonPlusDials	int8u		
45.1	AssignMovieRecordButtonPlusDials	int8u		
46.1	FineTuneOptHighlightWeighted	int8u		
47.1 47.2	DynamicAreaAFDisplay	int8u int8u		
47.2	AFPointIllumination StoreByOrientation	int8u		
47.4	GroupAreaAFIllumination	int8u		
48.1	MatrixMetering	int8u		
48.2	LiveViewButtonOptions	int8u		
48.3	AFModeRestrictions	int8u		
49.1	LimitAFAreaModeSelection	int8u		
52.1	LensFocusFunctionButtons	int8u	&	0x3f
66.1	VerticalMultiSelector	int8u	&	0xff
67.1	AssignMB-D17FuncButton	int8u	&	0x3f
68.1	AssignMB-D17FuncButtonPlusDials	int8u	&	0x0f
70.1	AF-OnButton	int8u	&	0x3f
71.1	SubSelector	int8u	&	0x80
72.1	SubSelectorCenter	int8u		
73.1	SubSelectorPlusDials	int8u		
74.1	AssignMovieSubselector	int8u		
75.1	AssignMovieFunc1ButtonPlusDials	int8u		
75.2	AssignMoviePreviewButtonPlusDials	int8u		
76.1 77.1	AssignMovieSubselectorPlusDials	int8u int8u		
78.1	SyncReleaseMode Three-DTrackingWatchArea	int8u		
/ U . I	TITLE DILACATINGWALCHALEA	TIICOU	œ	OVOO

78.2	SubjectMotion	int8u	&	0x60
78.3	AFActivation	int8u	&	0x08
78.4	ShutterReleaseButtonAE-L	int8u	&	0x03
79.1	AssignMB-D17AF-OnButton	int8u	&	0x7f
80.1	Func2Button	int8u	&	0x3f
82.1	AssignMovieFunc2Button	int8u	&	0x70

## NikonCustom SettingsD610 Tags

Custom settings for the D610.

Index1	Tag Name	Writak	ole	2
0.1	AF-CPrioritySelection	 int8u	 &	0x80
0.2	AF-SPrioritySelection	int8u	&	0x20
0.3	NumberOfFocusPoints	int8u	&	0x10
0.4	FocusTrackingLockOn	int8u	&	0x07
1.1	FocusPointWrap	int8u	&	0x08
1.2	AFPointIllumination	int8u	&	0x06
1.3	AFAssist	int8u	&	0x01
5.1	EasyExposureCompensation	int8u	&	0x03
6.1	ExposureControlStep	int8u	&	0x40
6.2	ISOSensitivityStep	int8u	&	0x10
7.1	CenterWeightedAreaSize	int8u	&	0xe0
7.2	${ t Fine Tune Opt Matrix Metering}$	int8u	&	0x0f
8.1	FineTuneOptCenterWeighted	int8u	&	0xf0
8.2	FineTuneOptSpotMetering	int8u	&	0x0f
17.1	${ t ShutterReleaseButtonAE-L}$	int8u	&	0x02
18.1	StandbyTimer	int8u	&	0xf0
18.2	RemoteOnDuration	int8u	&	0x03
19.1	SelfTimerTime	int8u	&	0xc0
19.2	SelfTimerShotInterval	int8u	&	0x30
19.3	SelfTimerShotCount	int8u	&	0x0f
20.1	ImageReviewMonitorOffTime	int8u	&	0xe0
20.2	LiveViewMonitorOffTime	int8u	&	0x1c
21.1	MenuMonitorOffTime	int8u	&	0xe0
21.2	ShootingInfoMonitorOffTime	int8u	&	0x1c
35.1	PlaybackMonitorOffTime	int8u	&	0xe0

## NikonCustom SettingsZ6III Tags

Custom settings for the Z6III.

Index1	Tag Name	Writable
3	AF-CPrioritySelection	int8u
5	AF-SPrioritySelection	int8u
7	BlockShotAFResponse	int8u
11	AFPointSel	int8u
13	StoreByOrientation	int8u
15	AFActivation	int8u
16	AF-OnOutOfFocusRelease?	int8u
17	LimitAF-AreaModeSelPinpoint?	int8u
19	LimitAF-AreaModeSelWideAF_S?	int8u
20	LimitAF-AreaModeSelWideAF_L?	int8u
21	LimitAFAreaModeSelAuto?	int8u
22	FocusPointWrap?	int8u
23	ManualFocusPointIllumination?	int8u
24	DynamicAreaAFAssist?	int8u
26	AF-AssistIlluminator	int8u
27	ManualFocusRingInAFMode	int8u
29	ExposureControlStepSize	int8u
31	EasyExposureCompensation	int8u
33	${\tt CenterWeightedAreaSize}$	int8u
35	FineTuneOptMatrixMetering	int8s
37	FineTuneOptCenterWeighted	int8s
39	FineTuneOptSpotMetering	int8s
41	${ t Fine Tune Opt Highlight Weighted}$	int8s
43	ShutterReleaseButtonAE-L	int8u
45	SelfTimerTime	int8u

	ExifTool 13.24 Tag Names	
49	SelfTimerShotCount	int8u
53	SelfTimerShotInterval	int8u
55	PlaybackMonitorOffTime	int8u
57	MenuMonitorOffTime	int8u
59 61	<pre>ImageReviewMonitorOffTime ShootingInfoMonitorOffTime</pre>	int8u int8u
63	CLModeShootingSpeed	int8u
65	MaxContinuousRelease	no
69	SyncReleaseMode?	int8u
75	LimitSelectableImageAreaDX?	int8u
76	LimitSelectableImageArealTol?	int8u
77	LimitSelectableImageArea16To9?	int8u
78 81	FileNumberSequence FocusPeakingLevel?	int8u int8u
83	FocusPeakingHighlightColor?	int8u
85	ContinuousModeDisplay	int8u
87	FlashSyncSpeed	no
89	HighSpeedSync	int8u
91	FlashShutterSpeed	no
93	FlashExposureCompArea	int8u
95 97	AutoFlashISOSensitivity ModelingFlash	int8u int8u
97	AutoBracketModeM	int8u
101	AutoBracketOrder	int8u
103	Func1Button	int8u
119	Func2Button	int8u
135	AFOnButton	int8u
147	SubSelector?	int8u
159	AssignMovieRecordButton?	int8u
163 171	LensFunc1Button LensFunc2Button	int8u int8u
177	LensControlRing	int8u
179	MultiSelectorShootMode	int8u
183	MultiSelectorPlaybackMode	int8u
187	ShutterSpeedLock	int8u
188	ApertureLock	int8u
190	CmdDialsReverseRotation	int8u
195 197	UseDialWithoutHold? ReverseIndicators?	int8u int8u
199	MovieFunc1Button	int8u
205	MovieFunc2Button	int8u
211	MovieAF-OnButton	int8u
223	MovieLensControlRing	int8u
225	MovieMultiSelector?	int8u
229	MovieAFSpeed	int8u
<ul><li>231</li><li>233</li></ul>	MovieAFSpeedApply MovieAFTrackingSensitivity	int8u int8u
241	LCDIllumination?	int8u
242	ExtendedShutterSpeeds	int8u
245	FocusPointPersistence	int8u
257	FlashBurstPriority?	int8u
319	LimitAF-AreaModeSelDynamic_S?	int8u
320	LimitAF-AreaModeSelDynamic_M?	int8u
321	LimitAF-AreaModeSelDynamic_L?	int8u
323 325	LimitAF-AreaModeSel3DTracking? PlaybackFlickUp?	int8u int8u
329	PlaybackFlickDown?	int8u
333	ISOStepSize	int8u
340	TouchFn?	int8u
341	TouchFnRole?	int8u
345	TouchFnAreaWide?	int8u
347	TouchFnAreaTall?	int8u
350 351	EVFImageFrame? EVFGrid?	int8u int8u
353	VirtualHorizonStyle?	int8u
415	Func1ButtonPlaybackMode?	int8u
417	Func2ButtonPlaybackMode?	int8u
431	MovieRecordButtonPlaybackMode?	int8u
463	ControlRingResponse	int8u
559	FocusPeakingDisplay?	int8u

# NikonCustom SettingsZ8 Tags

Custom settings for the Z8.

Index1	Tag Name	Writable
1	CustomSettingsBank	int8u
3	AF-CPrioritySelection	int8u
5	AF-SPrioritySelection	int8u
7	BlockShotAFResponse	int8u
11	AFPointSel	int8u
13	StoreByOrientation	int8u
15	AFActivation	int8u
16	AF-OnOutOfFocusRelease?	int8u
17 19	LimitAF-AreaModeSelPinpoint? LimitAF-AreaModeSelWideAF_S?	int8u int8u
20	LimitAF-AreaModeSelWideAF L?	int8u
21	LimitAFAreaModeSelAuto?	int8u
22	FocusPointWrap?	int8u
23	ManualFocusPointIllumination?	int8u
24	DynamicAreaAFAssist?	int8u
25	AF-AssistIlluminator	int8u
26	ManualFocusRingInAFMode	int8u
27	ExposureControlStepSize	int8u
29	EasyExposureCompensation	int8u
31	${\tt CenterWeightedAreaSize}$	int8u
33	FineTuneOptMatrixMetering	int8s
35	FineTuneOptCenterWeighted	int8s
37	FineTuneOptSpotMetering	int8s
39	FineTuneOptHighlightWeighted	int8s
41	ShutterReleaseButtonAE-L	int8u
43 45	SelfTimerTime SelfTimerShotCount	int8u int8u
49	SelfTimerShotCount	int8u
51	PlaybackMonitorOffTime	int8u
53	MenuMonitorOffTime	int8u
55	ShootingInfoMonitorOffTime	int8u
57	ImageReviewMonitorOffTime	int8u
59	CLModeShootingSpeed	int8u
61	MaxContinuousRelease	no
65	SyncReleaseMode?	int8u
69	LimitSelectableImageAreaDX?	int8u
70	LimitSelectableImageArea1To1?	int8u
71	LimitSelectableImageArea16To9?	int8u
72	FileNumberSequence	int8u
73	FocusPeakingLevel?	int8u
75 01	FocusPeakingHighlightColor?	int8u
81 83	ContinuousModeDisplay FlashSyncSpeed	int8u no
85	HighSpeedSync	int8u
87	FlashShutterSpeed	no
89	FlashExposureCompArea	int8u
91	AutoFlashISOSensitivity	int8u
93	ModelingFlash	int8u
95	AutoBracketModeM	int8u
97	AutoBracketOrder	int8u
99	Func1Button	int8u
115	Func2Button	int8u
131	AFOnButton	int8u
143	SubSelector?	int8u
155	AssignMovieRecordButton?	int8u
159 167	LensFunc1Button	int8u
167 173	LensFunc2Button LensControlRing	int8u int8u
175	MultiSelectorShootMode	int8u
179	MultiSelectorPlaybackMode	int8u
183	ShutterSpeedLock	int8u
184	ApertureLock	int8u
186	CmdDialsReverseRotation	int8u

191	UseDialWithoutHold?	int8u
193	ReverseIndicators?	int8u
195	MovieFunc1Button	int8u
199	MovieFunc2Button	int8u
203	MovieAF-OnButton	int8u
215	MovieLensControlRing	int8u
217		int8u
	MovieMultiSelector?	
221	MovieAFSpeed	int8u
223	MovieAFSpeedApply	int8u
225	MovieAFTrackingSensitivity	int8u
257	LCDIllumination?	int8u
258	ExtendedShutterSpeeds	int8u
259	SubjectMotion	int8u
261	FocusPointPersistence	int8u
263	AutoFocusModeRestrictions?	int8u
		int8u
267	CHModeShootingSpeed	
273	FlashBurstPriority?	int8u
335	LimitAF-AreaModeSelDynamic_S?	int8u
336	LimitAF-AreaModeSelDynamic_M?	int8u
337	LimitAF-AreaModeSelDynamic_L?	int8u
339	LimitAF-AreaModeSel3DTracking?	int8u
341	PlaybackFlickUp?	int8u
345	PlaybackFlickDown?	int8u
349	ISOStepSize	int8u
355	ReverseFocusRing	int8u
356	EVFImageFrame?	int8u
357	EVFGrid?	int8u
359	VirtualHorizonStyle?	int8u
421	Func1ButtonPlaybackMode?	int8u
423	Func2ButtonPlaybackMode?	int8u
437	MovieRecordButtonPlaybackMode?	int8u
453	WBButtonPlaybackMode	int8u
459	CommandDialPlaybackMode?	int8u
461	CommandDialVideoPlaybackMode?	int8u
463	SubCommandDialPlaybackMode?	int8u
465	SubCommandDialVideoPlaybackMode?	int8u
467	FocusPointLock?	int8u
469	ControlRingResponse	int8u
515	MovieAFAreaMode?	int8u
529	ZebraPatternToneRange?	int8u
531	MovieZebraPattern?	int8u
533	MovieHighlightDisplayThreshold?	int8u
535	MovieMidtoneDisplayValue?	int8u
537	MovieMidtoneDisplayRange?	int8u~
541	MovieEVFGrid?	int8u
549	MovieShutterSpeedLock?	int8u
	<del>-</del>	
550	MovieFocusPointLock?	int8u
563	MatrixMetering?	int8u
564	AF-CFocusDisplay	int8u
565	FocusPeakingDisplay?	int8u
567	KeepExposure	int8u
585	StarlightView?	int8u
587	EVFWarmDisplayMode?	int8u
589	EVFWarmDisplayBrightness?	int8s
591	EVFReleaseIndicator?	int8u
601	MovieApertureLock?	int8u
607	FlickAdvanceDirection?	int8u
647	PreReleaseBurstLength	int8u
649	PostReleaseBurstLength	int8u
681	ViewModeShowEffectsOfSettings?	int8u
683	DispButton	int8u
753	ExposureDelay	int16u~

# NikonCustom SettingsZ9 Tags

Custom settings for the Z9.

Index1	Tag Name	Writable
1	CustomSettingsBank	int8u

	ExifTool 13.24 Tag Names	
3	AF-CPrioritySelection	int8u
5	AF-SPrioritySelection	int8u
7	BlockShotAFResponse	int8u
11	AFPointSel	int8u
13	StoreByOrientation	int8u
15	AFActivation	int8u
16	AF-OnOutOfFocusRelease?	int8u
17	LimitAF-AreaModeSelPinpoint?	int8u
19	LimitAF-AreaModeSelWideAF_S?	int8u
20 21	LimitAF-AreaModeSelWideAF_L? LimitAFAreaModeSelAuto?	int8u int8u
22	FocusPointWrap?	int8u
23	ManualFocusPointIllumination?	int8u
24	DynamicAreaAFAssist?	int8u
25	AF-AssistIlluminator	int8u
26	ManualFocusRingInAFMode	int8u
27	ExposureControlStepSize	int8u
29	EasyExposureCompensation	int8u
31	CenterWeightedAreaSize	int8u
33	FineTuneOptMatrixMetering	int8s
35	FineTuneOptCenterWeighted	int8s
37	FineTuneOptSpotMetering	int8s
39	FineTuneOptHighlightWeighted	int8s
41	ShutterReleaseButtonAE-L	int8u
43 45	SelfTimerTime SelfTimerShotCount	int8u
45 49	SelfTimerShotCount SelfTimerShotInterval	int8u int8u
51	PlaybackMonitorOffTime	int8u
53	MenuMonitorOffTime	int8u
55	ShootingInfoMonitorOffTime	int8u
57	ImageReviewMonitorOffTime	int8u
59	CLModeShootingSpeed	int8u
61	MaxContinuousRelease	no
65	SyncReleaseMode?	int8u
69	LimitSelectableImageAreaDX?	int8u
70	LimitSelectableImageArea1To1?	int8u
71	LimitSelectableImageArea16To9?	int8u
72	FileNumberSequence	int8u
73	FocusPeakingLevel?	int8u
75	FocusPeakingHighlightColor?	int8u
81 83	ContinuousModeDisplay FlashSyncSpeed	int8u
85	HighSpeedSync	no int8u
87	FlashShutterSpeed	no
89	FlashExposureCompArea	int8u
91	AutoFlashISOSensitivity	int8u
93	ModelingFlash	int8u
95	AutoBracketModeM	int8u
97	AutoBracketOrder	int8u
99	Func1Button	int8u
115	Func2Button	int8u
131	AFOnButton	int8u
143	SubSelector?	int8u
155	AssignMovieRecordButton?	int8u
159 167	LensFunc1Button LensFunc2Button	int8u int8u
173	LensControlRing	int8u
175	MultiSelectorShootMode	int8u
179	MultiSelectorPlaybackMode	int8u
183	ShutterSpeedLock	int8u
184	ApertureLock	int8u
186	CmdDialsReverseRotation	int8u
191	UseDialWithoutHold?	int8u
193	ReverseIndicators?	int8u
195	MovieFunc1Button	int8u
199	MovieFunc2Button	int8u
203	MovieAF-OnButton	int8u
207	MovieMultiSelector?	int8u
215	MovieLensControlRing	int8u
221	MovieAFSpeed	int8u

	ExitTool 13.24 Tag Names	
223	MovieAFSpeedApply	int8u
225	MovieAFTrackingSensitivity	int8u
257	LCDIllumination?	int8u
258	ExtendedShutterSpeeds	int8u
259	SubjectMotion	int8u
261	FocusPointPersistence	int8u
263	AutoFocusModeRestrictions?	int8u
267	CHModeShootingSpeed	int8u
269.1	LimitReleaseModeSelCL?	int8u & 0x02
269.2 269.3	LimitReleaseModeSelCH? LimitReleaseModeSelC30?	int8u & 0x04 int8u & 0x10
269.3	LimitReleaseModeSelC120?	int8u & 0x10
269.5	LimitReleaseModeSelSelf?	int8u & 0x40
273	FlashBurstPriority?	int8u
277	VerticalFuncButton	int8u
281	Func3Button	int8u
285	VerticalAFOnButton	int8u
293	VerticalMultiSelectorPlaybackMode?	int8u
295	MovieFunc3Button	int8u
335	LimitAF-AreaModeSelDynamic_S?	int8u
336	LimitAF-AreaModeSelDynamic_M?	int8u
337	LimitAF-AreaModeSelDynamic_L?	int8u
339	LimitAF-AreaModeSel3DTracking?	int8u
341	PlaybackFlickUp?	int8u
345	PlaybackFlickDown?	int8u
349	ISOStepSize	int8u
355	ReverseFocusRing	int8u
356	EVFImageFrame?	int8u
357	EVFGrid?	int8u
359	VirtualHorizonStyle?	int8u
373	Func4Button?	int8u
379 381	AudioButton? QualityButton?	int8u int8u
399	VerticalMultiSelector?	int8u
421	Func1ButtonPlaybackMode?	int8u
423	Func2ButtonPlaybackMode?	int8u
425	Func3ButtonPlaybackMode?	int8u
431	Func4ButtonPlaybackMode?	int8u
437	MovieRecordButtonPlaybackMode?	int8u
439	VerticalFuncButtonPlaybackMode?	int8u
441	AudioButtonPlaybackMode?	int8u
447	QualityButtonPlaybackMode?	int8u
453	WhiteBalanceButtonPlaybackMode?	int8u
459	CommandDialPlaybackMode?	int8u
463	SubCommandDialPlaybackMode?	int8u
467	FocusPointLock?	int8u
469	ControlRingResponse	int8u
481	VerticalMovieFuncButton?	int8u
505 515	VerticalMovieAFOnButton? MovieAFAreaMode?	int8u
515	HDMIViewAssist?	int8u int8u
529	ZebraPatternToneRange?	int8u
531	MovieZebraPattern?	int8u
533	MovieHighlightDisplayThreshold?	int8u
535	MovieMidtoneDisplayValue?	int8u
537	MovieMidtoneDisplayRange?	int8u~
541	MovieEVFGrid?	int8u
549	MovieShutterSpeedLock?	int8u
550	MovieFocusPointLock?	int8u
563	MatrixMetering?	int8u
564	AF-CFocusDisplay	int8u
565	FocusPeakingDisplay?	int8u
567	KeepExposure	int8u
585	StarlightView?	int8u
587	EVFWarmDisplayMode?	int8u
589	EVFWarmDisplayBrightness?	int8s
591	EVFReleaseIndicator?	int8u
601	MovieApertureLock? FlickAdvanceDirection?	int8u
607	FIICKAUVAIICEDILECCIOII:	int8u

## NikonCustom SettingsZ9v4 Tags

Custom settings for the Z9.

- 1 1		1. 1.7
Index1	Tag Name	Writable
1	CustomSettingsBank	int8u
3	AF-CPrioritySelection	int8u
5	AF-SPrioritySelection	int8u
7	BlockShotAFResponse	int8u
11	AFPointSel	int8u
13	StoreByOrientation	int8u
15	AFActivation	int8u
16	AF-OnOutOfFocusRelease?	int8u
17	LimitAF-AreaModeSelPinpoint?	int8u
19	LimitAF-AreaModeSelWideAF_S?	int8u
20 21	LimitAF-AreaModeSelWideAF_L? LimitAFAreaModeSelAuto?	int8u int8u
22	FocusPointWrap?	int8u
23	ManualFocusPointIllumination?	int8u
24	DynamicAreaAFAssist?	int8u
25	AF-AssistIlluminator	int8u
26	ManualFocusRingInAFMode	int8u
27	ExposureControlStepSize	int8u
29	EasyExposureCompensation	int8u
31	CenterWeightedAreaSize	int8u
33	FineTuneOptMatrixMetering	int8s
35	FineTuneOptCenterWeighted	int8s
37	FineTuneOptSpotMetering	int8s
39	FineTuneOptHighlightWeighted	int8s
41	ShutterReleaseButtonAE-L	int8u
43	SelfTimerTime	int8u
45	SelfTimerShotCount	int8u
49	SelfTimerShotInterval	int8u
51	PlaybackMonitorOffTime	int8u
53	MenuMonitorOffTime	int8u
55	ShootingInfoMonitorOffTime	int8u
57	ImageReviewMonitorOffTime	int8u
59 61	CLModeShootingSpeed MaxContinuousRelease	int8u
65	SyncReleaseMode?	no int8u
69	LimitSelectableImageAreaDX?	int8u
70	LimitSelectableImageArealTol?	int8u
71	LimitSelectableImageArea16To9?	int8u
72	FileNumberSequence	int8u
73	FocusPeakingLevel?	int8u
75	FocusPeakingHighlightColor?	int8u
81	ContinuousModeDisplay	int8u
83	FlashSyncSpeed	no
85	HighSpeedSync	int8u
87	FlashShutterSpeed	no
89	FlashExposureCompArea	int8u
91	AutoFlashISOSensitivity	int8u
93	ModelingFlash	int8u
95	AutoBracketModeM	int8u
97	AutoBracketOrder	int8u
99 115	Func1Button Func2Button	int8u int8u
131	AFOnButton	int8u
143	SubSelector?	int8u
155	AssignMovieRecordButton?	int8u
159	LensFunc1Button	int8u
167	LensFunc2Button	int8u
173	LensControlRing	int8u
175	MultiSelectorShootMode	int8u
179	MultiSelectorPlaybackMode	int8u
183	ShutterSpeedLock	int8u
184	ApertureLock	int8u
186	CmdDialsReverseRotation	int8u
191	UseDialWithoutHold?	int8u

	ExifTool 13.24 Tag Names	
193	ReverseIndicators?	int8u
195	MovieFunc1Button	int8u
199	MovieFunc2Button	int8u
203	MovieAF-OnButton	int8u
207 215	MovieMultiSelector? MovieLensControlRing	int8u int8u
221	MovieAFSpeed	int8u
223	MovieAFSpeedApply	int8u
225	MovieAFTrackingSensitivity	int8u
279	LCDIllumination?	int8u
280	ExtendedShutterSpeeds	int8u
281	SubjectMotion	int8u
283 285	FocusPointPersistence AutoFocusModeRestrictions?	int8u int8u
289	CHModeShootingSpeed	int8u
293.1	LimitReleaseModeSelCL?	int8u & 0x02
293.2	LimitReleaseModeSelCH?	int8u & 0x04
293.3	LimitReleaseModeSelC30?	int8u & 0x10
293.4	LimitReleaseModeSelC120?	int8u & 0x40
293.5	LimitReleaseModeSelSelf?	int8u & 0x80
297	FlashBurstPriority? VerticalFuncButton	int8u
301 305	Func3Button	int8u int8u
309	VerticalAFOnButton	int8u
317	VerticalMultiSelectorPlaybackMode?	int8u
319	MovieFunc3Button	int8u
359	LimitAF-AreaModeSelDynamic_S?	int8u
360	LimitAF-AreaModeSelDynamic_M?	int8u
361	LimitAF-AreaModeSelDynamic_L?	int8u
363	LimitAF-AreaModeSel3DTracking?	int8u
365 369	PlaybackFlickUp? PlaybackFlickDown?	int8u int8u
373	ISOStepSize	int8u
379	ReverseFocusRing	int8u
380	EVFImageFrame?	int8u
381	EVFGrid?	int8u
383	VirtualHorizonStyle?	int8u
397	Func4Button?	int8u
403 405	AudioButton? QualityButton?	int8u int8u
423	VerticalMultiSelector?	int8u
445	Func1ButtonPlaybackMode?	int8u
447	Func2ButtonPlaybackMode?	int8u
449	Func3ButtonPlaybackMode?	int8u
455	Func4ButtonPlaybackMode?	int8u
461	MovieRecordButtonPlaybackMode?	int8u
463 465	VerticalFuncButtonPlaybackMode? AudioButtonPlaybackMode?	int8u int8u
471	QualityButtonPlaybackMode?	int8u
477	WhiteBalanceButtonPlaybackMode?	int8u
483	CommandDialPlaybackMode?	int8u
485	CommandDialVideoPlaybackMode?	int8u
487	SubCommandDialPlaybackMode?	int8u
489	SubCommandDialVideoPlaybackMode?	int8u
491 493	FocusPointLock? ControlRingResponse	int8u int8u
505	VerticalMovieFuncButton?	int8u
529	VerticalMovieAFOnButton?	int8u
539	MovieAFAreaMode?	int8u
551	HDMIViewAssist?	int8u
553	ZebraPatternToneRange?	int8u
555	MovieZebraPattern?	int8u
557 550	MovieHighlightDisplayThreshold?	int8u
559 561	MovieMidtoneDisplayValue? MovieMidtoneDisplayRange?	int8u int8u~
565	MovieEVFGrid?	int8u
573	MovieShutterSpeedLock?	int8u
574	MovieFocusPointLock?	int8u
587	MatrixMetering?	int8u
588	AF-CFocusDisplay	int8u

589	FocusPeakingDisplay?	int8u
591	KeepExposure	int8u
609	StarlightView?	int8u
611	EVFWarmDisplayMode?	int8u
613	EVFWarmDisplayBrightness?	int8s
615	EVFReleaseIndicator?	int8u
625	MovieApertureLock?	int8u
631	FlickAdvanceDirection?	int8u

## NikonSettings Tags

User settings for newer Nikon models. A number of the tags are marked as Unknown only to reduce the volume of the normal output.

Tag ID	Tag Name	Writable
$0 \times 0001$	ISOAutoHiLimit	no
0x0002	ISOAutoFlashLimit	no
$0 \times 0003$	ISOAutoShutterTime	no
0x000b	FlickerReductionShooting	no
0x000c	FlickerReductionIndicator	no
0x000d	MovieISOAutoHiLimit	no
0x000e	MovieISOAutoControlManualMode	no
0x000f	MovieWhiteBalanceSameAsPhoto	no
0x001d 0x001e	AF-CPrioritySel	no
0x001e $0x0020$	AF-SPrioritySel AFPointSel	no no
0x0020 $0x0022$	AFActivation	_
0x0022 0x0023	FocusPointWrap	no no
0x0025	ManualFocusPointIllumination	no
0x0025	AF-AssistIlluminator	no
0x0020 0x0027	ManualFocusRingInAFMode	no
0x0027 $0x0029$	ISOStepSize	no
0x002a	ExposureControlStepSize	no
0x002b	EasyExposureCompensation	no
0x002c	MatrixMetering	no
0x002d	CenterWeightedAreaSize	no
0x002f	FineTuneOptMatrixMetering	no
0x0030	FineTuneOptCenterWeighted	no
0x0031	FineTuneOptSpotMetering	no
$0 \times 0032$	FineTuneOptHighlightWeighted	no
$0 \times 0033$	ShutterReleaseButtonAE-L	no
$0 \times 0034$	StandbyMonitorOffTime	no
0x0035	SelfTimerTime	no
0x0036	SelfTimerShotCount	no
$0 \times 0037$	SelfTimerShotInterval	no
$0 \times 0038$	PlaybackMonitorOffTime	no
$0 \times 0039$	MenuMonitorOffTime	no
0x003a	ShootingInfoMonitorOffTime	no
0x003b	ImageReviewMonitorOffTime	no
0x003c	LiveViewMonitorOffTime	no
0x003e	CLModeShootingSpeed	no
0x003f	MaxContinuousRelease	no
$0 \times 0040$	ExposureDelayMode	no
$0 \times 0.041$	ElectronicFront-CurtainShutter	no
$0 \times 0042$	FileNumberSequence	no
$0 \times 0.043$	FramingGridDisplay	no
$0 \times 0045$	LCDIllumination	no
$0 \times 0046$	OpticalVR	no
$0 \times 0047$ $0 \times 0048$	FlashSyncSpeed	no
0x0048 $0x0049$	FlashShutterSpeed	no
0x0049 0x004a	FlashExposureCompArea AutoFlashISOSensitivity	no
0x004a 0x0051	AssignBktButton	no no
0x0051 $0x0052$	AssignMovieRecordButton	no
0x0052 $0x0053$	MultiSelectorShootMode	no
0x0053	MultiSelectorPlaybackMode	no
0x0054	MultiSelectorLiveView	no
0x0050	CmdDialsReverseRotExposureComp?	no
0x0050	CmdDialsChangeMainSubExposure?	no
0x005a	CmdDialsChangeMainSub	no
	<u> </u>	-

	ExilTool 13.24 Tag Names	
0x005b	CmdDialsMenuAndPlayback	no
0x005c	SubDialFrameAdvance	no
0x005d	ReleaseButtonToUseDial	no
0x005e	ReverseIndicators	no
$0 \times 0062$	MovieShutterButton	no
0x0063	Language	no
0x006c	ShootingInfoDisplay	no
$0 \times 0074$	FlickAdvanceDirection	no
$0 \times 0075$	HDMIOutputResolution	no
$0 \times 0077$	HDMIOutputRange	no
$0 \times 0080$	RemoteFuncButton	no
0x008b	CmdDialsReverseRotation	no
0x008d	FocusPeakingHighlightColor	no
0x008e	ContinuousModeDisplay	no
0x008f	ShutterSpeedLock	no
0x0090	ApertureLock	no
$0 \times 0091$	MovieHighlightDisplayThreshold	no
0x0092	HDMIExternalRecorder	no
$0 \times 0093$	BlockShotAFResponse	no
0x0094	SubjectMotion	no
$0 \times 0095$	Three-DTrackingFaceDetection	no
$0 \times 0097$	StoreByOrientation	no
$0 \times 0099$	DynamicAreaAFAssist	no
0x009a	ExposureCompStepSize	no
0x009b	SyncReleaseMode	no
$0 \times 009c$	ModelingFlash	no
0x009d	AutoBracketModeM	no
0x009e	PreviewButton	no
0x00a0	Func1Button	no
0x00a2	Func2Button	no
0x00a3	AF-OnButton	no
0x00a4	SubSelector	no
0x00a5	SubSelectorCenter	no
0x00a7	LensFunc1Button	no
0x00a8	CmdDialsApertureSetting	no
0x00a9	MultiSelector	no
0x00aa	LiveViewButtonOptions	no
0x00ab	LightSwitch	no
0x00b1	MoviePreviewButton	no
0 001 0	MovieFunclButton	no
0x00b3	MovieFunc1Button	no
0001-5	MovieFunc2Button	no
$0 \times 0.005$	MovieFunc2Button	no
0x00b6	AssignMovieSubselector	no
0x00b8	LimitAFAreaModeSelD9?	no
0x00b9 0x00bc	LimitAFAreaModeSelD25? LimitAFAreaModeSel3D?	no
0x00bd		no
0x00ba 0x00be	LimitAFAreaModeSelGroup? LimitAFAreaModeSelAuto?	no
0x00be	LimitSelectableImageArea5To4?	no no
0x00c1	LimitSelectableImageArealTo1?	no
0x00d4	PhotoShootingMenuBank	no
0x00d4	CustomSettingsBank	no
0x00d6	LimitAF-AreaModeSelPinpoint?	no
0x00d7	LimitAF-AreaModeSelDynamic?	no
0x00d8	LimitAF-AreaModeSelWideAF S?	no
0x00d9	LimitAF-AreaModeSelWideAF L?	no
0x00da	LowLightAF	no
0x00db	LimitSelectableImageAreaDX?	no
0x00dc	LimitSelectableImageArea5To4?	no
0x00dd	LimitSelectableImageArealTo1?	no
0x00de	LimitSelectableImageArea16To9?	no
0x00df	ApplySettingsToLiveView	no
0x00e0	FocusPeakingLevel	no
0x00ea	LensControlRing	no
0x00ed	MovieMultiSelector	no
0x00ee	MovieAFSpeed	no
0x00ef	MovieAFSpeedApply	no
0x00f0	MovieAFTrackingSensitivity	no
0x00f1	MovieHighlightDisplayPattern	no

	EXIITOOI 13.24 Tag Names	
0x00f2	SubDialFrameAdvanceRating5?	no
0x00f3	SubDialFrameAdvanceRating4?	no
0x00f4	SubDialFrameAdvanceRating3?	no
0x00f5	SubDialFrameAdvanceRating2?	no
0x00f6	SubDialFrameAdvanceRating1?	no
0x00f7	SubDialFrameAdvanceRating0?	no
0x00f9	MovieAF-OnButton	no
0x00fb	SecondarySlotFunction	no
0x00fc 0x00fd	SilentPhotography ExtendedShutterSpeeds	no no
0x001d 0x0102	HDMIBitDepth	no
0x0102	HDMIOutputHDR	no
0x0103	HDMIViewAssist	no
0x0109	BracketSet	no
0x010a	BracketProgram	no
0x010b	BracketIncrement	no
0x010c	BracketIncrement	no
0x010e	MonitorBrightness	no
$0 \times 0116$	GroupAreaC1	no
$0 \times 0117$	AutoAreaAFStartingPoint	no
$0 \times 0118$	FocusPointPersistence	no
$0 \times 0119$	LimitAFAreaModeSelD49?	no
0x011a	LimitAFAreaModeSelD105?	no
0x011b	LimitAFAreaModeSelGroupC1?	no
0x011c	LimitAFAreaModeSelGroupC2?	no
0x011d	AutoFocusModeRestrictions	no
0x011e 0x011f	FocusPointBrightness	no
0x0111 0x0120	CHModeShootingSpeed CLModeShootingSpeed	no no
0x0120 0x0121	QuietShutterShootingSpeed	no
0x0121	LimitReleaseModeSelCL?	no
0x0122	LimitReleaseModeSelCH?	no
0x0124	LimitReleaseModeSelQ?	no
$0 \times 0125$	LimitReleaseModeSelTimer?	no
0x0126	LimitReleaseModeSelMirror-Up?	no
$0 \times 0127$	LimitSelectableImageArea16To9?	no
$0 \times 0128$	RearControPanelDisplay	no
0x0129	FlashBurstPriority	no
0x012a	RecallShootFuncExposureMode	no
$0 \times 012b$	RecallShootFuncShutterSpeed	no
0x012c	RecallShootFuncAperture	no
0x012d	RecallShootFuncExposureComp	no
0x012e	RecallShootFuncISO	no
0x012f	RecallShootFuncMeteringMode RecallShootFuncWhiteBalance	no
0x0130 0x0131	RecallShootFuncAFAreaMode	no
0x0131 $0x0132$	RecallShootFuncFocusTracking	no no
0x0132 $0x0133$	RecallShootFuncAF-On	no
0x0133	VerticalFuncButton	no
0x0135	Func3Button	no
0x0136	VerticalAF-OnButton	no
$0 \times 0137$	VerticalMultiSelector	no
$0 \times 0138$	MeteringButton	no
$0 \times 0139$	PlaybackFlickUp	no
0x013a	PlaybackFlickUpRating	no
0x013b	PlaybackFlickDown	no
0x013c	PlaybackFlickDownRating	no
0x013d	MovieFunc3Button	no
$0 \times 0150$	ShutterType	no
0x0151	LensFunc2Button	no
$0 \times 0158$	USBPowerDelivery	no
0x0159	EnergySavingMode	no
0x015c	BracketingBurstOptions	no
0x015e	PrimarySlot	no
0x015f 0x0160	ReverseFocusRing VerticalFuncButton	no
0x0160 0x0161	VerticalFuncButton VerticalAFOnButton	no
0x0161 0x0162	Vertical MultiSelector	no no
0x0162 0x0164	VerticalMovieFuncButton	no
0x0164	VerticalMovieAFOnButton	no

$0 \times 0169$	LimitAF-AreaModeSelAutoPeople?	no
0x016a	LimitAF-AreaModeSelAutoAnimals?	no
0x016b	LimitAF-AreaModeSelWideLPeople?	no
0x016c	LimitAF-AreaModeSelWideLAnimals?	no
0x016d	SaveFocus	no
0x016e	AFAreaMode	no
0x016f	MovieAFAreaMode	no
$0 \times 0170$	PreferSubSelectorCenter	no
$0 \times 0171$	KeepExposureWithTeleconverter	no
$0 \times 0174$	FocusPointSelectionSpeed	no

## Nintendo Tags

Tag ID	Tag Name	Writable
0x1101	CameraInfo	Nintendo CameraInfo

## Nintendo CameraInfo Tags

Tag Name	Writable
ModelID	undef[4]
TimeStamp	int32u
InternalSerialNumber	undef[4]
Parallax	float
Category	int16u
	ModelID TimeStamp InternalSerialNumber Parallax

### Olympus Tags

Tags 0x0000 through 0x0103 are used by some older Olympus cameras, and are the same as Konica/Minolta tags. These tags are also used for some models from other brands such as Acer, BenQ, Epson, Hitachi, HP, Maginon, Minolta, Pentax, Ricoh, Samsung, Sanyo, SeaLife, Sony, Supra and Vivitar.

Tag ID	Tag Name	Writable
0×0000	MakerNoteVersion	undef
0x0001	MinoltaCameraSettingsOld	Minolta CameraSettings
0x0003	MinoltaCameraSettings	Minolta CameraSettings
$0 \times 0040$	CompressedImageSize	int32u
0x0081	PreviewImageData	no
0x0088	PreviewImageStart	no
0x0089	PreviewImageLength	no
$0 \times 0100$	ThumbnailImage	undef
$0 \times 0104$	BodyFirmwareVersion	string
$0 \times 0200$	SpecialMode	int32u[3]~
0x0201	Quality	int16u~
0x0202	Macro	int16u
$0 \times 0203$	BWMode	int16u
$0 \times 0204$	DigitalZoom	rational64u
$0 \times 0205$	FocalPlaneDiagonal	rational64u
$0 \times 0206$	LensDistortionParams	int16s[6]
$0 \times 0207$	CameraType	string
0x0208	TextInfo	Olympus TextInfo
0x0209	CameraID	string
0x020b	EpsonImageWidth	int32u
0x020c	EpsonImageHeight	int32u
0x020d	EpsonSoftware	string
0x0280	PreviewImage	int8u
0x0300	PreCaptureFrames	int16u
0x0301	WhiteBoard	int16u
0x0302	OneTouchWB	int16u
0x0303	WhiteBalanceBracket	int16u
0x0304	WhiteBalanceBias	int16u
$0 \times 0400$	SensorArea	undef[8]
$0 \times 0401$	BlackLevel	int32u[4]
0x0403	SceneMode	int16u
$0 \times 0404$	SerialNumber	string
$0 \times 0405$	Firmware	string
0x0e00	PrintIM	PrintIM
0x0f00	DataDump	no

	ExifTool 13.24 Tag Names	
0x0f01	DataDump2	no
0x0f04	ZoomedPreviewStart	int32u*
0x0f05	ZoomedPreviewLength	int32u*
0x0f06	ZoomedPreviewSize	int16u[2]
0x1000	ShutterSpeedValue	rational64s
0x1001	ISOValue	rational64s
0x1002	ApertureValue	rational64s
0x1003	BrightnessValue	rational64s
0x1004	FlashMode	int16u
0x1005	FlashDevice	int16u rational64s
0x1006 0x1007	ExposureCompensation SensorTemperature	int16s
0x1007	LensTemperature	int16s
0x1000	LightCondition	int16u
0x100a	FocusRange	int16u
0x100b	FocusMode	int16u
0x100c	ManualFocusDistance	rational64u
0x100d	ZoomStepCount	int16u
0x100e	FocusStepCount	int16u
0x100f	Sharpness	int16u
0x1010	FlashChargeLevel	int16u
0x1011	ColorMatrix	int16u[9]
0x1012	BlackLevel	int16u[4]
0x1013	ColorTemperatureBG?	int16u
0x1014	ColorTemperatureRG?	int16u
0x1015	WBMode	int16u[2]
0x1017	RedBalance	int16u[2]
0x1018 0x1019	BlueBalance ColorMatrixNumber	int16u[2] int16u
0x1019 0x101a	SerialNumber	string
0x101a	ExternalFlashAE1_0?	int32u
0x101c	ExternalFlashAE2_0?	int32u
0x101d	InternalFlashAE1_0?	int32u
0x101e	InternalFlashAE2_0?	int32u
0x101f	ExternalFlashAE1?	int32u
0x1020	ExternalFlashAE2?	int32u
0x1021	InternalFlashAE1?	int32u
0x1022	InternalFlashAE2?	int32u
0x1023	FlashExposureComp	rational64s
0x1024	InternalFlashTable	int16u
0x1025	ExternalFlashGValue	rational64s
0x1026	ExternalFlashBounce	int16u
0x1027 0x1028	ExternalFlashZoom ExternalFlashMode	int16u int16u
0x1028 $0x1029$	Contrast	int16u
0x1025 0x102a	SharpnessFactor	int16u
0x102b	ColorControl	int16u[6]
0x102c	ValidBits	int16u[2]
0x102d	CoringFilter	int16u
0x102e	OlympusImageWidth	int32u
0x102f	OlympusImageHeight	int32u
0x1030	SceneDetect	int16u
0x1031	SceneArea?	int32u[8]
0x1033	SceneDetectData?	int32u[720]
0x1034	CompressionRatio	rational64u
0x1035	PreviewImageValid	int32u
0x1036	PreviewImageStart	int32u*
0x1037	PreviewImageLength	int32u*
0x1038	AFResult	int16u
0x1039	CCDScanMode NoiseReduction	int16u int16u
0x103a 0x103b	FocusStepInfinity	int16u
0x103b	FocusStepNear	int16u
0x103d	LightValueCenter	rational64s
0x103a	LightValuePeriphery	rational64s
0x103£	FieldCount?	int16u
0x2010	Equipment	Olympus Equipment
	EquipmentIFD	Olympus Equipment
0x2020	CameraSettings	Olympus CameraSettings
	CameraSettingsIFD	Olympus CameraSettings

0x2030	RawDevelopment	Olympus	RawDevelopment
0112030	RawDevelopmentIFD		RawDevelopment
0x2031	RawDev2		RawDevelopment2
0112001	RawDev2IFD		RawDevelopment2
$0 \times 2040$	ImageProcessing	4 1	ImageProcessing
	ImageProcessingIFD		ImageProcessing
0x2050	FocusInfo		FocusInfo
	FocusInfoIFD		FocusInfo
	CameraParameters	undef	
0x2100	Olympus2100	Olympus	FE
	Olympus2100IFD	Olympus	
0x2200	Olympus2200	Olympus	FE
	Olympus2200IFD	Olympus	FE
0x2300	Olympus2300	Olympus	FE
	Olympus2300IFD	Olympus	FE
0x2400	Olympus2400	Olympus	FE
	Olympus2400IFD	Olympus	FE
0x2500	Olympus2500	Olympus	FE
	Olympus2500IFD	Olympus	FE
0x2600	Olympus2600	Olympus	FE
	Olympus2600IFD	Olympus	FE
0x2700	Olympus2700	Olympus	FE
	Olympus2700IFD	Olympus	
0x2800	Olympus2800	Olympus	
	Olympus2800IFD	Olympus	
0x2900	Olympus2900	Olympus	
	Olympus2900IFD	Olympus	
0x3000	RawInfo		RawInfo
	RawInfoIFD		RawInfo
0x4000	MainInfo	Olympus	
	MainInfoIFD	Olympus	
0x5000	UnknownInfo		UnknownInfo
	UnknownInfoIFD	Olympus	UnknownInfo

# Olympus TextInfo Tags

This information is in text format (similar to APP12 information, but with spaces instead of linefeeds). Below are tags which have been observed, but any information found here will be extracted, even if the tag is not listed.

Tag ID	Tag Name	Writable
'Resolution'	Resolution	no
'Type'	CameraType	no

## Olympus Equipment Tags

Tag ID	Tag Name	Writable
0x0000	EquipmentVersion	undef[4]
$0 \times 0100$	CameraType2	string[6]
$0 \times 0101$	SerialNumber	string[32]
$0 \times 0102$	InternalSerialNumber	string[32]
$0 \times 0103$	FocalPlaneDiagonal	rational64u
$0 \times 0104$	BodyFirmwareVersion	int32u
$0 \times 0201$	LensType	int8u[6]
0x0202	LensSerialNumber	string[32]
0x0203	LensModel	string
$0 \times 0204$	LensFirmwareVersion	int32u
0x0205	MaxApertureAtMinFocal	int16u
0x0206	MaxApertureAtMaxFocal	int16u
0x0207	MinFocalLength	int16u
0x0208	MaxFocalLength	int16u
0x020a	MaxAperture	int16u
0x020b	LensProperties	int16u
0x0301	Extender	int8u[6]
0x0302	ExtenderSerialNumber	string[32]
0x0303	ExtenderModel	string
0x0304	ExtenderFirmwareVersion	int32u

$0 \times 0403$	ConversionLens	string
$0 \times 1000$	FlashType	int16u
$0 \times 1001$	FlashModel	int16u
0x1002	FlashFirmwareVersion	int32u
$0 \times 1003$	FlashSerialNumber	string[32]

## Olympus CameraSettings Tags

Tag ID	Tag Name	Writable
00000		
$0 \times 0000$ $0 \times 0100$	CameraSettingsVersion PreviewImageValid	undef[4] int32u
0x0100	PreviewImageStart	int32u*
0x0101	PreviewImageLength	int32u*
0x0202	ExposureMode	int16u
0x0201	AELock	int16u
0x0202	MeteringMode	int16u
$0 \times 0203$	ExposureShift	rational64s
$0 \times 0204$	NDFilter	yes
0x0300	MacroMode	int16u
$0 \times 0301$	FocusMode	int16u[n]
0x0302	FocusProcess	int16u[n]
0x0303	AFSearch	int16u
$0 \times 0304$	AFAreas	int32u[64]~
0x0305 0x0306	AFPointSelected AFFineTune	rational64s[5] int8u
0x0300 $0x0307$	AFFineTuneAdj	int16s[3]
0x0307 0x0308	FocusBracketStepSize	int8u
0x0300	AISubjectTrackingMode	int16u
$0 \times 0400$	FlashMode	int16u
0x0401	FlashExposureComp	rational64s
$0 \times 0403$	FlashRemoteControl	int16u
$0 \times 0404$	FlashControlMode	int16u[n]
$0 \times 0405$	FlashIntensity	rational64s[n]
$0 \times 0406$	ManualFlashStrength	rational64s[n]
$0 \times 0500$	WhiteBalance2	int16u
0x0501	WhiteBalanceTemperature	int16u
0x0502	WhiteBalanceBracket	int16s
$0 \times 0503$	CustomSaturation ModifiedSaturation	int16s[3]~ int16u
$0 \times 0504$ $0 \times 0505$	ContrastSetting	int16s[3]
0x0505	SharpnessSetting	int16s[3]
0x0500	ColorSpace	int16u
0x0509	SceneMode	int16u
0x050a	NoiseReduction	int16u
0x050b	DistortionCorrection	int16u
0x050c	ShadingCompensation	int16u
0x050d	CompressionFactor	rational64u
0x050f	Gradation	int16s[n]
$0 \times 0520$	PictureMode	int16u[n]
$0 \times 0521$	PictureModeSaturation	int16s[3]
$0 \times 0522$	PictureModeHue?	intl6s
$0 \times 0523$ $0 \times 0524$	PictureModeContrast PictureModeSharpness	int16s[3] int16s[3]
0x0524 $0x0525$	PictureModeSMarphess PictureModeBWFilter	int16s
0x0525 $0x0526$	PictureModeTone	int16s
0x0520	NoiseFilter	int16s[3]
0x0529	ArtFilter	int16u[4]
0x052c	MagicFilter	int16u[4]
0x052d	PictureModeEffect	int16s[3]
0x052e	ToneLevel	yes
0x052f	ArtFilterEffect	int16u[20]
$0 \times 0532$	ColorCreatorEffect	int16s[6]
$0 \times 0537$	MonochromeProfileSettings	int16s[6]
0x0538	FilmGrainEffect ColorProfileSettings	int16s
0x0539 0x053a	ColorProfileSettings MonochromeVignetting	int16s[14] int16s
0x053a 0x053b	MonochromeColor	int16s
0x0530	DriveMode	int16u[n]~
0x0601	PanoramaMode	int16u~

0x0603	ImageQuality2	int16u
$0 \times 0604$	ImageStabilization	int32u
$0 \times 0804$	StackedImage	int32u[2]
$0 \times 0900$	ManometerPressure	int16u
0x0901	ManometerReading	int32s[2]
$0 \times 0902$	ExtendedWBDetect	int16u
$0 \times 0903$	RollAngle	int16s[2]
$0 \times 0904$	PitchAngle	int16s[2]
$0 \times 0908$	DateTimeUTC	string

## Olympus RawDevelopment Tags

0x0000 RawDevVersion unde	ef[4]
0x0100 RawDevExposureBiasValue rat:	ional64s
0x0101 RawDevWhiteBalanceValue int:	16u
0x0102 RawDevWBFineAdjustment int:	16s
0x0103 RawDevGrayPoint int:	16u[3]
0x0104 RawDevSaturationEmphasis int	16s[3]
0x0105 RawDevMemoryColorEmphasis int:	16u
0x0106 RawDevContrastValue int:	16s[3]
0x0107 RawDevSharpnessValue int:	16s[3]
0x0108 RawDevColorSpace int:	16u
0x0109 RawDevEngine int:	16u
0x010a RawDevNoiseReduction int	16u
0x010b RawDevEditStatus int:	16u
0x010c RawDevSettings int	16u

# Olympus RawDevelopment2 Tags

Tag ID	Tag Name	Writable
$0 \times 0 0 0 0$	RawDevVersion	undef[4]
$0 \times 0100$	RawDevExposureBiasValue	rational64s
$0 \times 0101$	RawDevWhiteBalance	int16u
$0 \times 0102$	RawDevWhiteBalanceValue	int16u
$0 \times 0103$	RawDevWBFineAdjustment	int16s
$0 \times 0104$	RawDevGrayPoint	int16u[3]
$0 \times 0105$	RawDevContrastValue	int16s[3]
0x0106	RawDevSharpnessValue	int16s[3]
$0 \times 0107$	RawDevSaturationEmphasis	int16s[3]
$0 \times 0108$	RawDevMemoryColorEmphasis	int16u
$0 \times 0109$	RawDevColorSpace	int16u
0x010a	RawDevNoiseReduction	int16u
0x010b	RawDevEngine	int16u
0x010c	RawDevPictureMode	int16u
0x010d	RawDevPMSaturation	int16s[3]
0x010e	RawDevPMContrast	int16s[3]
0x010f	RawDevPMSharpness	int16s[3]
$0 \times 0110$	RawDevPM_BWFilter	int16u
$0 \times 0111$	RawDevPMPictureTone	int16u
$0 \times 0112$	RawDevGradation	int16s[3]
$0 \times 0113$	RawDevSaturation3	int16s[3]
$0 \times 0119$	RawDevAutoGradation	int16u
0x0120	RawDevPMNoiseFilter	int16u
$0 \times 0121$	RawDevArtFilter	int16u[4]

## Olympus ImageProcessing Tags

Tag Name	Writable
ImageProcessingVersion	undef[4]
WB_RBLevels	int16u[n]
WB_RBLevels3000K	int16u[n]
WB_RBLevels3300K	int16u[n]
WB_RBLevels3600K	int16u[n]
WB_RBLevels3900K	int16u[n]
WB_RBLevels4000K	int16u[n]
WB_RBLevels4300K	int16u[n]
	ImageProcessingVersion WB_RBLevels WB_RBLevels3000K WB_RBLevels3300K WB_RBLevels3600K WB_RBLevels3900K WB_RBLevels4000K

0x0108	WB_RBLevels4500K	int16u[n]
$0 \times 0109$	WB_RBLevels4800K	int16u[n]
0x010a	WB_RBLevels5300K	int16u[n]
$0 \times 010 b$	WB_RBLevels6000K	int16u[n]
0x010c	WB_RBLevels6600K	int16u[n]
0x010d	WB_RBLevels7500K	int16u[n]
0x010e	WB_RBLevelsCWB1	int16u[n]
0x010f	WB_RBLevelsCWB2	int16u[n]
$0 \times 0110$	WB_RBLevelsCWB3	int16u[n]
$0 \times 0111$	WB_RBLevelsCWB4	int16u[n]
$0 \times 0113$	WB_GLevel3000K	int16u
$0 \times 0114$	WB_GLevel3300K	int16u
$0 \times 0115$	WB_GLevel3600K	int16u
$0 \times 0116$	WB_GLevel3900K	int16u
$0 \times 0117$	WB_GLevel4000K	int16u
0x0118	WB_GLevel4300K	int16u
$0 \times 0119$	WB_GLevel4500K	int16u
0x011a	WB_GLevel4800K	int16u
0x011b	WB_GLevel5300K	int16u
0x011c	WB_GLevel6000K	int16u
0x011d	WB_GLevel6600K	int16u
0x011e	WB_GLevel7500K	int16u
0x011f	WB_GLevel	int16u
$0 \times 0200$	ColorMatrix	int16u[9]
$0 \times 0300$	Enhancer	int16u
0x0301	EnhancerValues	int16u[7]
0x0310	CoringFilter	int16u
0x0311	CoringValues	int16u[7]
0x0600	BlackLevel2	int16u[4]
0x0610	GainBase	int16u
0x0611	ValidBits	int16u[2]
$0 \times 0612$	CropLeft	int16u[2]
0x0613	CropTop	int16u[2]
0x0614	CropWidth	int32u
0x0615	CropHeight UnknownBlock1?	int32u
$0 \times 0635$		undef undef
$0 \times 0636$ $0 \times 0805$	UnknownBlock2? SensorCalibration	int16s[2]
0x0805 $0x1010$	NoiseReduction2	int16s[2]
0x1010 0x1011	DistortionCorrection2	int16u
0x1011 0x1012	ShadingCompensation2	int16u
0x1012 0x101c	MultipleExposureMode	int16u[2]
0x1010	UnknownBlock3?	undef
0x1103 $0x1104$	UnknownBlock4?	undef
0x1104 0x1112	AspectRatio	int8u[2]
0x1112 $0x1113$	AspectFrame	int16u[4]
0x1113 0x1200	FacesDetected	int32u[n]
0x1200	FaceDetectArea	int16s[n]
0x1201	MaxFaces	int32u[3]
0x1202 $0x1203$	FaceDetectFrameSize	int16u[6]
0x1203 $0x1207$	FaceDetectFrameCrop	int16s[12]
0x1207	CameraTemperature	no
0x1900	KeystoneCompensation	int8u[2]
0x1900	KeystoneDirection	int8u[2]
0x1901	KeystoneValue	int16s[3]
3111700	1101 200110 1 41 40	

# Olympus FocusInfo Tags

Tag ID	Tag Name	Writable
0x0000	FocusInfoVersion	undef[4]
0x0209	AutoFocus?	int16u
$0 \times 0210$	SceneDetect	int16u
$0 \times 0211$	SceneArea?	int32u[8]
0x0212	SceneDetectData?	int32u[720]
0x0300	ZoomStepCount	int16u
0x0301	FocusStepCount	int16u
0x0303	FocusStepInfinity	int16u
$0 \times 0304$	FocusStepNear	int16u
0x0305	FocusDistance	rational64u

0x0308	AFPoint	int16u
0x031b	AFPointDetails	no
	AFPointDetails	int16u
0x0328	AFInfo	Olympus AFInfo
0x1201	ExternalFlash	int16u[2]
0x1203	ExternalFlashGuideNumber?	rational64s
0x1204	ExternalFlashBounce	int16u
0x1205	ExternalFlashZoom	rational64u
0x1208	InternalFlash	int16u[n]
0x1209	ManualFlash	int16u[2]~
0x120a	MacroLED	int16u
0x1500	SensorTemperature	int16s
0x1600	ImageStabilization	undef~

## Olympus AFInfo Tags

Index1	Tag Name	Writable
[no tags	known]	

## Olympus FE Tags

Some FE models write a large number of tags here, but most of this information remains unknown.

Tag ID	Tag Name	Writable
$0 \times 0100$	BodyFirmwareVersion	string

## Olympus RawInfo Tags

These tags are found only in ORF images of some models (eg. C8080WZ).

Tag ID	Tag Name	Writable
0x0000	RawInfoVersion	undef[4]
0x0100	WB RBLevelsUsed	int16u[2]
0x0110	WB_RBLevelsAuto	int16u[2]
0x0120	WB RBLevelsShade	int16u[2]
0x0121	WB_RBLevelsCloudy	int16u[2]
0x0122	WB_RBLevelsFineWeather	int16u[2]
$0 \times 0123$	WB_RBLevelsTungsten	int16u[2]
0x0124	WB_RBLevelsEveningSunlight	int16u[2]
0x0130	WB_RBLevelsDaylightFluor	int16u[2]
0x0131	WB_RBLevelsDayWhiteFluor	int16u[2]
0x0132	WB_RBLevelsCoolWhiteFluor	int16u[2]
0x0133	WB_RBLevelsWhiteFluorescent	int16u[2]
0x0200	ColorMatrix2	int16u[9]
0x0310	CoringFilter	int16u
$0 \times 0311$	CoringValues	int16u[11]
0x0600	BlackLevel2	int16u[4]
0x0601	YCbCrCoefficients	no
0x0611	ValidPixelDepth	int16u[2]
0x0612	CropLeft	int16u
$0 \times 0613$	CropTop	int16u
0x0614	CropWidth	int32u
$0 \times 0615$	CropHeight	int32u
0x1000	LightSource	int16u
0x1001	WhiteBalanceComp	int16s[3]
0x1010	SaturationSetting	int16s[3]
$0 \times 1011$	HueSetting	int16s[3]
0x1012	ContrastSetting	int16s[3]
$0 \times 1013$	SharpnessSetting	int16s[3]
0x2000	CMExposureCompensation	rational64s
0x2001	CMWhiteBalance	int16u
0x2002	CMWhiteBalanceComp	int16s
0x2010	CMWhiteBalanceGrayPoint	int16u[3]
0x2020	CMSaturation	int16s[3]
0x2021	CMHue	int16s[3]
0x2022	CMContrast	int16s[3]

0x2023 CMSharpness int16s[3]

## <u>Olympus UnknownInfo Tags</u>

Tag ID	Tag Name	Writable
[no tags	known]	

#### Olympus DSS Tags

Information extracted from DSS/DS2 files and the ID3 XOLY frame of MP3 files written by some Olympus voice recorders.

Tag Name	Writable
Model	no
StartTime	no
EndTime	no
Duration	no
Comment	no
	Model StartTime EndTime Duration

#### Olympus AVI Tags

This information is found in Olympus AVI videos.

Index1	Tag Name	Writable
18	Make	no
44	Model	no
94	FNumber	no
131	DateTime1	no
157	DateTime2	no
297	ThumbInfo	Olympus thmb2

## Olympus thmb2 Tags

Tag Name	Writable
ThumbnailWidth	no
ThumbnailHeight	no
ThumbnailLength	no
ThumbnailImage	no
	ThumbnailWidth ThumbnailHeight ThumbnailLength

### Olympus WAV Tags

This information is found in WAV files from Olympus PCM linear recorders like the LS-5, LS-10, LS-11.

Index1	Tag Name	Writable
12	Model	no
28	FileNumber	no
38	DateTimeOriginal	no
50	DateTimeEnd	no
62	RecordingTime	no
512	Duration	no
522	Index01	no
532	Index02	no
542	Index03	no
552	Index04	no
562	Index05	no
572	Index06	no
582	Index07	no
592	Index08	no
602	Index09	no
612	Index10	no
622	Index11	no
632	Index12	no
642	Index13	no
652	Index14	no

662	Index15	no
672	Index16	no

### Olympus MOV1 Tags

This information is found in MOV videos from Olympus models such as the D540Z, D595Z, FE100, FE110, FE115, FE170 and FE200.

Index1	Tag Name	Writable
0	Make	no
24	Model	no
38	ExposureUnknown?	no
42	FNumber	no
50	ExposureCompensation	no
72	FocalLength	no

### Olympus MOV2 Tags

This information is found in MOV videos from Olympus models such as the FE120, FE140 and FE190.

Index1	Tag Name	Writable
0	Make	no
24	Model	no
54	ExposureTime	no
58	FNumber	no
66	ExposureCompensation	no
88	FocalLength	no
193	ISO	no

#### Olympus MP4 Tags

This information is found in MP4 videos from Olympus models such as the u7040 and u9010.

Index1	Tag Name	Writable
0	Make	no
24	Model	no
40	FNumber	no
48	ExposureCompensation	no
104	MovableInfo	Olympus MovableInfo
114	MovableInfo	Olympus MovableInfo

### Olympus MovableInfo Tags

Index1	Tag Name	Writable
4	ISO	no
44	EncoderVersion	no
60	DecoderVersion	no
131	Thumbnail	Olympus Thumbnail

### Olympus Thumbnail Tags

Index4	Tag Name	Writable
1	ThumbnailWidth	no
2	ThumbnailHeight	no
3	ThumbnailLength	no
4	ThumbnailOffset	no

#### Olympus MOV3 Tags

QuickTime information found in the TAGS atom of MOV videos from the  $\text{E-M5}\,.$ 

'OLYM' OlympusAtom Olympus OLYM2

## Olympus OLYM2 Tags

Tag ID	Tag Name	Writable
'prms'	MakerNotes	Olympus prms
'scrn'	PreviewInfo	Olympus scrn2
'thmb'	ThumbInfo	Olympus thmb2

#### Olympus prms Tags

Information extracted from the "prms" atom in MOV videos from Olympus models such as the OM  $\hbox{E-M5}\,.$ 

Index1	Tag Name	Writable
18	Make	no
44	Model	no
131	DateTime1	no
157	DateTime2	no
383	LensModel	no

#### Olympus scrn2 Tags

Index1	Tag Name	Writable
2	OlympusPreview	Olympus scrn

### Olympus scrn Tags

Information extracted from the "scrn" atom of Olympus MP4 videos.

Index1	Tag Name	Writable
0	PreviewImageLength	no
4	PreviewImage	no

## Olympus thmb Tags

Information extracted from the "thmb" atom of Olympus MP4 videos.

Index1	Tag Name	Writable
0	ThumbnailLength	no
4	ThumbnailImage	no

### Olympus OLYM Tags

Tags found in the OLYM atom of MP4 videos from the TG-810.

Index1	Tag Name	Writable
14	Make	no
40	Model	no
90	FNumber	no
127	DateTimeOriginal	no
153	DateTime2	no
265	ThumbnailWidth	no
267	ThumbnailHeight	no

### Panasonic Tags

These tags are used in Panasonic/Leica cameras.

Tag ID	Tag Name	Writable
$0 \times 0001$	ImageQuality	int16u
$0 \times 0002$	FirmwareVersion	undef
0x0003	WhiteBalance	int16u

	ExifTool 13.24 Tag Names -	· <b>-</b>
0x0007	FocusMode	int16u
0x000f	AFAreaMode	int8u[2]
0x001a	ImageStabilization	int16u
0x001c	MacroMode	int16u
0x001f	ShootingMode	int16u
$0 \times 0020$	Audio	int16u
$0 \times 0021$	DataDump	no
$0 \times 0023$ $0 \times 0024$	WhiteBalanceBias FlashBias	int16s int16s
0x0024 $0x0025$	InternalSerialNumber	undef[16]
0x0025	PanasonicExifVersion	undef
0x0027	VideoFrameRate	int16u
0x0028	ColorEffect	int16u
0x0029	TimeSincePowerOn	int32u
0x002a	BurstMode	int16u
0x002b	SequenceNumber	int32u
0x002c	ContrastMode	int16u
0x002d	NoiseReduction	int16u
0x002e	SelfTimer	int16u
0x0030 0x0031	Rotation AFAssistLamp	int16u int16u
0x0031 $0x0032$	ColorMode	int16u
0x0032	BabyAge	string
0x0034	OpticalZoomMode	int16u
0x0035	ConversionLens	int16u
0x0036	TravelDay	int16u
0x0038	BatteryLevel	int16u
0x0039	Contrast	int16u
0x003a	WorldTimeLocation	int16u
0x003b	TextStamp	int16u
0x003c	ProgramISO	int16u
0x003d 0x003e	AdvancedSceneType TextStamp	int16u int16u
0x003e 0x003f	FacesDetected	int16u
0x0031	Saturation	int16u
$0 \times 0.041$	Sharpness	int16u
0x0042	FilmMode	int16u
$0 \times 0043$	JPEGQuality	int16u
$0 \times 0044$	ColorTempKelvin	int16u
$0 \times 0045$	<del>-</del>	int16u
$0 \times 0046$	WBShiftAB	int16u
$0 \times 0047$	WBShiftGM	int16u
$0 \times 0048$ $0 \times 0049$	FlashCurtain LongExposureNoiseReduction	int16u int16u
0x0045	PanasonicImageWidth	int32u
0x004c	PanasonicImageHeight	int32u
0x004d	AFPointPosition	rational64u[2]
0x004e	FaceDetInfo	Panasonic FaceDetInfo
$0 \times 0051$	LensType	string
$0 \times 0052$	LensSerialNumber	string
$0 \times 0053$	AccessoryType	string
$0 \times 0.054$	AccessorySerialNumber	string
$0 \times 0.059$	Transform	undef[4]
0x005d 0x0060	<pre>IntelligentExposure LensFirmwareVersion</pre>	int16u undef[4]
0x0061	FaceRecInfo	Panasonic FaceRecInfo
0x0062	FlashWarning	int16u
0x0063	RecognizedFaceFlags?	undef[4]
0x0065	Title	undef
0x0066	BabyName	undef
0x0067	Location	undef
0x0069	Country	undef
0x006b	State	undef
0x006d	City Landmark	undef
0x006f 0x0070	Landmark IntelligentResolution	undef int8u
0x0070 $0x0076$	MergedImages	int16u
0x0070	BurstSpeed	int16u
0x0079	IntelligentD-Range	int16u
0x007c	ClearRetouch	int16u

	EXILIOOI 13.24 Tag Names	
$0 \times 00 \times 0$	City2	undef
0x0086	ManometerPressure	int16u
0x0089	PhotoStyle	int16u
0x008a	ShadingCompensation	int16u
0x008b	WBShiftIntelligentAuto	int16u
0x008c	AccelerometerZ	int16u
0x008d	AccelerometerX	int16u
0x008e	AccelerometerY	int16u
0x008f	CameraOrientation	int8u
0x0090	RollAngle	int16u
0x0091	PitchAngle	int16u
0x0092	WBShiftCreativeControl	int8u
0x0093	SweepPanoramaDirection	int8u
$0 \times 0094$	SweepPanoramaFieldOfView	int16u
0x0096	TimerRecording	int8u
0x009d	InternalNDFilter	rational64u
0x009e	HDR	int16u
0x009f	ShutterType	int16u
0x00a1	FilterEffect	rational64u[0.5]
0x00a3	ClearRetouchValue	rational64u
0x00a7	OutputLUT	yes
0x00ab	TouchAE	int16u
0x00ac	MonochromeFilterEffect	int16u
0x00ad	HighlightShadow	int16u[2]
0x00af	TimeStamp	string
0x00b3	VideoBurstResolution	int16u
0x00b4	MultiExposure	int16u
0x00b9	RedEyeRemoval	int16u
0x00bb	VideoBurstMode	int32u
0x00bc	DiffractionCorrection	int16u
0x00bd	FocusBracket	int16u
0x00be	LongExposureNRUsed	int16u
0x00bf	PostFocusMerging	int32u[2]
0x00c1	VideoPreburst	int16u
0x00c4	LensTypeMake	int16u
0x00c1	LensTypeModel	int16u
0x00ca	SensorType	int16u
0x00d1	ISO	int32u
0x00d2	MonochromeGrainEffect	int16u
0x00d2	NoiseReductionStrength	rational64s
0x00e4	LensTypeModel	int16u
0x00e8	MinimumISO	int32u
0x00e9	AFSubjectDetection	int16u
0x00ee	DynamicRangeBoost	int16u
0x0e00	PrintIM	PrintIM
0x2003	TimeInfo	Panasonic TimeInfo
0x2000	MakerNoteVersion	undef
0x8000	SceneMode	int16u
0x8001	HighlightWarning	int16u
0x8002	DarkFocusEnvironment	int16u
0x8003	WBRedLevel	int16u
0x8004 0x8005	WBGreenLevel	int16u
0x8005	WBBlueLevel	int16u
0x8008	TextStamp	int16u
0x8008	TextStamp	int16u
0x8009 0x8010	BabyAge	string
0x8010 0x8012	Transform	undef[4]
OVOOTZ	IT ALIST UT III	ander[4]

## Panasonic DSA Tags

XMP Digital Shift Assistant tags written by some Leica cameras.

These tags belong to the ExifTool XMP-xmpDSA family 1 group.

Tag Name	Writable
ApplyAutomatically	boolean/
CorrectionAlreadyApplied	boolean/
FocalLength35mm	real/
NormalizedCropCorners	real/+

PitchAngle	real/
RollAngle	real/
ScalingFactorHeight	real/
TargetAspectRatio	real/
ValidCropCorners	boolean/
Version	string/

## Panasonic FaceDetInfo Tags

Face detection position information.

Tag Name	Writable
NumFacePositions	int16u
FacelPosition	int16u[4]
Face2Position	int16u[4]
Face3Position	int16u[4]
Face4Position	int16u[4]
Face5Position	int16u[4]
	NumFacePositions Face1Position Face2Position Face3Position Face4Position

### Panasonic FaceRecInfo Tags

Tags written by cameras with facial recognition. These cameras not only detect faces in an image, but also recognize specific people based a user-supplied set of known faces.

Index1	Tag Name	Writable
0	FacesRecognized	int16u
4	RecognizedFace1Name	string[20]
24	RecognizedFacelPosition	int16u[4]
32	RecognizedFace1Age	string[20]
52	RecognizedFace2Name	string[20]
72	RecognizedFace2Position	int16u[4]
80	RecognizedFace2Age	string[20]
100	RecognizedFace3Name	string[20]
120	RecognizedFace3Position	int16u[4]
128	RecognizedFace3Age	string[20]

## Panasonic TimeInfo Tags

Index1	Tag Name	Writable
0	PanasonicDateTime	undef[8]
16	TimeLapseShotNumber	int32u

## Panasonic Leica2 Tags

These tags are used by the Leica  ${\tt M8.}$ 

Tag ID	Tag Name	Writable
0x0300	Quality	int16u
$0 \times 0302$	UserProfile	int32u
$0 \times 0303$	SerialNumber	int32u
$0 \times 0304$	WhiteBalance	int16u
$0 \times 0310$	LensType	int32u
$0 \times 0311$	ExternalSensorBrightnessValue	rational64s
$0 \times 0312$	MeasuredLV	rational64s
$0 \times 0313$	ApproximateFNumber	rational64u
$0 \times 0320$	CameraTemperature	int32s
$0 \times 0321$	ColorTemperature	int32u
$0 \times 0322$	WBRedLevel	rational64u
$0 \times 0323$	WBGreenLevel	rational64u
$0 \times 0324$	WBBlueLevel	rational64u
$0 \times 0325$	UV-IRFilterCorrection	int32u
$0 \times 0330$	CCDVersion	int32u
$0 \times 0331$	CCDBoardVersion	int32u
$0 \times 0332$	ControllerBoardVersion	int32u
0x0333	M16CVersion	int32u

0x0340 ImageIDNumber int32u

## Panasonic Leica3 Tags

These tags are used by the Leica R8 and R9 digital backs.

Tag ID	Tag Name	Writable
0x000b	SerialInfo	Panasonic SerialInfo
0x000d	WB RGBLevels	int16u[3]

## Panasonic SerialInfo Tags

Index1	Tag Name	Writable
4	SerialNumber	no

## Panasonic Leica4 Tags

This information is written by the M9.

Tag ID	Tag Name	Writable	
0x3000	Subdir3000	Panasonic	Subdir
0x3100	Subdir3100	Panasonic	Subdir
$0 \times 3400$	Subdir3400	Panasonic	Subdir
0x3900	Subdir3900	Panasonic	Subdir

## Panasonic Subdir Tags

Tag ID	Tag Name	Writable
0x300a	Contrast	int32u
0x300b	Sharpening	int32u
0x300d	Saturation	int32u
0x3033	WhiteBalance	int32u
0x3034	JPEGQuality	int32u
0x3036	WB_RGBLevels	rational64u[3]
0x3038	UserProfile	string
0x303a	JPEGSize	int32u
0x3103	SerialNumber	string
0x3109	FirmwareVersion	string
0x312a	BaseISO	int32u
0x312b	SensorWidth	int32u
0x312c	SensorHeight	int32u
0x312d	SensorBitDepth	int32u
$0 \times 3402$	CameraTemperature	int32s
$0 \times 3405$	LensType	int32u
$0 \times 3406$	ApproximateFNumber	rational64u
$0 \times 3407$	MeasuredLV	int32s
$0 \times 3408$	ExternalSensorBrightnessValue	int32s
0x3901	Data1	Panasonic Datal
0x3902	Data2	Panasonic Data2

## Panasonic Datal Tags

Index1	Tag Name	Writable
22	LensType	int32u

### Panasonic Data2 Tags

Index1	Tag Name	Writable
[no tags	known]	

## Panasonic Leica5 Tags

This information is written by the X1, X2, X VARIO and T.

Tag ID	Tag Name	Writable
0x0303	LensType	string
0x0305	SerialNumber	int32u
$0 \times 0407$	OriginalFileName	string
0x0408	OriginalDirectory	string
0x040a	FocusInfo	Panasonic FocusInfo
0x040d	ExposureMode	int8u[4]
$0 \times 0410$	ShotInfo	Panasonic ShotInfo
$0 \times 0412$	FilmMode	string
0x0413	WB_RGBLevels	rational64u[3]
0x0500	InternalSerialNumber	undef
0x05ff	CameraIFD	PanasonicRaw CameraIFD

## Panasonic FocusInfo Tags

Index2	Tag Name	Writable
0	FocusDistance	int16u
1	FocalLength	int16u

### Panasonic ShotInfo Tags

Index1	Tag Name	Writable
0	FileIndex	int16u

## Panasonic Leica6 Tags

This information is written by the S2 and M (Typ 240), as a trailer in JPEG images.

Tag ID	Tag Name	Writable
0x0300	PreviewImage	undef
0x0301	UnknownBlock?	no
0x0303	LensType	string
0x0304	FocusDistance	int32u
0x0311	ExternalSensorBrightnessValue	rational64s
0x0312	MeasuredLV	rational64s
0x0320	FirmwareVersion	int8u[4]
$0 \times 0321$	LensSerialNumber	int32u

## Panasonic Leica9 Tags

This information is written by the Leica S (Typ 007) and M10 models.

Tag ID	Tag Name	Writable
0x0304 0x0311 0x0312	FocusDistance ExternalSensorBrightnessValue MeasuredLV	int32u rational64s rational64s
0x0312 0x034c 0x0359 0x035a	UserProfile ISOSelected FNumber	string int32s int32s
0x035a 0x035b 0x035c	CorrelatedColorTemp ColorTint	int16u int16s
0x035d 0x0370	WhitePoint LensProfileName	rational64u[2] string

### Panasonic Type2 Tags

This type of maker notes is used by models such as the NV-DS65, PV-D2002, PV-DC3000, PV-DV203, PV-DV401, PV-DV702, PV-L2001, PV-SD4090, PV-SD5000 and iPalm.

Index2	Tag Name	Writable
0	MakerNoteType	no
3	Gain	no

# Panasonic PANA Tags

Tags extracted from the PANA and LEIC user data found in MP4 videos from various Panasonic and Leica models.

Index1	Tag Name	Writable
0	Make	no
4	Model	no
12	Model	no
16	JPEG-likeData	EXIF
22	Model	no
52	Version1	no
62	Version2	no
80	MakerNoteLeica5	Panasonic Leica5
88	ThumbnailWidth	no
90	ThumbnailHeight	no
92	ThumbnailImage	no
1334	ThumbnailWidth	no
1338	ThumbnailHeight	no
1342	ThumbnailLength	no
1350	ThumbnailImage	no
1358	ThumbnailWidth	no
1362	ThumbnailHeight	no
1366	ThumbnailLength	no
1374	ThumbnailImage	no
16488	ExifData	EXIF
16512	ExifData	EXIF
0x00200080	ExifData	EXIF

## Pentax Tags

These tags are used in Pentax/Asahi cameras.

Tag ID	Tag Name	Writable
0x0000	PentaxVersion	int8u[4]
$0 \times 0001$	PentaxModelType	int16u
$0 \times 0002$	PreviewImageSize	int16u[2]
0x0003	PreviewImageLength	int32u*
$0 \times 0 0 0 4$	PreviewImageStart	int32u*
0x0005	PentaxModelID	int32u
$0 \times 0006$	Date	undef[4]
0x0007	Time	undef[3]
0x0008	Quality	int16u
0x0009	PentaxImageSize	int16u
0x000b	PictureMode	int16u[n]
0x000c	FlashMode	int16u[n]
0x000d	FocusMode	int16u
0x000e	AFPointSelected	int16u
0x000f	AFPointsInFocus	int32u
	AFPointsInFocus	int16u
$0 \times 0010$	FocusPosition	int16u
$0 \times 0012$	ExposureTime	int32u
$0 \times 0013$	FNumber	int16u
$0 \times 0014$	ISO	int16u
$0 \times 0015$	LightReading	int16u
$0 \times 0016$	ExposureCompensation	int16u
	ExposureCompensation	int16u[2]
$0 \times 0017$	MeteringMode	int16u
$0 \times 0018$	AutoBracketing	int16u[n]
$0 \times 0019$	WhiteBalance	int16u
0x001a	WhiteBalanceMode	int16u
0x001b	BlueBalance	int16u
0x001c	RedBalance	int16u
$0 \times 001d$	FocalLength	int32u
0x001e	DigitalZoom	int16u
0x001f	Saturation	<pre>int16u[n]</pre>
$0 \times 0020$	Contrast	int16u[n]
0x0021	Sharpness	int16u[n]

	ExifTool	13.24	Tag	Names	
0x0022	WorldTimeLocation				int16u
$0 \times 0023$	HometownCity				int16u
$0 \times 0024$	DestinationCity				int16u
$0 \times 0025$	HometownDST				int16u
0x0026	DestinationDST				int16u
$0 \times 0027$	DSPFirmwareVersion				undef
0x0028	CPUFirmwareVersion				undef int32u
0x0029 0x002d	FrameNumber EffectiveLV				int16u
020020	EffectiveLV				int32u
0x0032	ImageEditing				undef[4]
0x0033	PictureMode				int8u[3]
$0 \times 0034$	DriveMode				int8u[4]
0x0035	SensorSize				int16u[2]
$0 \times 0037$	ColorSpace				int16u
0x0038	ImageAreaOffset				int16u[2]
$0 \times 0039$	RawImageSize AFPointsInFocus				int16u[2]~
0x003c 0x003d	DataScaling				no int16u
0x003a	PreviewImageBorders				int8u[4]
0x003f	LensRec				Pentax LensRec
$0 \times 0040$	SensitivityAdjust				int16u
$0 \times 0041$	ImageEditCount				int16u
$0 \times 0047$	CameraTemperature				int8s
$0 \times 0048$	AELock				int16u
0x0049	NoiseReduction				int16u
0x004d	FlashExposureComp FlashExposureComp				int32s int8s[2]
0x004f	ImageTone				int16u
$0 \times 0050$	ColorTemperature				int16u
0x0053	ColorTempDaylight				undef[4]
$0 \times 0054$	ColorTempShade				undef[4]
$0 \times 0055$	ColorTempCloudy				undef[4]
$0 \times 0056$	ColorTempTungsten				undef[4]
0x0057	ColorTempFluorescen				undef[4]
0x0058	ColorTempFluorescen				undef[4] undef[4]
0x0059 0x005a	ColorTempFluorescen ColorTempFlash	LW			undef[4] undef[4]
0x005c	ShakeReductionInfo				Pentax SRInfo
					Pentax SRInfo2
0x005d	ShutterCount				undef[4]
$0 \times 0060$	FaceInfo				Pentax FaceInfo
0x0062	RawDevelopmentProce	SS			int16u
0x0067	Hue				int16u
0x0068 0x0069	AWBInfo DynamicRangeExpansi	on			Pentax AWBInfo undef[4]
0x0069	TimeInfo	OII			Pentax TimeInfo
0x006c	HighLowKeyAdj				int16s[2]
0x006d	ContrastHighlight				int16s[2]
0x006e	ContrastShadow				int16s[2]
0x006f	ContrastHighlightSh	adowAd	lj		int8u
$0 \times 0070$	FineSharpness				int8u[n]
$0 \times 0071$	HighISONoiseReduction	on			int8u
0x0072 0x0073	AFAdjustment MonochromeFilterEff	oat			int16s int16u
0x0073 $0x0074$	MonochromeToning	ect			int16u
0x0076	FaceDetect				int8u[2]
$0 \times 0077$	FaceDetectFrameSize				int16u[2]
0x0079	ShadowCorrection				int8u[n]
0x007a	ISOAutoMinSpeed				int8u[2]
0x007b	CrossProcess				int8u
0x007d	LensCorr				Pentax LensCorr int32u
0x007e 0x007f	WhiteLevel BleachBypassToning				int32u int16u
0x0071	AspectRatio				yes
0x0080	BlurControl				int8u[4]
$0 \times 0085$	HDR				int8u[4]
$0 \times 0087$	ShutterType				int8u
$0 \times 0088$	NeutralDensityFilte	r			int8u[n]
0x008b	ISO				int32u

0x0092	IntervalShooting	int16u[2]
0x0095	SkinToneCorrection	int8s[2]
020000	SkinToneCorrection	int8s[3]
00006		
0x0096	ClarityControl	int8s[2]
$0 \times 0200$	BlackPoint	int16u[4]
$0 \times 0201$	WhitePoint	int16u[4]
0x0203	ColorMatrixA	int16s[9]
$0 \times 0204$	ColorMatrixB	int16s[9]
$0 \times 0205$	CameraSettings	Pentax CameraSettings
	CameraSettingsUnknown	Pentax CameraSettingsUnknown
0x0206	AEInfo	Pentax AEInfo
	AEInfo2	Pentax AEInfo2
	AEInfo3	Pentax AEInfo3
	AEInfoUnknown	Pentax AEInfoUnknown
$0 \times 0207$	LensInfo	Pentax LensInfo
ONOZOT		Pentax LensInfo2
		Pentax LensInfo3
		Pentax LensInfo4
		Pentax LensInfo5
0x0208	FlashInfo	Pentax FlashInfo
	FlashInfoUnknown	Pentax FlashInfoUnknown
$0 \times 0209$	AEMeteringSegments	int8u[n]
0x020a	FlashMeteringSegments	int8u[n]
0x020b	SlaveFlashMeteringSegments	int8u[n]
0x020d	WB_RGGBLevelsDaylight	int16u[4]
0x020e	WB_RGGBLevelsShade	int16u[4]
0x020f	WB_RGGBLevelsCloudy	int16u[4]
$0 \times 0210$	WB_RGGBLevelsTungsten	int16u[4]
$0 \times 0211$	WB_RGGBLevelsFluorescentD	int16u[4]
$0 \times 0212$	WB RGGBLevelsFluorescentN	int16u[4]
$0 \times 0213$	WB_RGGBLevelsFluorescentW	int16u[4]
0x0214	WB RGGBLevelsFlash	int16u[4]
0x0215	CameraInfo	Pentax CameraInfo
0x0215 0x0216	BatteryInfo	Pentax BatteryInfo
0x021b	SaturationInfo?	no
0x021b	ColorMatrixA2	undef[18]
0x021d	ColorMatrixB2	undef[18]
	AFInfo	
0x021f		Pentax AFInfo
$0 \times 0220$	HuffmanTable?	no
$0 \times 0221$	KelvinWB	Pentax KelvinWB
0x0222	ColorInfo	Pentax ColorInfo
$0 \times 0224$	EVStepInfo	Pentax EVStepInfo
0x0226	ShotInfo	Pentax ShotInfo
$0 \times 0227$	FacePos	Pentax FacePos
0x0228	FaceSize	Pentax FaceSize
0x0229	SerialNumber	string
0x022a	FilterInfo	Pentax FilterInfo
		Pentax FilterInfo
0x022b	LevelInfoK3III	Pentax LevelInfoK3III
	LevelInfo	Pentax LevelInfo
0x022d	WBLevels	Pentax WBLevels
0x022e	Artist	string
0x022f	Copyright	string
0x0230	FirmwareVersion	string
0x0230	ContrastDetectAFArea	int16u[4]
0x0231	CrossProcessParams	undef[10]
0x0233	LensInfo0	
	~	Pentax LensInfoQ
$0 \times 023 f$	Model	string
$0 \times 0243$	PixelShiftInfo	Pentax PixelShiftInfo
$0 \times 0245$	AFPointInfo	Pentax AFPointInfo
0x03fe	DataDump	no
0x03ff	TempInfo	Pentax TempInfo
	UnknownInfo	Pentax UnknownInfo
$0 \times 0402$	ToneCurve	yes~
$0 \times 0403$	ToneCurves	yes~
$0 \times 0405$	UnknownBlock?	undef
0x0e00	PrintIM	PrintIM

This record stores the LensType, plus one or two unknown bytes for some models.

Index1	Tag Name	Writable
0	LensType	int8u[2]
3	ExtenderStatus	int8u

## Pentax SRInfo Tags

Shake reduction information.

Index1	Tag Name	Writable
0	SRResult	int8u
1	ShakeReduction	int8u
2	SRHalfPressTime	int8u
3	SRFocalLength	int8u

## Pentax SRInfo2 Tags

Shake reduction information for the K-3.

Index1	Tag Name	Writable
0	SRResult?	int8u
1	ShakeReduction	int8u

## Pentax FaceInfo Tags

Index1	Tag Name	Writable
0	FacesDetected	int8u
2	FacePosition	int8u[2]

## <u>Pentax</u> <u>AWBInfo</u> <u>Tags</u>

Index1	Tag Name	Writable
0	WhiteBalanceAutoAdjustment	int8u
1	TungstenAWB	int8u

## Pentax TimeInfo Tags

Index1	Tag Name	Writable
0.1	WorldTimeLocation	int8u & 0x01
0.2	HometownDST	int8u & 0x02
0.3	DestinationDST	int8u & 0x04
2	HometownCity	int8u
3	DestinationCity	int8u

# Pentax LensCorr Tags

Index1	Tag Name	Writable
0	DistortionCorrection	int8u
1	ChromaticAberrationCorrection	int8u
2	PeripheralIlluminationCorr	int8u
3	DiffractionCorrection	int8u

## <u>Pentax</u> <u>CameraSettings</u> <u>Tags</u>

Camera settings information written by Pentax DSLR cameras.

Index1	Tag Name	Writable
0	PictureMode2	int8u
1.1	ProgramLine	int8u & 0x03
1.2	EVSteps	int8u & 0x20

1 2	n n' 17 n	
1.3	E-DialInProgram	int8u & 0x40
1.4	ApertureRingUse	int8u & 0x80
2	FlashOptions	int8u & 0xf0
2.1	MeteringMode2	int8u & 0x0f
3	AFPointMode	int8u & 0xf0
3.1	FocusMode2	int8u & 0x0f
4	AFPointSelected2	int16u
6	ISOFloor	int8u
7	DriveMode2	int8u
8	ExposureBracketStepSize	int8u
9	BracketShotNumber	int8u
10	WhiteBalanceSet	int8u & 0xf0
10.1	MultipleExposureSet	int8u & 0x0f
13	RawAndJpgRecording	int8u
14.1	JpgRecordedPixels	int8u & 0x03
14.2	LinkAEToAFPoint	int8u & 0x01
14.3	SensitivitySteps	int8u & 0x02
14.4	ISOAuto	int8u & 0x04
16	FlashOptions2	int8u & 0xf0
16.1	MeteringMode3	int8u & 0x0f
17.1	SRActive	int8u & 0x80
17.2	Rotation	int8u & 0x60
17.3	ISOSetting	int8u & 0x04
17.4	SensitivitySteps	int8u & 0x02
18	TvExposureTimeSetting	int8u
19	AvApertureSetting	int8u
20	SvISOSetting	int8u
21	BaseExposureCompensation	int8u
21	Dabelipobal ccompetibacion	111000

## Pentax CameraSettingsUnknown Tags

This information has not yet been decoded for models such as the K-01.

Index1 Tag Name Writable
----[no tags known]

# Pentax AEInfo Tags

Auto-exposure information for most Pentax models.

Index1	Tag Name	Writable
0	AEExposureTime	int8u
1	AEAperture	int8u
2	AE_ISO	int8u
3	AEXv	int8u
4	AEBXv	int8s
5	AEMinExposureTime	int8u
6	AEProgramMode	int8u
7	AEFlags	no
8	AEApertureSteps	int8u
9	AEMaxAperture	int8u
10	AEMaxAperture2	int8u
11	AEMinAperture	int8u
12	AEMeteringMode	int8u
13	AEWhiteBalance	int8u & 0xf0
13.1	AEMeteringMode2	int8u & 0x0f
14	FlashExposureCompSet	int8s
21	LevelIndicator	int8u

## Pentax AEInfo2 Tags

Auto-exposure information for the K-01.

Index1	Tag Name	Writable
2	AEExposureTime	int8u
3	AEAperture	int8u
4	AE_ISO	int8u

5	AEXv	int8u
6	AEBXv	int8s
8	AEError	int8s
11	AEApertureSteps	int8u
15	SceneMode	int8u
16	AEMaxAperture	int8u
17	AEMaxAperture2	int8u
18	AEMinAperture	int8u
19	AEMinExposureTime	int8u

#### Pentax AEInfo3 Tags

Auto-exposure information for the K-1mkII, K-3, K-30, K-50, K-70, K-500 and KP.

Index1	Tag Name	Writable
16	AEExposureTime	int8u
17	AEAperture	int8u
18	AE_ISO	int8u
28	AEMaxAperture	int8u
29	AEMaxAperture2	int8u
30	AEMinAperture	int8u
31	AEMinExposureTime	int8u

## Pentax AEInfoUnknown Tags

Index1	Tag Name	Writable
Ino tags	s knownl	

## <u>Pentax LensInfo Tags</u>

Pentax lens information structure for models such as the \*istD.

Index1	Tag Name	Writable
0	LensType	int8u[2]
3	LensData	Pentax LensData

# Pentax LensData Tags

Pentax lens data information. Some of these tags require interesting binary gymnastics to decode them into useful values.

Index1	Tag Name	Writable
0.1	AutoAperture	int8u & 0x01
0.2	<b>1</b>	int8u & 0x06
0.3	<u> </u>	int8u & 0x70
1	LensKind?	int8u
2	LC1?	int8u
3	MinFocusDistance	int8u & 0xf8
3.1	FocusRangeIndex	int8u & 0x07
4	LC3?	int8u
5	LC4?	int8u
6	LC5?	int8u
7	LC6?	int8u
8	LC7?	int8u
9	LensFocalLength	int8u
	LC8?	int8u
10	NominalMaxAperture	int8u & 0xf0
10.1	NominalMinAperture	int8u & 0x0f
11	LC10?	int8u
12	LC11?	int8u
13	LC12?	int8u
14.1	MaxAperture	int8u & 0x7f
15	<u>-</u>	int8u
16	LC15?	int8u

## Pentax LensInfo2 Tags

Pentax lens information structure for models such as the K10D and K20D.

Index1	Tag Name	Writable
0	LensType	int8u[4]
4	LensData	Pentax LensData

## Pentax LensInfo3 Tags

Pentax lens information structure for 645D.

Index1	Tag Name	Writable
1	LensType	int8u[4]
13	LensData	Pentax LensData

## Pentax LensInfo4 Tags

Pentax lens information structure for models such as the K-5 and K-r.

Index1	Tag Name	Writable
1	LensType	int8u[4]
12	LensData	Pentax LensData

## Pentax LensInfo5 Tags

Pentax lens information structure for the K-01 and newer models.

Index1	Tag Name	Writable
1	LensType	int8u[5]
15	LensData	Pentax LensData

### Pentax FlashInfo Tags

Flash information tags for the K10D, K20D and K200D.

Index1	Tag Name	Writable
0	FlashStatus	int8u
1	InternalFlashMode	int8u
2	ExternalFlashMode	int8u
3	InternalFlashStrength	int8u
4	TTL_DA_AUp	int8u
5	TTL_DA_ADown	int8u
6	TTL_DA_BUp	int8u
7	TTL_DA_BDown	int8u
24.1	ExternalFlashGuideNumber	int8u & 0x1f
25	ExternalFlashExposureComp	int8u
26	ExternalFlashBounce	int8u

## Pentax FlashInfoUnknown Tags

Index1	Tag Name	Writable
[no tags	known]	

## <u>Pentax</u> <u>CameraInfo</u> <u>Tags</u>

Index4	Tag Name	Writable
0	PentaxModelID	int32u
1	ManufactureDate	int32u
2	ProductionCode	int32u[2]
4	InternalSerialNumber	int32u

## Pentax BatteryInfo Tags

Index1	Tag Name	Writable
0.1	PowerSource	int8u & 0x0f
0.2	PowerAvailable	int8u & 0xf0
1.1	BodyBatteryState	int8u & 0xf0
1.2	GripBatteryState	int8u & 0x0f
2	BodyBatteryADNoLoad	int8u
	BodyBatteryVoltage1	int16u
	BodyBatteryState	int8u
3	BodyBatteryADLoad	int8u
	BodyBatteryPercent	int8u
4	GripBatteryADNoLoad	int8u
	BodyBatteryVoltage2	int16u
	BodyBatteryVoltage	int32u
5	GripBatteryADLoad	int8u
6	BodyBatteryVoltage3	int16u
8	BodyBatteryVoltage4	int16u
16	GripBatteryState	int8u
17	GripBatteryPercent	int8u
18	GripBatteryVoltage	int32u

# Pentax AFInfo Tags

Index1	Tag Name	Writable
0	AFPointsUnknown1?	int16u
2	AFPointsUnknown2?	int16u
4	AFPredictor	int16s
6	AFDefocus	int8u
7	AFIntegrationTime	int8u
11	AFPointsInFocus	int8u
506	LiveView	int8u
509	AFHold	int8u

# Pentax KelvinWB Tags

White balance Blue/Red gains as a function of color temperature.

Index2	Tag Name	Writable
1	KelvinWB_Daylight	int16u[4]
5	KelvinWB_01	int16u[4]
9	KelvinWB_02	int16u[4]
13	KelvinWB_03	int16u[4]
17	KelvinWB_04	int16u[4]
21	KelvinWB_05	int16u[4]
25	KelvinWB_06	int16u[4]
29	KelvinWB_07	int16u[4]
33	KelvinWB_08	int16u[4]
37	KelvinWB_09	int16u[4]
41	KelvinWB_10	int16u[4]
45	KelvinWB_11	int16u[4]
49	KelvinWB_12	int16u[4]
53	KelvinWB_13	int16u[4]
57	KelvinWB_14	int16u[4]
61	KelvinWB_15	int16u[4]
65	KelvinWB_16	int16u[4]

# Pentax ColorInfo Tags

Index1	Tag Name	Writable
16	WBShiftAB	int8s
17	WBShiftGM	int8s

# Pentax EVStepInfo Tags

Index1	Tag Name	Writable

0	EVSteps	int8u
1	SensitivitySteps	int8u
3	LiveView	int8u

# <u>Pentax ShotInfo Tags</u>

Index1	Tag Name	Writable
1	CameraOrientation	int8u

# Pentax FacePos Tags

Index2	Tag Name	Writable
0	Face1Position	int16u[2]
2	Face2Position	int16u[2]
4	Face3Position	int16u[2]
6	Face4Position	int16u[2]
8	Face5Position	int16u[2]
10	Face6Position	int16u[2]
12	Face7Position	int16u[2]
14	Face8Position	int16u[2]
16	Face9Position	int16u[2]
18	Face10Position	int16u[2]
20	FacellPosition	int16u[2]
22	Face12Position	int16u[2]
24	Face13Position	int16u[2]
26	Face14Position	int16u[2]
28	Face15Position	int16u[2]
30	Face16Position	int16u[2]
32	Face17Position	int16u[2]
34	Face18Position	int16u[2]
36	Face19Position	int16u[2]
38	Face20Position	int16u[2]
40	Face21Position	int16u[2]
42	Face22Position	int16u[2]
44	Face23Position	int16u[2]
46	Face24Position	int16u[2]
48	Face25Position	int16u[2]
50	Face26Position	int16u[2]
52	Face27Position	int16u[2]
54	Face28Position	int16u[2]
56	Face29Position	int16u[2]
58	Face30Position	int16u[2]
60	Face31Position	int16u[2]
62	Face32Position	int16u[2]

# Pentax FaceSize Tags

Index2	Tag Name	Writable
0	Face1Size	int16u[2]
2	Face2Size	int16u[2]
4	Face3Size	int16u[2]
6	Face4Size	int16u[2]
8	Face5Size	int16u[2]
10	Face6Size	int16u[2]
12	Face7Size	int16u[2]
14	Face8Size	int16u[2]
16	Face9Size	int16u[2]
18	Face10Size	int16u[2]
20	Face11Size	int16u[2]
22	Face12Size	int16u[2]
24	Face13Size	int16u[2]
26	Face14Size	int16u[2]
28	Face15Size	int16u[2]
30	Face16Size	int16u[2]
32	Face17Size	int16u[2]
34	Face18Size	int16u[2]
36	Face19Size	int16u[2]

38	Face20Size	int16u[2]
40	Face21Size	int16u[2]
42	Face22Size	int16u[2]
44	Face23Size	int16u[2]
46	Face24Size	int16u[2]
48	Face25Size	int16u[2]
50	Face26Size	int16u[2]
52	Face27Size	int16u[2]
54	Face28Size	int16u[2]
56	Face29Size	int16u[2]
58	Face30Size	int16u[2]
60	Face31Size	int16u[2]
62	Face32Size	int16u[2]

## Pentax FilterInfo Tags

The parameters associated with each type of digital filter are unique, and these settings are also extracted with the DigitalFilter tag. Information is not extracted for filters that are "Off" unless the Unknown option is used.

Index1	Tag Name	Writable
0	SourceDirectoryIndex	 int16u
2	SourceFileIndex	int16u
5	DigitalFilter01	undef[17]
22	DigitalFilter02	undef[17]
39	DigitalFilter03	undef[17]
56	DigitalFilter04	undef[17]
73	DigitalFilter05	undef[17]
90	DigitalFilter06	undef[17]
107	DigitalFilter07	undef[17]
124	DigitalFilter08	undef[17]
141	DigitalFilter09	undef[17]
158	DigitalFilter10	undef[17]
175	DigitalFilter11 DigitalFilter11	undef[17]
192	5	undef[17]
209	DigitalFilter12	undef[17]
	DigitalFilter13	<del>-</del> -
226	DigitalFilter14	undef[17]
243	DigitalFilter15	undef[17]
260	DigitalFilter16	undef[17]
277	DigitalFilter17	undef[17]
294	DigitalFilter18	undef[17]
311	DigitalFilter19	undef[17]
328	DigitalFilter20	undef[17]

## Pentax LevelInfoK3III Tags

Tags decoded from the electronic level information for the K-3 III.

Index1	Tag Name	Writable
1	CameraOrientation	int8s
3	RollAngle	int16s
5	PitchAngle	int16s

## Pentax LevelInfo Tags

Tags decoded from the electronic level information for the K-5. May not be valid for other models.

Index1	Tag Name	Writable
0	LevelOrientation	int8s & 0x0f
0.1	CompositionAdjust	int8s & 0xf0
1	RollAngle	int8s
2	PitchAngle	int8s
5	CompositionAdjustX	int8s
6	CompositionAdjustY	int8s
7	CompositionAdjustRotation	int8s

## Pentax WBLevels Tags

Index1	Tag Name	Writable
2	WB_RGGBLevelsDaylight	int16u[4]
11	WB_RGGBLevelsShade	int16u[4]
20	WB_RGGBLevelsCloudy	int16u[4]
29	WB_RGGBLevelsTungsten	int16u[4]
38	WB_RGGBLevelsFluorescentD	int16u[4]
47	WB_RGGBLevelsFluorescentN	int16u[4]
56	WB_RGGBLevelsFluorescentW	int16u[4]
65	WB_RGGBLevelsFlash	int16u[4]
74	WB_RGGBLevelsFluorescentL	int16u[4]
83	WB_RGGBLevelsUnknown?	int16u[4]
92	WB_RGGBLevelsUserSelected	int16u[4]

#### Pentax LensInfoQ Tags

More lens information stored by the Pentax Q.

Index1	Tag Name	Writable
12	LensModel	string[30]
42	LensInfo	string[20]

## Pentax PixelShiftInfo Tags

Pixel shift information stored by the K-3 II.

Index1	Tag Name	Writable
0	PixelShiftResolution	int8u

## Pentax AFPointInfo Tags

AF point information written by the K-1.

Index1	Tag Name	Writable
2	NumAFPoints	int16u
4	AFPointsInFocus	int8u[9]~
4.1	AFPointsSelected	int8u[9]~
4.2	AFPointsSpecial	int8u[9]~

## Pentax TempInfo Tags

A number of additional temperature readings are extracted from this 256-byte binary-data block in images from models such as the K-01, K-3, K-5, K-50 and K-500. It is currently not known where the corresponding temperature sensors are located in the camera.

Tag Name	Writable
SensorTemperature	int16s
SensorTemperature2	int16s
CameraTemperature4	int16s
CameraTemperature5	int16s
	SensorTemperature SensorTemperature2 CameraTemperature4

#### Pentax UnknownInfo Tags

Index1	Tag Name	Writable
[no tags	known]	

## Pentax Type2 Tags

These tags are used by the Pentax Optio 330 and 430, and are similar to the tags used by Casio.

Tag ID	Tag Name	Writable
$0 \times 0001$	RecordingMode	int16u
0x0002	Quality	int16u
0x0003	FocusMode	int16u
$0 \times 0004$	FlashMode	int16u
$0 \times 0007$	WhiteBalance	int16u
0x000a	DigitalZoom	int32u
0x000b	Sharpness	int16u
0x000c	Contrast	int16u
0x000d	Saturation	int16u
$0 \times 0014$	ISO	int16u
$0 \times 0017$	ColorFilter	int16u
0x0e00	PrintIM	PrintIM
0x1000	HometownCityCode	undef[4]
0x1001	DestinationCityCode	undef[4]

## Pentax Type4 Tags

The following few tags are extracted from the wealth of information available in maker notes of the Optio E20 and E25. These maker notes are stored as ASCII text in a format very similar to some HP models.

Tag ID	Tag Name	Writable
'F/W Version'	FirmwareVersion	no

## Pentax S1 Tags

Tags extracted from the maker notes of AVI videos from the Optio S1.

Tag ID	Tag Name	Writable
0x0000	MakerNoteVersion	no

## Pentax Junk Tags

Tags found in the JUNK chunk of AVI videos from the RS1000.

Index1	Tag Name	Writable
12	Model	no

## Pentax Junk2 Tags

This information is found in AVI videos from the Optio RZ18.

Index1	Tag Name	Writable
18	Make	no
44	Model	no
94	FNumber	no
131	DateTime1	no
157	DateTime2	no
299	ThumbnailWidth	no
301	ThumbnailHeight	no
303	ThumbnailLength	no
307	ThumbnailImage	no

#### Pentax AVI Tags

Pentax-specific RIFF tags found in AVI videos.

Tritable
Pentax
Pentax
-

# <u>Pentax PENT Tags</u>

Tags found in the PENT atom of MOV videos from the Optio WG-2 GPS.

Index1	Tag Name	Writable
0	Make	no
26	Model	no
56	ExposureTime	no
60	FNumber	no
68	ExposureCompensation	no
84	FocalLength	no
113	DateTime1	no
139	DateTime2	no
167	ISO	no
199	GPSVersionID	no
207	GPSLatitudeRef	no
209	GPSLatitude	no
233	GPSLongitudeRef	no
235	GPSLongitude	no
259	GPSAltitudeRef	no
260	GPSAltitude	no
284	GPSTimeStamp	no
308	GPSSatellites	no
311	GPSStatus	no
313	GPSMeasureMode	no
315	GPSMapDatum	no
322	GPSDateStamp	no
371	AudioCodecID	no
2003	PreviewImage	no

## Pentax PXTH Tags

Tags found in the PXTH atom of MOV videos from the K-01.

Index1	Tag Name	Writable
0	PreviewImageLength	no
4	PreviewImage	no

## Pentax MOV Tags

This information is found in MOV videos from cameras such as the Optio  $\mbox{WP}\,.$ 

Index1	Tag Name	Writable
0	Make	no
38	ExposureTime	no
42	FNumber	no
50	ExposureCompensation	no
68	WhiteBalance	no
72	FocalLength	no
175	ISO	no

## PhaseOne Tags

These tags are extracted from the maker notes of Phase One images.

Tag ID	Tag Name	Writable
0x0100	CameraOrientation	no
$0 \times 0102$	SerialNumber	string
0x0105	ISO	int32s
$0 \times 0106$	ColorMatrix1	float[9]
$0 \times 0107$	WB_RGBLevels	float[3]
0x0108	SensorWidth	int32s
$0 \times 0109$	SensorHeight	int32s
0x010a	SensorLeftMargin	int32s
0x010b	SensorTopMargin	int32s
0x010c	ImageWidth	int32s
0x010d	ImageHeight	int32s
0x010e	RawFormat	int32s

0x010f	RawData	no
$0 \times 0110$	SensorCalibration	PhaseOne SensorCalibration
0x0112	DateTimeOriginal	no
0x0113	ImageNumber	int32s
0x0203	Software	string
$0 \times 0204$	System	string
0x0210	SensorTemperature	float
0x0211	SensorTemperature2	float
$0 \times 0212$	UnknownDate?	int32u
0x021c	StripOffsets	no
0x021d	BlackLevel	int32s
0x0222	SplitColumn	int32s
0x0223	BlackLevelData	int16u[n]
$0 \times 0226$	ColorMatrix2	float[9]
$0 \times 0267$	AFAdjustment	float
$0 \times 0301$	FirmwareVersions	string
$0 \times 0400$	ShutterSpeedValue	float
$0 \times 0401$	ApertureValue	float
$0 \times 0402$	ExposureCompensation	float
$0 \times 0403$	FocalLength	float
$0 \times 0410$	CameraModel	string
$0 \times 0412$	LensModel	string
$0 \times 0414$	MaxApertureValue	float
$0 \times 0415$	MinApertureValue	float
$0 \times 0455$	Viewfinder	string

# PhaseOne SensorCalibration Tags

Tag ID	Tag Name	Writable
$0 \times 0400$	SensorDefects	no
$0 \times 0401$	AllColorFlatField1?	no
$0 \times 0407$	SerialNumber	string
$0 \times 040 b$	RedBlueFlatField?	no
$0 \times 0410$	AllColorFlatField2?	no
$0 \times 0416$	AllColorFlatField3?	no
$0 \times 0419$	LinearizationCoefficients1	no
0x041a	LinearizationCoefficients2	no

# Reconyx Tags

The following tags are extracted from the maker notes of Reconyx Hyperfire cameras such as the HC500, HC600 and PC900.

Index2	Tag Name	Writable
0	MakerNoteVersion	no
1	FirmwareVersion	no
4	FirmwareDate	int16u[2]
6	TriggerMode	string[2]
7	Sequence	int16u[2]
9	EventNumber	int16u[2]
11	DateTimeOriginal	int16u[6]
18	MoonPhase	int16u
19	AmbientTemperatureFahrenheit	int16s
20	AmbientTemperature	int16s
21	SerialNumber	undef[30]
36	Contrast	int16u
37	Brightness	int16u
38	Sharpness	int16u
39	Saturation	int16u
40	InfraredIlluminator	int16u
41	MotionSensitivity	int16u
42	BatteryVoltage	int16u
43	UserLabel	string[22]

# Reconyx Type2 Tags

Tags extracted from models such as the UltraFire.

Index1 Tag Name

24	FirmwareVersion	undef[7]
31	MicrolVersion	undef[7]
38	BootLoaderVersion	undef[7]
45	Micro2Version	undef[7]
52	TriggerMode	undef[1]
53	Sequence	int8u[2]
55	EventNumber	int32u
59	DateTimeOriginal	int8u[7]
66	DayOfWeek	int8u
67	MoonPhase	int8u
68	AmbientTemperatureFahrenheit	int16s
70	AmbientTemperature	int16s
72	Illumination	int8u
73	BatteryVoltage	int16u
75	SerialNumber	string[15]
90	UserLabel	string[21]

# Reconyx Type3 Tags

Tags extracted from models such as the HF2 PRO.

	Index1	Tag Name	Writable
	16	 FileNumber	 int16u
	18	DirectoryNumber	int16u
	42	FirmwareVersion	int16u[3]
	48	FirmwareDate	int16u[2]
	52	TriggerMode	string[2]
	54	Sequence	int16u[2]
	58	EventNumber	int16u[2]
	62	DateTimeOriginal	int16u[6]
	74	DayOfWeek	int16u
	76	MoonPhase	int16u
	78	AmbientTemperatureFahrenheit	int16s
	80	AmbientTemperature	int16s
	82	Contrast	int16u
	84	Brightness	int16u
	86	Sharpness	int16u
	88	Saturation	int16u
	90	Flash	int16u
	92	AmbientInfrared	int16u
	94	AmbientLight	int16u
	96	MotionSensitivity	int16u
	98	BatteryVoltage	int16u
	100	BatteryVoltageAvg	int16u
	102	BatteryType	int16u
	104	UserLabel	string[22]
	126	SerialNumber	unicode[15]
Ricoh	Tags		
	Tag ID	Tag Name	Writable
	0x0001	MakerNoteType	string
	0x0002	FirmwareVersion	string
	0x0005	SerialNumber	undef[16]
	0110005	InternalSerialNumber	undef[16]
	0x0e00	PrintIM	PrintIM
	0x1000	RecordingFormat	int16u
	0x1001	ImageInfo	Ricoh ImageInfo
		ExposureProgram	int16u
	0x1002	DriveMode	int16u
	0x1003	Sharpness	int32u
		WhiteBalance	int16u
	0x1004	WhiteBalanceFineTune	int16u
	0x1006	FocusMode	int16u
	0x1007	AutoBracketing	int16u
	0x1009	MacroMode	int16u
	0x100a	FlashMode	int16u
	0x100b	FlashExposureComp	rational64s

	_	
0x100c	ManualFlashOutput	rational64s
0x100d	FullPressSnap	int16u
0x100e	DynamicRangeExpansion	int16u
0x100f	NoiseReduction	int16u
0x1010	ImageEffects	int16u
0x1011	Vignetting	int16u
0x1012	Contrast	int32u
0x1013	Saturation	int32u
0x1014	Sharpness	int32u
0x1015	ToningEffect	int16u
0x1016	HueAdjust	int16u
$0 \times 1017$	WideAdapter	int16u
0x1018	CropMode	int16u
0x1019	NDFilter	int16u
0x101a	WBBracketShotNumber	int16u
0x1200	AFStatus	int16u
0x1201	AFAreaXPosition1	int32u
0x1202	AFAreaYPosition1	int32u
0x1203	AFAreaXPosition	int32u
$0 \times 1204$	AFAreaYPosition	int32u
0x1205	AFAreaMode	int16u
0x1307	ColorTempKelvin	int32u
0x1308	ColorTemperature	int32u
0x1500	FocalLength	rational64u
0x1601	SensorWidth	int32u
$0 \times 1602$	SensorHeight	int32u
0x1603	CroppedImageWidth	int32u
0x1604	CroppedImageHeight	int32u
0x2001	RicohSubdir	Ricoh Subdir
	RicohSubdirIFD	Ricoh Subdir
	RicohRR1Subdir	Ricoh Subdir
$0 \times 4001$	ThetaSubdir	Ricoh ThetaSubdir

# Ricoh ImageInfo Tags

Index1	Tag Name	Writable
0	RicohImageWidth	int16u
2	RicohImageHeight	int16u
6	RicohDate	int8u[7]
28	PreviewImageStart	int16u*
30	PreviewImageLength	int16u*
32	FlashMode	int8u
33	Macro	int8u
34	Sharpness	int8u
38	WhiteBalance	int8u
39	ISOSetting	int8u
40	Saturation	int8u

# Ricoh Subdir Tags

Tag ID	Tag Name	Writable
$0 \times 0 0 0 4$	ManufactureDate1	string[20]
0x0005	ManufactureDate2	string[20]
0x001a	FaceInfo	Ricoh FaceInfo
0x0029	FirmwareInfo	Ricoh FirmwareInfo
0x002a	NoiseReduction	int32u
0x002c	SerialInfo	Ricoh SerialInfo

# Ricoh FaceInfo Tags

Index1	Tag Name	Writable
181	FacesDetected	int8u
182	FaceDetectFrameSize	int16u[2]
188	Face1Position	int16u[4]
200	Face2Position	int16u[4]
212	Face3Position	int16u[4]
224	Face4Position	int16u[4]

236	Face5Position	int16u[4]
248	Face6Position	int16u[4]
260	Face7Position	int16u[4]
272	Face8Position	int16u[4]

## Ricoh FirmwareInfo Tags

Index1	Tag Name	Writable
0	FirmwareRevision	string[12]
12	FirmwareRevision2	string[12]

#### Ricoh SerialInfo Tags

This information is found in images from the GXR.

Index1	Tag Name	Writable
0	BodyFirmware	string[16]
16	BodySerialNumber	string[16]
32	LensFirmware	string[16]
48	LensSerialNumber	string[16]

#### Ricoh ThetaSubdir Tags

Tag ID	Tag Name	Writable
0x0003	Accelerometer	rational64s[2]
$0 \times 0004$	Compass	rational64u
0x000a	TimeZone	string

#### Ricoh Type2 Tags

Tags written by models such as the Ricoh HZ15 and the Pentax XG-1. These are not writable due to numerous formatting errors as written by these cameras.

Tag ID	Tag Name	Writable
$0 \times 0207$	RicohModel	no
$0 \times 0300$	RicohMake	no

## Ricoh Text Tags

Some Ricoh DC and RDC models use a text-based format for their maker notes instead of the IFD format used by the Caplio models. Below is a list of known tags in this information.

Tag ID	Tag Name	Writable
'Bg	BlueGain	no
' Gg '	GreenGain	no
'Rev'	FirmwareVersion	no
'Rg'	RedGain	no
'Rv'	FirmwareVersion	no

## Ricoh RMETA Tags

The Ricoh Caplio Pro G3 has the ability to add custom fields to the APP5 "RMETA" segment of JPEG images. While only a few observed tags have been defined below, ExifTool will extract any information found here.

Tag ID	Tag Name	Writable
'Azimuth'	Azimuth	no
'Condition'	Condition	no
'Lit'	Lit	no
'Location'	Location	no
'Sign type'	SignType	no

'\_audio' SoundFile no '\_barcode' Barcodes no+

## Ricoh AVI Tags

Tag ID	Tag Name	Writable
'mnrt'	MakerNoteRicoh	Ricoh
'rdc2'	RicohRDC2?	no
'thum'	ThumbnailImage	no
'ucmt'	Comment	no

#### Ricoh RDTA Tags

Tag ID	Tag Name	Writable
0x0000	Accelerometer	no
$0 \times 0010$	TimeStamp	no

#### Ricoh RDTB Tags

Tag ID	Tag Name	Writable
0x0000	Gyroscope	no
$0 \times 0010$	TimeStamp	no

## Ricoh RDTC Tags

Tag ID	Tag Name	Writable
0x0000	MagneticField	no
$0 \times 0010$	TimeStamp	no

#### Ricoh RDTG Tags

Tag ID	Tag Name	Writable
0x0000	TimeStamp	no
$0 \times 0064$	FrameNumber	no

# Ricoh RDTL Tags

Tag ID	Tag Name	Writable
0x0000	GPSDateTime	no
0x0008	GPSLatitude	no
$0 \times 0010$	GPSLongitude	no
0x0018	GPSAltitude	no

## Samsung Tags

Tags found in the binary "STMN" format maker notes written by a number of Samsung models.

Index4	Tag Name	Writable
0	MakerNoteVersion	undef[8]
2	PreviewImageStart	int32u*
3	PreviewImageLength	int32u*
11	SamsungIFD	Samsung IFD

## Samsung IFD Tags

This is a standard-format IFD found in the maker notes of some Samsung models, except that the entry count is a 4-byte integer and the offsets are relative to the end of the IFD. Currently, no tags in this IFD are known, so the Unknown (-u) or Verbose (-v) option must be used to see this information.

Tag ID	Tag Name	Writable

[no tags known]

# Samsung Type2 Tags

Tags found in the EXIF-format maker notes of newer Samsung models.

m TD	mar. Nama	77
Tag ID	Tag Name	Writable
		undef[4]
$0 \times 0001$	MakerNoteVersion	
$0 \times 0002$	DeviceType	int32u
0x0003	SamsungModelID	int32u
0x0011	OrientationInfo	Samsung OrientationInfo
$0 \times 0020$	SmartAlbumColor	int16u[2]
$0 \times 0021$	PictureWizard	Samsung PictureWizard
0x0030	LocalLocationName	string
0x0031	LocationName	string
$0 \times 0035$	PreviewIFD	Nikon PreviewIFD
		Nikon PreviewIFD
$0 \times 0040$	RawDataByteOrder	yes
$0 \times 0041$	WhiteBalanceSetup	int32u
$0 \times 0043$	CameraTemperature	rational64s
$0 \times 0050$	RawDataCFAPattern	yes
0x0100	FaceDetect	int16u
$0 \times 0120$	FaceRecognition	int32u
0x0123	FaceName	string
0xa001	FirmwareName	string
0xa002	SerialNumber	string
0xa003	LensType	int16u[n]
0xa004	LensFirmware	string
0xa005	InternalLensSerialNumber	string
0xa010	SensorAreas	int32u[8]
0xa011	ColorSpace	int16u
0xa012	SmartRange	int16u
0xa013	ExposureCompensation	rational64s
0xa014	ISO	int32u
0xa018	ExposureTime	rational64u
0xa019	FNumber	rational64u
0xa01a	FocalLengthIn35mmFormat	int32u
0xa020	EncryptionKey	int32u[11]!
0xa021	WB_RGGBLevelsUncorrected	int32u[4]
0xa022	WB_RGGBLevelsAuto	int32u[4]
0xa023	WB_RGGBLevelsIlluminator1	int32u[4]
0xa024	WB_RGGBLevelsIlluminator2	int32u[4]
0xa025	HighlightLinearityLimit	int32u
0xa028	WB_RGGBLevelsBlack	int32s[4]
0xa030	ColorMatrix	int32s[9]
0xa031	ColorMatrixSRGB	int32s[9]
0xa032	ColorMatrixAdobeRGB	int32s[9]
0xa033	CbCrMatrixDefault	int32s[4]
0xa034	CbCrMatrix	int32s[4]
0xa035	CbCrGainDefault	int32u[2]
0xa036	CbCrGain	int32u[2]
0xa040	ToneCurveSRGBDefault	int32u[23]
0xa041	ToneCurveAdobeRGBDefault	int32u[23]
0xa042	ToneCurveSRGB	int32u[23]
0xa043	ToneCurveAdobeRGB	int32u[23]
0xa048	RawData?	int32s[12]
0xa050	Distortion?	int32s[8]
0xa051	ChromaticAberration?	int16u[22]
0xa052	Vignetting?	int16u[15]
0xa053	VignettingCorrection?	int16u[15]
0xa054	VignettingSetting?	int16u[15]

# Samsung OrientationInfo Tags

Camera orientation information written by the Gear  $360 \, (SM-C200)$ .

Index8	Tag Name	Writable
0	YawAngle?	rational64s

1	PitchAngle	rational64s
2	RollAngle	rational64s

## Samsung PictureWizard Tags

Index2	Tag Name	Writable
0	PictureWizardMode	int16u
1	PictureWizardColor	int16u
2	PictureWizardSaturation	int16u
3	PictureWizardSharpness	int16u
4	PictureWizardContrast	int16u

## Samsung APP5 Tags

Tag ID	Tag Name	Writable
'ssuniqueid'	UniqueID	no

## Samsung Trailer Tags

Tags extracted from the SEFT trailer of JPEG and PNG images written when using certain features (such as "Sound & Shot" or "Shot & More") from Samsung models such as the Galaxy S4 and Tab S, and from the 'sefd' atom in HEIC images from models such as the S10+.

Tag Name	Writable
DepthMapData	no
DepthMapData2	no
DepthMapName	no
DualCameraImage	no
DualCameraImageName	no
DualShotExtra	Samsung DualShotExtra
EmbeddedAudioFile	no
EmbeddedAudioFileName	no
EmbeddedImage	no
EmbeddedImage2	no
EmbeddedImageName	no
EmbeddedVideoFile	no
EmbeddedVideoType	no
MCCData	no
PEg_Info	JSON
RemasterInfo	no
SamsungCaptureInfo	no
SingleShotDepthMap	no
SingleShotMeta	Samsung SingleShotMeta
SurroundShotVideo	no
SurroundShotVideoName	no
TimeStamp	no

# Samsung DualShotExtra Tags

Index4	Tag Name	Writable
16	DepthMapWidth	no
17	DepthMapHeight	no

## Samsung SingleShotMeta Tags

Tag Name	Writable
BeautyColorLevel	no
BeautyRetouchLevel	no
BlurStrength	no
BokehShape	no
ColorpopStrength	no
DepthHWHeight	no
DepthHWWidth	no
DepthSWHeight	no
	BeautyColorLevel BeautyRetouchLevel BlurStrength BokehShape ColorpopStrength DepthHWHeight DepthHWWidth

'depthSWWidth'	DepthSWWidth	no
'deviceOrientation'	DeviceOrientation	no
'effectStrength'	EffectStrength	no
'effectType'	EffectType	no
'flipStatus'	FlipStatus	no
'inputHeight'	InputHeight	no
'inputWidth'	InputWidth	no
'isArtBokeh'	IsArtBokeh	no
'lensFacing'	LensFacing	no
'monoStrength'	MonoStrength	no
'objectOrientation'	ObjectOrientation	no
'outputHeight'	OutputHeight	no
'outputWidth'	OutputWidth	no
'perfMode'	PerfMode	no
'segHeight'	SegHeight	no
'segWidth'	SegWidth	no
'sidelightStrength'	SidelightStrength	no
'spinStrength'	SpinStrength	no
'vintageStrength'	VintageStrength	no
'zoomStrength'	ZoomStrength	no

#### Samsung sec Tags

This information is found in the @sec atom of Samsung MP4 videos from models such as the WB30F.

Index1	Tag Name	Writable
0	Make	no
32	Model	no
512	ThumbnailWidth	no
516	ThumbnailHeight	no
520	ThumbnailLength	no
524	ThumbnailImage	no

## Samsung INFO Tags

This information is found in MP4 videos from Samsung models such as the  ${\tt SMX-C20N}.$ 

Tag ID	Tag Name	Writable
'EFCT'	Effect	no
'QLTY'	Quality	no

## Samsung MP4 Tags

This information is found in Samsung MP4 videos from models such as the WP10.

Index1	Tag Name	Writable
0	Make	no
24	Model	no
46	ExposureTime	no
50	FNumber	no
58	ExposureCompensation	no
106	ISO	no
125	Software	no
244	Thumbnail	Samsung Thumbnail

## Samsung Thumbnail Tags

Tag Name	Writable
ThumbnailWidth	no
ThumbnailHeight	no
ThumbnailLength	no
ThumbnailOffset	no
	ThumbnailWidth ThumbnailHeight ThumbnailLength

#### Samsung smta Tags

This information is found in the smta atom of Samsung MP4 videos from models such as the Galaxy S4.

Tag ID	Tag Name	Writable
'mdln'	SamsungModel	no
'svss'	SamsungSvss	Samsung svss

## Samsung svss Tags

This information is found in the svss atom of Samsung MP4 videos from models such as the Galaxy S4.

Tag ID	Tag Name	Writable
Ino tags	knownl	

## Sanyo Tags

rags		
Tag ID	Tag Name	Writable
0x00ff	MakerNoteOffset	int32u
$0 \times 0100$	SanyoThumbnail	undef
$0 \times 0200$	SpecialMode	int32u[3]
$0 \times 0201$	SanyoQuality	int16u
$0 \times 0202$	Macro	int16u
$0 \times 0204$	DigitalZoom	rational64u
$0 \times 0207$	SoftwareVersion	yes
0x0208	PictInfo	yes
0x0209	CameraID	yes
0x020e	SequentialShot	int16u
0x020f	WideRange	int16u
$0 \times 0210$	ColorAdjustmentMode	int16u
$0 \times 0213$	QuickShot	int16u
$0 \times 0214$	SelfTimer	int16u
$0 \times 0216$	VoiceMemo	int16u
$0 \times 0217$	RecordShutterRelease	int16u
$0 \times 0218$	FlickerReduce	int16u
$0 \times 0219$	OpticalZoomOn	int16u
0x021b	DigitalZoomOn	int16u
0x021d	LightSourceSpecial	int16u
0x021e	Resaved	int16u
0x021f	SceneSelect	int16u
$0 \times 0223$	ManualFocusDistance	rational64u
	FaceInfo	-
$0 \times 0224$	SequenceShotInterval	int16u
$0 \times 0225$	FlashMode	int16u
0x0e00	PrintIM	PrintIM
0x0f00	DataDump	no

# Sanyo FaceInfo Tags

Index4	Tag Name	Writable
0	FacesDetected	int32u
4	FacePosition	int32u[4]

#### Sanyo MOV Tags

This information is found in Sanyo MOV videos.

Index1	Tag Name	Writable
0	Make	no
24	Model	no
38	ExposureTime	no
42	FNumber	no
50	ExposureCompensation	no
68	WhiteBalance	no

no

## 72 FocalLength

## Sanyo MP4 Tags

This information is found in Sanyo MP4 videos.

Index1	Tag Name	Writable
0	Make	no
24	Model	no
50	FNumber	no
58	ExposureCompensation	no
106	ISO	no
209	Software	no
210	Software	no
241	Thumbnail	Sanyo Thumbnail
242	Thumbnail	Sanyo Thumbnail

## Sanyo Thumbnail Tags

Index4	Tag Name	Writable
1	ThumbnailWidth	no
2	ThumbnailHeight	no
3	ThumbnailLength	no
4	ThumbnailOffset	no

## Sigma Tags

These tags are written by Sigma/Foveon cameras. In the early days Sigma was a class leader by releasing their maker note specification to the public, but since then they have deviated from this standard and newer camera models are less than consistent about their metadata formats.

	Пос. Може	Mai table
Tag ID	Tag Name	Writable
0×0002	SerialNumber	string
0x0002	DriveMode	string
$0 \times 00003$	ResolutionMode	string
$0 \times 0005$	AFMode	string
0x0005	FocusSetting	string
0x0000	WhiteBalance	string
0x0007	ExposureMode	string
0x0009	MeteringMode	string
0x0003	LensFocalRange	string
0x000b	ColorSpace	string
0x000c	ExposureCompensation	string
0110000	ExposureAdjust?	rational64s
0x000d	Contrast	string
0110004	Contrast	rational64s
0x000e	Shadow	string
0110000	Shadow	rational64s
0x000f	Highlight	string
	Highlight	rational64s
0x0010	Saturation	string
	Saturation	rational64s
0x0011	Sharpness	string
	Sharpness	rational64s
0x0012	X3FillLight	string
	X3FillLight	rational64s
$0 \times 0014$	ColorAdjustment	string
	ColorAdjustment	rational64s[3]
$0 \times 0015$	AdjustmentMode	string
$0 \times 0016$	Quality	string
$0 \times 0017$	Firmware	string
$0 \times 0018$	Software	string
$0 \times 0019$	AutoBracket	string
0x001a	PreviewImageStart	int32u*
	ChrominanceNoiseReduction	string
0x001b	PreviewImageLength	int32u*

0 001	LuminanceNoiseReduction	string
0x001c	PreviewImageSize	int16u[2]
0 0011	PreviewImageStart	int32u*
0x001d	MakerNoteVersion	undef
0001 -	PreviewImageLength	int32u*
0x001e	PreviewImageSize	int16u[2]
0x001f	AFPoint	string
0 0000	MakerNoteVersion	undef
$0 \times 0022$	FileFormat	string
$0 \times 0024$	Calibration	string
$0 \times 0026$	FileFormat	string
0x0027	LensType	string
	LensType	- G'
0000-	I I D	Sigma LensType
0x002a	LensFocalRange	rational64u[2]
0x002b	LensMaxApertureRange	rational64u[2]
0x002c	ColorMode	int32u
$0 \times 0030$	LensApertureRange	string
0 0001	Calibration	string
$0 \times 0031$	FNumber	rational64u
$0 \times 0032$	ExposureTime	rational64u
0x0033	ExposureTime2	string
0x0034	BurstShot	int32u
$0 \times 0035$	ExposureCompensation	rational64s
0x0039	SensorTemperature	string
0x003a	FlashExposureComp	rational64s
0x003b	Firmware	string
0x003c	WhiteBalance	string
0x003d	PictureMode	string
$0 \times 0048$	LensApertureRange	string
$0 \times 0049$	FNumber	rational64u
0x004a	ExposureTime	rational64u
0x004b	ExposureTime2	string
$0 \times 004d$	ExposureCompensation	rational64s
$0 \times 0.055$	SensorTemperature	string
$0 \times 0.056$	FlashExposureComp	rational64s
$0 \times 0.057$	Firmware2	string
$0 \times 0.058$	WhiteBalance	string
0x0059	DigitalFilter	string
0x0084	Model	string
$0 \times 00086$	ISO	int16u
$0 \times 0087$	ResolutionMode	string
$0 \times 0088$	WhiteBalance	string
0x008c	Firmware	string
0x011f	CameraCalibration	float[9]
$0 \times 0120$	WBSettings	Sigma WBSettings
0x0121	WBSettings2	Sigma WBSettings2

# Sigma WBSettings Tags

Index4	Tag Name	Writable
0	WB_RGBLevelsAuto	float[3]
3	WB_RGBLevelsDaylight	float[3]
6	WB_RGBLevelsShade	float[3]
9	WB_RGBLevelsOvercast	float[3]
12	WB_RGBLevelsIncandescent	float[3]
15	WB_RGBLevelsFluorescent	float[3]
18	WB_RGBLevelsFlash	float[3]
21	WB_RGBLevelsCustom1	float[3]
24	WB_RGBLevelsCustom2	float[3]
27	WB_RGBLevelsCustom3	float[3]

# Sigma WBSettings2 Tags

Index4	Tag Name	Writable
0	WB_RGBLevelsUnknown0?	float[3]
3	WB_RGBLevelsUnknown1?	float[3]
6	WB_RGBLevelsUnknown2?	float[3]

9	WB_RGBLevelsUnknown3?	float[3]
12	WB_RGBLevelsUnknown4?	float[3]
15	WB_RGBLevelsUnknown5?	float[3]
18	WB_RGBLevelsUnknown6?	float[3]
21	WB_RGBLevelsUnknown7?	float[3]
24	WB_RGBLevelsUnknown8?	float[3]
27	WB RGBLevelsUnknown9?	float[3]

## Sony Tags

The following information has been decoded from the MakerNotes of Sony cameras. Some of these tags have been inherited from the Minolta MakerNotes.

Tag ID	Tag Name	Writable
0x0010	CameraInfo	Sony CameraInfo
	CameraInfo2	Sony CameraInfo2
	CameraInfo3	Sony CameraInfo3
	CameraInfoUnknown	Sony CameraInfoUnknown
0x0020	FocusInfo	Sony FocusInfo
	MoreInfo	Sony MoreInfo
0x0102	Quality	int32u
$0 \times 0104$	FlashExposureComp	rational64s
0x0105	Teleconverter	int32u
$0 \times 0112$	WhiteBalanceFineTune	int32u
$0 \times 0114$	CameraSettings	Sony CameraSettings
	CameraSettings2	Sony CameraSettings2
	CameraSettings3	Sony CameraSettings3
	CameraSettingsUnknown	Sony CameraSettingsUnknown
$0 \times 0115$	WhiteBalance	int32u
0x0116	ExtraInfo	Sony ExtraInfo
	ExtraInfo2	Sony ExtraInfo2
	ExtraInfo3	Sony ExtraInfo3
0x0e00	PrintIM	PrintIM
0x1000	MultiBurstMode	undef
0x1001	MultiBurstImageWidth	int16u
0x1002	MultiBurstImageHeight	int16u
0x1003	Panorama	Sony Panorama
0x2001	PreviewImage	undef
0x2002	Rating	int32u
0x2004	Contrast	int32s
0x2005	Saturation	int32s
0x2006	Sharpness	int32s
0x2007	Brightness	int32s
0x2008	LongExposureNoiseReduction	int32u
0x2009	HighISONoiseReduction	int16u
0x200a	HDR	int32u
0x200b	MultiFrameNoiseReduction	int32u
0x200e	PictureEffect	int16u
0x200f	SoftSkinEffect	int32u
0x2010	Tag2010a	Sony Tag2010a
	Tag2010b	Sony Tag2010b
	Tag2010c	Sony Tag2010c
	Tag2010d	Sony Tag2010d
	Tag2010e	Sony Tag2010e
	Tag2010f	Sony Tag2010f
	Tag2010g	Sony Tag2010g
	Tag2010h	Sony Tag2010h
	Tag2010i	Sony Tag2010i
0x2011	VignettingCorrection	int32u
0x2012	LateralChromaticAberration	int32u
0x2013	DistortionCorrectionSetting	int32u
0x2014	WBShiftAB_GM	int32s[2]
0x2016	AutoPortraitFramed	int16u
0x2017	FlashAction	int32u
0x201a	ElectronicFrontCurtainShutter	int32u
0x201b	FocusMode	int8u
0x201c	AFAreaModeSetting	int8u
0x201d	FlexibleSpotPosition	int16u[2]
0x201e	AFPointSelected	int8u

	EXITION 13.24 Tag Names	
0x2020	AFPointsUsed	no
0x2021	AFTracking	int8u
0x2022	FocalPlaneAFPointsUsed	no
0x2023	MultiFrameNREffect	int32u
0x2026	WBShiftAB_GM_Precise	int32s[2]~
0x2027	FocusLocation	int16u[4]
0x2028	VariableLowPassFilter	int16u[2]
0x2020	RAWFileType	int16u
0x2029 0x202a		Sony Tag202a
	Tag202a	int8u
0x202b	PrioritySetInAWB	
0x202c	MeteringMode2	int16u
0x202d	ExposureStandardAdjustment	rational64s
0x202e	Quality	int16u[2]
0x202f	PixelShiftInfo	undef
0x2031	SerialNumber	string
0x2032	Shadows	int32s
0x2033	Highlights	int32s
0x2034	Fade	int32s
0x2035	SharpnessRange	int32s
0x2036	Clarity	int32s
0x2037	FocusFrameSize	no
0x2039	JPEG-HEIFSwitch	int16u
0x2044	HiddenInfo	Sony HiddenInfo
0x204a	FocusLocation2	int16u[4]
0x3000	ShotInfo	Sony ShotInfo
0x900b	Tag900b	Sony Tag900b
0x9050	Tag9050a	Sony Tag9050a
	Tag9050b	Sony Tag9050b
	Tag9050c	Sony Tag9050c
	Tag9050d	Sony Tag9050d
0x9400	Tag9400a	Sony Tag9400a
027400	Tag9400b	Sony Tag9400a Sony Tag9400b
	Tag9400c	Sony Tag9400D
0x9401	Tag9401	Sony Tag94000 Sony Tag9401
0x9401 0x9402	<del>-</del>	
	Tag9402	Sony Tag9402
0x9403	Tag9403	Sony Tag9403
0x9404	Tag9404a	Sony Tag9404a
	Tag9404b	Sony Tag9404b
	Tag9404c	Sony Tag9404c
0x9405	Tag9405a	Sony Tag9405a
	Tag9405b	Sony Tag9405b
0x9406	Tag9406	Sony Tag9406
	Tag9406b	Sony Tag9406b
0x940a	Tag940a	Sony Tag940a
0x940c	Tag940c	Sony Tag940c
0x940e	AFInfo	Sony AFInfo
	Tag940e	Sony Tag940e
0x9416	Sony_0x9416	Sony Tag9416
0xb000	FileFormat	int8u[4]
0xb001	SonyModelID	int16u
0xb020	CreativeStyle	string
0xb021	ColorTemperature	int32u
0xb022	ColorCompensationFilter	int32u
0xb023	SceneMode	int32u
0xb024	ZoneMatching	int32u
0xb025	DynamicRangeOptimizer	int32u
0xb026	ImageStabilization	int32u
0xb027	LensType	int32u
0xb028	MinoltaMakerNote	Minolta
0xb029	ColorMode	int32u
0xb025	LensSpec	int8u[8]
0xb02a	FullImageSize	int32u[2]
0xb02b 0xb02c	PreviewImageSize	int32u[2]
0xb02C	Macro	int16u
0xb040 0xb041		int16u
0xb041 0xb042	ExposureMode FocusMode	int16u
0xb042 0xb043	AFAreaMode	int16u int16u
0xb043 0xb044	AFIlluminator	int16u int16u
0xb047 0xb048	JPEGQuality FlashLevel	int16u int16s
0 <del>2</del> U U X U	L TOSITHEAET	1110108

0xb049	ReleaseMode	int16u
0xb04a	SequenceNumber	int16u
0xb04b	Anti-Blur	int16u
0xb04e	FocusMode	int16u
0xb04f	DynamicRangeOptimizer	int16u
0xb050	HighISONoiseReduction2	int16u
0xb052	IntelligentAuto	int16u
0xb054	WhiteBalance	int16u

## Sony CameraInfo Tags

Camera information for the A700, A850 and A900.

Index1	Tag Name	Writable
0	LensSpec	undef[8]
20	FocusModeSetting	int8u
21	AFPointSelected	int8u
25	AFPoint	int8u
30	AFStatusActiveSensor	int16s
32	AFStatusUpper-left	int16s
34	AFStatusLeft	int16s
36	AFStatusLower-left	int16s
38	AFStatusFarLeft	int16s
40	AFStatusBottomAssist-left	int16s
42	AFStatusBottom	int16s
44	AFStatusBottomAssist-right	int16s
46	AFStatusCenter-7	int16s
48	AFStatusCenter-horizontal	int16s
	AFStatusCenter-9	int16s
	AFStatusCenter-10	int16s
54	AFStatusCenter-11	int16s
56	AFStatusCenter-12	int16s
58	AFStatusCenter-vertical	int16s
60	AFStatusCenter-14	int16s
62	AFStatusTopAssist-left	int16s
64	AFStatusTop	int16s
66	AFStatusTopAssist-right	int16s
68	AFStatusFarRight	int16s
70	AFStatusUpper-right	int16s
72	AFStatusRight	int16s
74	AFStatusLower-right	int16s
76	AFStatusCenterF2-8	int16s
304	AFMicroAdjValue	int8u
305	AFMicroAdjMode	int8u & 0x80
305.1	AFMicroAdjRegisteredLenses	int8u & 0x7f

# Sony CameraInfo2 Tags

Camera information for the DSLR-A200, A230, A290, A300, A330, A350, A380 and A390.

Index1	Tag Name	Writable
0	LensSpec	undef[8]
20	AFPointSelected	int8u
21	FocusModeSetting	int8u
24	AFPoint	int8u
27	AFStatusActiveSensor	int16s
29	AFStatusTop-right	int16s
31	AFStatusBottom-right	int16s
33	AFStatusBottom	int16s
35	AFStatusMiddleHorizontal	int16s
37	AFStatusCenterVertical	int16s
39	AFStatusTop	int16s
41	AFStatusTop-left	int16s
43	AFStatusBottom-left	int16s
45	AFStatusLeft	int16s
47	AFStatusCenterHorizontal	int16s
49	AFStatusRight	int16s

## Sony CameraInfo3 Tags

Camera information stored by the A33, A35, A55, A450, A500, A550, A560, A580, NEX-3/5/5C/C3 and VG10E. Some tags are valid only for some of these models.

Index1	Tag Name	Writable
0	LensSpec	undef[8]
14	FocalLength	int16u
16	FocalLengthTeleZoom	int16u
20	AFPointSelected	int8u
21	FocusMode	int8u
24	AFPoint	int8u
25	FocusStatus	int8u
27	AFStatusActiveSensor	int16s
28	AFPointSelected	int8u
29	FocusMode	int8u
	AFStatusTop-right	int16s
31	AFStatusBottom-right	int16s
32	AFPoint	int8u
33	AFStatusActiveSensor	int16s
	AFStatusBottom	int16s
35	AFStatus15	Sony AFStatus15
	AFStatusMiddleHorizontal	int16s
37	AFStatusCenterVertical	int16s
39	AFStatusTop	int16s
41	AFStatusTop-left	int16s
43	AFStatusBottom-left	int16s
45	AFStatusLeft	int16s
47	AFStatusCenterHorizontal	int16s
49	AFStatusRight	int16s

## Sony AFStatus15 Tags

AF Status information for models with 15-point AF.

Index1	Tag Name	Writable
0	 AFStatusUpper-left	 int16s
2	AFStatusLeft	int16s
4	AFStatusLower-left	int16s
6	AFStatusFarLeft	int16s
8	AFStatusTopHorizontal	int16s
10	AFStatusNearRight	int16s
12	AFStatusCenterHorizontal	int16s
14	AFStatusNearLeft	int16s
16	AFStatusBottomHorizontal	int16s
18	AFStatusTopVertical	int16s
20	AFStatusCenterVertical	int16s
22	AFStatusBottomVertical	int16s
24	AFStatusFarRight	int16s
26	AFStatusUpper-right	int16s
28	AFStatusRight	int16s
30	AFStatusLower-right	int16s
32	AFStatusUpper-middle	int16s
34	AFStatusLower-middle	int16s

## Sony CameraInfoUnknown Tags

Index1	Tag Name	Writable
[no tags	known l	

## Sony FocusInfo Tags

More camera settings and focus information decoded for models such as the A200, A230, A290, A300, A330, A350, A380, A390, A700, A850 and A900.

Index1	Tag Name	Writable
14	DriveMode2	int8u
16	Rotation	int8u
20	ImageStabilizationSetting	int8u
21	DynamicRangeOptimizerMode	int8u
43	BracketShotNumber	int8u
44	WhiteBalanceBracketing	int8u
45	BracketShotNumber2	int8u
46	DynamicRangeOptimizerBracket	int8u
47	ExposureBracketShotNumber	int8u
63	ExposureProgram	int8u
65	CreativeStyle	int8u
109	ISOSetting	int8u
111	ISO	int8u
119	DynamicRangeOptimizerMode	int8u
121	DynamicRangeOptimizerLevel	int8u
2118	ShutterCount	int32u
2491	FocusPosition	int8u
4368	TiffMeteringImage	no

# Sony MoreInfo Tags

More camera settings information decoded for the A450, A500, A550, A560, A580, A33, A35, A55, NEX-3/5/C3 and VG10E.

Tag ID	Tag Name	Writable
0x0001	MoreSettings	Sony MoreSettings
$0 \times 0002$	FaceInfo	Sony FaceInfo
	FaceInfoA	Sony FaceInfoA
$0 \times 0107$	TiffMeteringImage	no
$0 \times 0201$	MoreInfo0201	Sony MoreInfo0201
$0 \times 0401$	MoreInfo0401	Sony MoreInfo0401

# Sony MoreSettings Tags

Index1	Tag Name	Writable
1	DriveMode2	int8u
2	ExposureProgram	int8u
3	MeteringMode	int8u
4	DynamicRangeOptimizerSetting	int8u
5	DynamicRangeOptimizerLevel	int8u
6	ColorSpace	int8u
7	CreativeStyleSetting	int8u
8	ContrastSetting	int8s
9	SaturationSetting	int8s
10	SharpnessSetting	int8s
13	WhiteBalanceSetting	int8u
14	ColorTemperatureSetting	int8u
15	ColorCompensationFilterSet	int8s
16	FlashMode	int8u
17	LongExposureNoiseReduction	int8u
18	HighISONoiseReduction	int8u
19	FocusMode	int8u
21	MultiFrameNoiseReduction	int8u
22	HDRSetting	int8u
23	HDRLevel	int8u
24	ViewingMode	int8u
25	FaceDetection	int8u
26	CustomWB_RBLevels	int16uRev[2]
30	BrightnessValue	int8u
	ExposureCompensationSet	int8u
31	ISO	int8u
	FlashExposureCompSet	int8u
32	FNumber	int8u
	LiveViewAFMethod	int8u
33	ExposureTime	int8u

34	ISO FNumber	int8u int8u
35	FocalLength2 ExposureTime	int8u int8u
36	ExposureCompensation2	int16s
37	FocalLength2	int8u
2.0	ISO	int8u
38	FlashExposureCompSet2	int16s
	ExposureCompensation2 FNumber	int16s int8u
39	ExposureTime	int8u
40	Orientation2	int8u
41	FocusPosition2	int.8u
41	FocalLength2	int8u
42	FlashAction	int8u
	ExposureCompensation2	int16s
43	FocusPosition2	int8u
44	FocusMode2	int8u
	FlashAction	int8u
	FlashExposureCompSet2	int16s
46	FocusMode2	int8u
	Orientation2	int8u
47	FocusPosition2	int8u
48	FlashAction	int8u
50	FocusMode2	int8u
119	FlashAction2	int8u
120	FlashActionExternal	int8u
124	FlashActionExternal	int8u
130	FlashStatus	int8u
134	FlashStatus	int8u

# Sony FaceInfo Tags

Index2	Tag Name	Writable
0	FacesDetected	int16s
1	Face1Position	int16u[4]
6	Face2Position	int16u[4]
11	Face3Position	int16u[4]
16	Face4Position	int16u[4]
21	Face5Position	int16u[4]
26	Face6Position	int16u[4]
31	Face7Position	int16u[4]
36	Face8Position	int16u[4]

# Sony FaceInfoA Tags

Index2	Tag Name	Writable
3	FacesDetected	no
11	PotentialFace1Position	int16u[4]
21	PotentialFace2Position	int16u[4]
31	PotentialFace3Position	int16u[4]
41	PotentialFace4Position	int16u[4]
51	PotentialFace5Position	int16u[4]
61	PotentialFace6Position	int16u[4]
71	PotentialFace7Position	int16u[4]
81	PotentialFace8Position	int16u[4]
91	Face1Position	int16u[4]
101	Face2Position	int16u[4]
111	Face3Position	int16u[4]
121	Face4Position	int16u[4]

# Sony MoreInfo0201 Tags

Index1	Tag Name	Writable
283	ImageCount	int32u
293	ShutterCount	int32u
330	ShutterCount	int32u

# Sony MoreInfo0401 Tags

Index1	Tag Name	Writable
1102	ShotNumberSincePowerUp	int32u

## Sony CameraSettings Tags

Camera settings for the A200, A300, A350, A700, A850 and A900.

Index2	Tag Name	Writable
		wiicabie
0	ExposureTime	int16u
1	FNumber	int16u
2	HighSpeedSync	int16u
3	ExposureCompensationSet	int16u
4	DriveMode	int16u & 0xff
5	WhiteBalanceSetting	int16u
6	WhiteBalanceFineTune	int16u
7	ColorTemperatureSet	int16u
8	ColorCompensationFilterSet	int16u
12	ColorTemperatureCustom	int16u
13	ColorCompensationFilterCustom	int16u
15	WhiteBalance	int16u
16	FocusModeSetting	int16u
17	AFAreaMode	int16u
18	AFPointSetting	int16u
19	FlashMode	int16u
20	FlashExposureCompSet	int16u
21	MeteringMode	int16u
22	ISOSetting	int16u
24	DynamicRangeOptimizerMode	int16u
25	DynamicRangeOptimizerLevel	int16u
26	CreativeStyle	int16u
27	ColorSpace	int16u
28	Sharpness	int16u
29	Contrast	int16u
30	Saturation	int16u
31	ZoneMatchingValue	int16u
34	Brightness	int16u
35	FlashControl	int16u
40	PrioritySetupShutterRelease	int16u
41	AFIlluminator	int16u
42	AFWithShutter	int16u
43	LongExposureNoiseReduction	int16u
44	HighISONoiseReduction	int16u
45	ImageStyle	int16u
46	FocusModeSwitch	int16u
47	ShutterSpeedSetting	int16u
48	ApertureSetting	int16u
60	ExposureProgram	int16u
61	ImageStabilizationSetting	int16u
62	FlashAction	int16u
63	Rotation	int16u
64	AELock	int16u
76	FlashAction2	int16u
77	FocusMode	int16u
80	BatteryState	int16u
81	BatteryLevel	int16u
83	FocusStatus	int16u
84	SonyImageSize	int16u
85	AspectRatio	int16u
86	Quality	int16u
88	ExposureLevelIncrements	int16u
106	RedEyeReduction	int16u
154	FolderNumber	int16u & 0x3ff
155	ImageNumber	int16u & 0x3fff

Camera settings for the A230, A290, A330, A380 and A390.

Index2	Tag Name	Writable
0	ExposureTime	int16u
1	FNumber	int16u
2	HighSpeedSync	int16u
3	ExposureCompensationSet	int16u
4	WhiteBalanceSetting	int16u
5	WhiteBalanceFineTune	int16u
6	ColorTemperatureSet	int16u
7	ColorCompensationFilterSet	int16u
8	CustomWB_RGBLevels	int16u[3]
11	ColorTemperatureCustom	int16u
12	ColorCompensationFilterCustom	int16u
14	WhiteBalance	int16u
15	FocusModeSetting	int16u
16	AFAreaMode	int16u
17	AFPointSetting	int16u
18	FlashExposureCompSet	int16u
19	MeteringMode	int16u
20	ISOSetting	int16u
22	DynamicRangeOptimizerMode	int16u
23	DynamicRangeOptimizerLevel	int16u
24	CreativeStyle	int16u
25	Sharpness	int16u
26	Contrast	int16u
27	Saturation	int16u
31	FlashControl	int16u
37	LongExposureNoiseReduction	int16u
38	HighISONoiseReduction	int16u
39	ImageStyle	int16u
40 41	ShutterSpeedSetting	int16u
60	ApertureSetting	int16u
60 61	ExposureProgram TmageStabilizationSatting	int16u int16u
62	ImageStabilizationSetting FlashAction	int16u
63	Rotation	int16u
64	AELock	int16u
76	FlashAction2	int16u
77	FocusMode	int16u
83	FocusStatus	int16u
84	SonyImageSize	int16u
85	AspectRatio	int16u
86	Quality	int16u
88	ExposureLevelIncrements	int16u
126	DriveMode	int16u & 0xff
127	FlashMode	int16u
131	ColorSpace	int16u
~ -	<u>-</u>	- <del></del>

# Sony CameraSettings3 Tags

Camera settings for models such as the A33, A35, A55, A450, A500, A550, A560, A580, NEX-3, NEX-5, NEX-C3 and NEX-VG10E.

Index1	Tag Name	Writable
0	ShutterSpeedSetting	int8u
1	ApertureSetting	int8u
2	ISOSetting	int8u
3	ExposureCompensationSet	int8u
4	DriveModeSetting	int8u
5	ExposureProgram	int8u
6	FocusModeSetting	int8u
7	MeteringMode	int8u
9	SonyImageSize	int8u
10	AspectRatio	int8u
11	Quality	int8u
12	DynamicRangeOptimizerSetting	int8u

	_	
13	DynamicRangeOptimizerLevel	int8u
14	ColorSpace	int8u
15	CreativeStyleSetting	int8u
16	ContrastSetting	int8s
17	SaturationSetting	int8s
18	SharpnessSetting	int8s
22	WhiteBalanceSetting	int8u
23	ColorTemperatureSetting	int8u
24	ColorCompensationFilterSet	int8s
25	CustomWB_RGBLevels	<pre>int16uRev[3]</pre>
32	FlashMode	int8u
33	FlashControl	int8u
35	FlashExposureCompSet	int8u
36	AFAreaMode	int8u
37	LongExposureNoiseReduction	int8u
38	HighISONoiseReduction	int8u
39	SmileShutterMode	int8u
40	RedEyeReduction	int8u
45	HDRSetting	int8u
46	HDRLevel	int8u
47	ViewingMode	int8u
48	FaceDetection	int8u
49	SmileShutter	int8u
50	SweepPanoramaSize	int8u
51	SweepPanoramaDirection	int8u
52	DriveMode	int8u
53	MultiFrameNoiseReduction	int8u
54	LiveViewAFSetting	int8u
56	PanoramaSize3D	int8u
131	AFButtonPressed	int8u
132	LiveViewMetering	int8u
133	ViewingMode2	int8u
134	AELock	int8u
135	FlashStatusBuilt-in	int8u
136	FlashStatusExternal	int8u
139	LiveViewFocusMode	int8u
153	LensMount	int8u
268	SequenceNumber	int8u
276	FolderNumber	int32u & 0xffc000
276.1	ImageNumber	int32u & 0x3fff
512	ShotNumberSincePowerUp2	int32u
643	AFButtonPressed	int8u
644	LiveViewMetering	int8u
645	ViewingMode2	int8u
646	AELock	int8u
647	FlashStatusBuilt-in	int8u
648	FlashStatusExternal	int8u
651	LiveViewFocusMode	int8u
780	SequenceNumber	int8u
788	ImageNumber	int16u & 0x3fff
790	FolderNumber	int16u & 0x3ff
1008	LensE-mountVersion	int16u
1011	LensFirmwareVersion	int16u~
1015	LensType2	int16u
1024	ImageNumber	int16u & 0x3fff
1026	FolderNumber	int16u & 0x3ff
<u>ony Camer</u>	aSettingsUnknown Tags	

# Sony CameraSettingsUnknown Tags

Index2	Tag Name	Writable
[no tags	known]	

# Sony ExtraInfo Tags

Extra hardware information for the A850 and A900.

Index1	Tag Name	Writable
1	BatteryTemperature	int8u

2	BatteryUnknown?	no
8	BatteryVoltage?	no
10	ImageStabilization2?	int8u
12	BatteryLevel	int8u
26	ExtraInfoVersion	int8u[4]

## Sony ExtraInfo2 Tags

Extra hardware information for the A230/290/330/380/390.

Index1	Tag Name	Writable
4	BatteryLevel	int8u
18	ImageStabilization	int8u

## Sony ExtraInfo3 Tags

Extra hardware information for the A33, A35, A55, A450, A500, A550, A560, A580 and NEX-3/5/C3/VG10.

Index1	Tag Name	Writable
0	BatteryUnknown?	int16u
2	BatteryTemperature	int8u
4	BatteryLevel	int8u
6	BatteryVoltage1	int16u
8	BatteryVoltage2	int16u
17	ImageStabilization	int8u
20	BatteryState	int8u
	ExposureProgram	int8u
	ModeDialPosition	int8u
22	MemoryCardConfiguration	int8u & 0xc0
	CameraOrientation	int8u
24	CameraOrientation	int8u & 0x30

## Sony Panorama Tags

Tags found in panorama images from various Sony DSC, NEX, SLT and DSLR cameras. The width/height values of these tags are not affected by camera rotation -- the width is always the longer dimension.

Index4	Tag Name	Writable
1	PanoramaFullWidth	int32u
2	PanoramaFullHeight	int32u
3	PanoramaDirection	int32u
4	PanoramaCropLeft	int32u
5	PanoramaCropTop	int32u
6	PanoramaCropRight	int32u
7	PanoramaCropBottom	int32u
8	PanoramaFrameWidth	int32u
9	PanoramaFrameHeight	int32u
10	PanoramaSourceWidth	int32u
11	PanoramaSourceHeight	int32u

## Sony Tag2010a Tags

Valid for NEX-5N.

Index1	Tag Name	Writable
1200 4392 4396 4404 4408 4414 4416 4420 4424	MeterInfo? ReleaseMode3 ReleaseMode2 SelfTimer FlashMode StopsAboveBaseISO BrightnessValue DynamicRangeOptimizer HDRSetting	Sony MeterInfo int8u int8u int8u int8u int16u int16u int16u int8u int8u

4428	ExposureCompensation	int16s
4446	PictureProfile	int8u
4447	PictureProfile	int8u
4451	PictureEffect2	int8u
4464	Quality2	int8u
4468	MeteringMode	int8u
4469	ExposureProgram	int8u
4476	WB_RGBLevels	int16u[3]

## Sony MeterInfo Tags

Information possibly related to metering. Extracted only if the Unknown option is used.

Index1	Tag Name	Writable
0	MeterInfolRow1	int32u[27]
108	MeterInfolRow2	int32u[27]
216	MeterInfolRow3	int32u[27]
324	MeterInfolRow4	int32u[27]
432	MeterInfolRow5	int32u[27]
540	MeterInfolRow6	int32u[27]
648	MeterInfolRow7	int32u[27]
756	MeterInfo2Row1	int32u[33]
888	MeterInfo2Row2	int32u[33]
1020	MeterInfo2Row3	int32u[33]
1152	MeterInfo2Row4	int32u[33]
1284	MeterInfo2Row5	int32u[33]
1416	MeterInfo2Row6	int32u[33]
1548	MeterInfo2Row7	int32u[33]
1680	MeterInfo2Row8	int32u[33]
1812	MeterInfo2Row9	int32u[33]

## Sony Tag2010b Tags

Valid for SLT-A65/A77, NEX-7/VG20E.

Index1	Tag Name	Writable
0	SequenceImageNumber	int32u
4	SequenceFileNumber	int32u
8	ReleaseMode2	int32u
438	SonyDateTime	undef[7]
804	DynamicRangeOptimizer	int8u
1204	MeterInfo?	Sony MeterInfo
4392	ReleaseMode3	int8u
4396	ReleaseMode2	int8u
4404	SelfTimer	int8u
4408	FlashMode	int8u
4414	StopsAboveBaseISO	int16u
4416	BrightnessValue	int16u
4420	DynamicRangeOptimizer	int8u
4424	HDRSetting	int8u
4428	ExposureCompensation	int16s
4450	PictureProfile	int8u
4451	PictureProfile	int8u
4455	PictureEffect2	int8u
4468	Quality2	int8u
4472	MeteringMode	int8u
4473	ExposureProgram	int8u
4480	WB_RGBLevels	int16u[3]
4632	SonyISO	int16u
6691	DistortionCorrParams	int16s[16]

## Sony Tag2010c Tags

Valid for SLT-A37/A57 and NEX-F3.

Index1	Tag Name	Writable

0	SequenceImageNumber	int32u
4	SequenceFileNumber	int32u
8	ReleaseMode2	int32u
512	DigitalZoomRatio	int8u
528	SonyDateTime	undef[7]
768	DynamicRangeOptimizer	int8u
1168	MeterInfo?	Sony MeterInfo
4356	ReleaseMode3	int8u
4360	ReleaseMode2	int8u
4368	SelfTimer	int8u
4372	FlashMode	int8u
4378	StopsAboveBaseISO	int16u
4380	BrightnessValue	int16u
4384	DynamicRangeOptimizer	int8u
4388	HDRSetting	int8u
4392	ExposureCompensation	int16s
4414	PictureProfile	int8u
4415	PictureProfile	int8u
4419	PictureEffect2	int8u
4432	Quality2	int8u
4436	MeteringMode	int8u
4437	ExposureProgram	int8u
4444	WB_RGBLevels	int16u[3]
4596	SonyISO	int16u

## Sony Tag2010d Tags

 $\label{localization} \mbox{Valid for DSC-HX10V/HX20V/HX200V/TX66/TX200V/TX300V/WX50/WX100/WX150, but not valid for panorama images.}$ 

Index1	Tag Name	Writable
0	SequenceImageNumber	int32u
4	SequenceFileNumber	int32u
8	ReleaseMode2	int32u
510	SonyDateTime	undef[7]
892	DynamicRangeOptimizer	int8u
1292	MeterInfo?	Sony MeterInfo
4480	ReleaseMode3	int8u
4484	ReleaseMode2	int8u
4492	SelfTimer	int8u
4496	FlashMode	int8u
4502	StopsAboveBaseISO	int16u
4504	BrightnessValue	int16u
4508	DynamicRangeOptimizer	int8u
4512	HDRSetting	int8u
4538	PictureProfile	int8u
4539	PictureProfile	int8u
4543	PictureEffect2	int8u
4560	MeteringMode	int8u
4561	ExposureProgram	int8u
4568	WB_RGBLevels	int16u[3]
4720	SonyISO	int16u

# Sony Tag2010e Tags

Valid for SLT-A58/A99, ILCE-3000/3500, NEX-3N/5R/5T/6/VG30E/VG900, DSC-RX100, DSC-RX1/RX1R. Also valid for DSC-HX300/HX50V/TX30/WX60/WX200/ WX300, but not for panorama images.

Index1	Tag Name	Writable
0	SequenceImageNumber	int32u
4	SequenceFileNumber	int32u
8	ReleaseMode2	int32u
540	DigitalZoomRatio	int8u
556	SonyDateTime	undef[7]
808	DynamicRangeOptimizer	int8u
1208	MeterInfo?	Sony MeterInfo
4444	ReleaseMode3	int8u

4448	ReleaseMode2	int8u
4456	SelfTimer	int8u
4460	FlashMode	int8u
4466	StopsAboveBaseISO	int16u
4468	BrightnessValue	int16u
4472	DynamicRangeOptimizer	int8u
4476	HDRSetting	int8u
4480	ExposureCompensation	int16s
4502	PictureProfile	int8u
4503	PictureProfile	int8u
4507	PictureEffect2	int8u
4520	Quality2	int8u
4524	MeteringMode	int8u
4525	ExposureProgram	int8u
4532	WB_RGBLevels	int16u[3]
4692	SonyISO	int16u
4696	SonyISO	int16u
4728	FocalLength	int16u
4730	MinFocalLength	int16u
4732	MaxFocalLength	int16u
4736	SonyISO	int16u
6256	DistortionCorrParams	int16s[16]
6289	LensFormat	int8u
6290	LensMount	int8u
6291	LensType2	int16u
6294	LensType	int16u
6296	DistortionCorrParamsPresent	int8u
6297	DistortionCorrParamsNumber	int8u
6444	AspectRatio	int8u
6792	AspectRatio	int8u

## Sony Tag2010f Tags

Valid for DSC-RX100M2, DSC-QX10/QX100.

Index1	Tag Name	Writable
4	ReleaseMode2	int32u
80	DynamicRangeOptimizer	int8u
480	MeterInfo?	Sony MeterInfo
4116	ReleaseMode3	int8u
4120	ReleaseMode2	int8u
4128	SelfTimer	int8u
4132	FlashMode	int8u
4138	StopsAboveBaseISO	int16u
4140	BrightnessValue	int16u
4144	DynamicRangeOptimizer	int8u
4148	HDRSetting	int8u
4152	ExposureCompensation	int16s
4174	PictureProfile	int8u
4175	PictureProfile	int8u
4179	PictureEffect2	int8u
4192	Quality2	int8u
4196	MeteringMode	int8u
4197	ExposureProgram	int8u
4204	WB_RGBLevels	int16u[3]
4404	FocalLength	int16u
4406	MinFocalLength	int16u
4408	MaxFocalLength	int16u
4412	SonyISO	int16u
6444	AspectRatio	int8u

## Sony Tag2010g Tags

 $\label{local-problem} \begin{tabular}{ll} Valid for DSC-HX60V/HX350/HX400V/QX30/RX10/RX100M3/WX220/WX350, \\ ILCE-7/7R/7S/7M2/5000/5100/6000/QX1, ILCA-68/77M2. \\ \end{tabular}$ 

Index1	Tag Name	Writable
4	ReleaseMode2	int32u

### -- ExifTool 13.24 Tag Names --

80	DynamicRangeOptimizer	int8u
524	ReleaseMode3	int8u
528	ReleaseMode2	int8u
536	SelfTimer	int8u
540	FlashMode	int8u
546	StopsAboveBaseISO	int16u
548	BrightnessValue	int16u
552	DynamicRangeOptimizer	int8u
556	HDRSetting	int8u
560	ExposureCompensation	int16s
582	PictureProfile	int8u
583	PictureProfile	int8u
587	PictureEffect2	int8u
600	Quality2	int8u
604	MeteringMode	int8u
605	ExposureProgram	int8u
612	WB_RGBLevels	int16u[3]
812	FocalLength	int16u
814	MinFocalLength	int16u
816	MaxFocalLength	int16u
836	SonyISO	int16u
904	MeterInfo?	Sony MeterInfo
6300	DistortionCorrParams	int16s[16]
6333	LensFormat	int8u
6334	LensMount	int8u
6335	LensType2	int16u
6338	LensType	int16u
6340	DistortionCorrParamsPresent	int8u
6341	DistortionCorrParamsNumber	int8u
6488	AspectRatio	int8u

## Sony Tag2010h Tags

Valid for DSC-HX80/HX90V/RX0/RX1RM2/RX10M2/RX10M3/RX100M4/RX100M5/WX500, ILCE-6300/6500/7RM2/7SM2, ILCA-99M2.

Index1	Tag Name	Writable
4	ReleaseMode2	int32u
80	DynamicRangeOptimizer	int8u
524	ReleaseMode3	int8u
528	ReleaseMode2	int8u
536	SelfTimer	int8u
540	FlashMode	int8u
546	StopsAboveBaseISO	int16u
548	BrightnessValue	int16u
552	DynamicRangeOptimizer	int8u
556	HDRSetting	int8u
560	ExposureCompensation	int16s
582	PictureProfile	int8u
583	PictureProfile	int8u
587	PictureEffect2	int8u
600	Quality2	int8u
604	MeteringMode	int8u
605	ExposureProgram	int8u
612	WB_RGBLevels	int16u[3]
812	FocalLength	int16u
814	MinFocalLength	int16u
816	MaxFocalLength	int16u
838	SonyISO	int16u
904	MeterInfo?	Sony MeterInfo
920	MeterInfo?	Sony MeterInfo
6348	DistortionCorrParams	int16s[16]
6381	LensFormat	int8u
6382	LensMount	int8u
6383	LensType2	int16u
6386	LensType	int16u
6388	DistortionCorrParamsPresent	int8u
6389	DistortionCorrParamsNumber	int8u

6444 AspectRatio

int8u

## Sony Tag2010i Tags

Valid for ILCE-6100/6400/6600/7C/7M3/7RM3/7RM4/9/9M2, DSC-RX0M2/RX10M4/RX100M6/ RX100M5A/RX100M7/HX99.

Index1	Tag Name	Writable
4	ReleaseMode2	int32u
78	DynamicRangeOptimizer	int8u
516	ReleaseMode3	int8u
520	ReleaseMode2	int8u
528	SelfTimer	int8u
529	FlashMode	int8u
535	StopsAboveBaseISO	int16u
537	BrightnessValue	int16u
539	DynamicRangeOptimizer	int8u
543	HDRSetting	int8u
547	ExposureCompensation	int16s
567	PictureProfile	int8u
568	PictureProfile	int8u
572	PictureEffect2	int8u
583	Quality2	int8u
587	MeteringMode	int8u
588	ExposureProgram	int8u
594	WB_RGBLevels	int16u[3]
778	FocalLength	int16u
780	MinFocalLength	int16u
782	MaxFocalLength	int16u
800	SonyISO	int16u
877	MeterInfo?	Sony MeterInfo9
6096	DistortionCorrParams	int16s[16]
6129	LensFormat	int8u
6130	LensMount	int8u
6131	LensType2	int16u
6134	LensType	int16u
6136	DistortionCorrParamsPresent	int8u
6137	DistortionCorrParamsNumber	int8u
6284	AspectRatio	int8u

### Sony MeterInfo9 Tags

Information possibly related to metering. Extracted only if the Unknown option is used.

Index1	Tag Name	Writable
0	MeterInfolRow1	no
90	MeterInfolRow2	no
180	MeterInfolRow3	no
270	MeterInfolRow4	no
360	MeterInfolRow5	no
450	MeterInfolRow6	no
540	MeterInfolRow7	no
630	MeterInfo2Row1	no
740	MeterInfo2Row2	no
850	MeterInfo2Row3	no
960	MeterInfo2Row4	no
1070	MeterInfo2Row5	no
1180	MeterInfo2Row6	no
1290	MeterInfo2Row7	no
1400	MeterInfo2Row8	no
1510	MeterInfo2Row9	no

## Sony Tag202a Tags

Index1	Tag Name	Writable
1	FocalPlaneAFPointsUsed	int8u

2	FocalPlaneAFPointArea	int16u[2]
6	FocalPlaneAFPointLocation1	int16u[2]
10	FocalPlaneAFPointLocation2	int16u[2]
14	FocalPlaneAFPointLocation3	int16u[2]
18	FocalPlaneAFPointLocation4	int16u[2]
22	FocalPlaneAFPointLocation5	int16u[2]
26	FocalPlaneAFPointLocation6	int16u[2]
30	FocalPlaneAFPointLocation7	int16u[2]
34	FocalPlaneAFPointLocation8	int16u[2]
38	FocalPlaneAFPointLocation9	int16u[2]
42	FocalPlaneAFPointLocation10	int16u[2]
46	FocalPlaneAFPointLocation11	int16u[2]
50	FocalPlaneAFPointLocation12	int16u[2]
54	FocalPlaneAFPointLocation13	int16u[2]
58	FocalPlaneAFPointLocation14	int16u[2]
62	FocalPlaneAFPointLocation15	int16u[2]

## Sony HiddenInfo Tags

Index4	Tag Name	Writable
0	HiddenDataOffset	int32u
1	HiddenDataLength	int32u

## Sony ShotInfo Tags

Index1	Tag Name	Writable
2	FaceInfoOffset	no
6	SonyDateTime	string[20]
26	SonyImageHeight	int16u
28	SonyImageWidth	int16u
48	FacesDetected	int16u
50	FaceInfoLength	no
52	MetaVersion	string[16]
72	FaceInfo1	Sony FaceInfol
94	FaceInfo2	Sony FaceInfo2

## Sony FaceInfol Tags

Index1	Tag Name	Writable
0	FacelPosition	int16u[4]
32	Face2Position	int16u[4]
64	Face3Position	int16u[4]
96	Face4Position	int16u[4]
128	Face5Position	int16u[4]
160	Face6Position	int16u[4]
192	Face7Position	int16u[4]
224	Face8Position	int16u[4]

## Sony FaceInfo2 Tags

Index1	Tag Name	Writable
0	FacelPosition	int16u[4]
37	Face2Position	int16u[4]
74	Face3Position	int16u[4]
111	Face4Position	int16u[4]
148	Face5Position	int16u[4]
185	Face6Position	int16u[4]
222	Face7Position	int16u[4]
259	Face8Position	int16u[4]

## Sony Tag900b Tags

Tag Name	Writable
FacesDetected	no
FaceDetection	no
	 FacesDetected

### Sony Tag9050a Tags

Data for tags 0x9050, 0x94xx and 0x2010 is encrypted by a simple substitution cipher, but the deciphered values are listed below.

Tag Name	Writable
ConyMayApartura	 int.8u
	int8u
	int16u[3]
	int8u
	int32u
	int16u
	int16u
-	int8u
	int32u
	undef[6]
<del>-</del>	int8u
	int8u[4]~
	int8u[5]
	int8u
	int8u
	int16u
	int16u
	int8u
	int8u
-	undef[2]
-	undef[2]
_	int32u
	int32u
ShutterCount3	int32u
	SonyMaxAperture SonyMinAperture Shutter FlashStatus ShutterCount SonyExposureTime SonyFNumber ReleaseMode2 ShutterCount2 SonyDateTime2 ReleaseMode2 InternalSerialNumber InternalSerialNumber LensMount LensFormat LensType2 LensType DistortionCorrParamsPresent APS-CSizeCapture LensSpecFeatures LensSpecFeatures ShutterCount3 ShutterCount3

## Sony Tag9050b Tags

Valid from July 2015 for ILCE-6100/6300/6400/6500/6600/7C/7M3/7RM2/7RM3/7RM4/ 7SM2/9/9M2, ILCA-99M2.

Index1	Tag Name	Writable
0	SonyMaxAperture	int8u
1	SonyMinAperture	int8u
38	Shutter	int16u[3]
57	FlashStatus	int8u
58	ShutterCount	int32u
70	SonyExposureTime	int16u
72	SonyFNumber	int16u
75	ReleaseMode2	int8u
80	ShutterCount2	int32u
82	ShutterCount2	int32u
88	ShutterCount2	int32u
97	SonyTimeMinSec	no
107	ReleaseMode2	int8u
109	ReleaseMode2	int8u
115	ReleaseMode2	int8u
136	InternalSerialNumber	int8u[6]~
261	LensMount	int8u
262	LensFormat	int8u
263	LensType2	int16u
265	LensType	int16u
267	DistortionCorrParamsPresent	int8u
276	APS-CSizeCapture	int8u
278	LensSpecFeatures	undef[2]
415	ShutterCount3	int32u
459	ShutterCount3	int32u
461	ShutterCount3	int32u
491	APS-CSizeCapture	int8u
493	LensSpecFeatures	undef[2]
494	APS-CSizeCapture	int8u

496	LensSpecFeatures	undef[2]
538	APS-CSizeCapture	int8u
540	LensSpecFeatures	undef[2]
	APS-CSizeCapture	int8u
542	LensSpecFeatures	undef[2]

### Sony Tag9050c Tags

Valid from July 2020 for ILCE-1/7SM3, ILME-FX3.

Index1	Tag Name	Writable
38	Shutter	int16u[3]
57	FlashStatus	int8u
58	ShutterCount	int32u~
70	SonyExposureTime	int16u
72	SonyFNumber	int16u
75	ReleaseMode2	int8u
80	ShutterCount2	int32u
102	SonyExposureTime	int16u
104	SonyFNumber	int16u
107	ReleaseMode2	int8u
136	InternalSerialNumber	int8u[6]~
138	InternalSerialNumber	int8u[6]~

### Sony Tag9050d Tags

Valid for ILCE-6700/7CM2/7CR/ZV-E1. Also for ILCE-1M2 when using mechanical shutter.

Index1	Tag Name	Writable
10	ShutterCount	int32u
26	SonyExposureTime	int16u
28	SonyFNumber	int16u
31	ReleaseMode2	int8u
56	InternalSerialNumber	int8u[6]~

### Sony Tag9400a Tags

Valid for many DSC, NEX and SLT models

Index1	Tag Name	Writable
8	SequenceImageNumber	int32u
12	SequenceFileNumber	int32u
16	ReleaseMode2	int8u
18	DigitalZoom	int8u
26	ShotNumberSincePowerUp	int32u
34	SequenceLength	int8u
40	CameraOrientation	int8u
41	Quality2	int8u
68	SonyImageHeight	int16u~
82	ModelReleaseYear	int8u~

### Sony Tag9400b Tags

Valid for NEX-3N, ILCE-3000/3500, SLT-A58, DSC-WX60, DSC-WX300, DSC-RX100M2, DSC-HX50V, DSC-QX10/QX100.

Index1	Tag Name	Writable
8	SequenceImageNumber	int32u
12	SequenceFileNumber	int32u
16	ReleaseMode2	int8u
18	DigitalZoom	int8u
22	ShotNumberSincePowerUp	int32u
30	SequenceLength	int8u
36	CameraOrientation	int8u
37	Quality2	int8u

63 SonyImageHeight int16u~ 70 ModelReleaseYear int8u~

### Sony Tag9400c Tags

ILCE-1/7/7C/7R/7S/7M2/7M3/7RM2/7RM3/7RM4/7SM2/7SM3/9/9M2/5000/
5100/6000/6100/6300/6400/6500/6600/QX1, ILCA-68/77M2/99M2.

Index1	Tag Name	Writable
9	ReleaseMode2	int8u
10	ShotNumberSincePowerUp	int32u
18	SequenceImageNumber	int32u
22	SequenceLength	int8u
26	SequenceFileNumber	int32u
30	SequenceLength	int8u
41	CameraOrientation	int8u
42	Quality2	int8u
83	ModelReleaseYear	int8u~
307	ShutterType	int8u
313	ShutterType	int8u
319	ShutterType	int8u

### Sony Tag9401 Tags

Index1	Tag Name	Writable
994	ISOInfo	Sony ISOInfo
1012	ISOInfo	Sony ISOInfo
1102	ISOInfo	Sony ISOInfo
1176	ISOInfo	Sony ISOInfo
1181	ISOInfo	Sony ISOInfo
1182	ISOInfo	Sony ISOInfo
1185	ISOInfo	Sony ISOInfo
1186	ISOInfo	Sony ISOInfo
1210	ISOInfo	Sony ISOInfo
1437	ISOInfo	Sony ISOInfo
1588	ISOInfo	Sony ISOInfo
1590	ISOInfo	Sony ISOInfo
1612	ISOInfo	Sony ISOInfo
1619	ISOInfo	Sony ISOInfo
1656	ISOInfo	Sony ISOInfo
1720	ISOInfo	Sony ISOInfo
1758	ISOInfo	Sony ISOInfo
1767	ISOInfo	Sony ISOInfo

### Sony ISOInfo Tags

Index1	Tag Name	Writable
0	ISOSetting	int8u
2	ISOAutoMin	int8u
4	ISOAutoMax	int8u

### Sony Tag9402 Tags

Index1	Tag Name	Writable
4	AmbientTemperature	int8s
22	FocusMode	int8u & 0x7f
23	AFAreaMode	int8u
45	FocusPosition2	int8u

### Sony Tag9403 Tags

int8s

5 CameraTemperature

# Sony Tag9404a Tags

Index1	Tag Name	Writable
11	ExposureProgram	int8u
13	IntelligentAuto	int8u
25	LensZoomPosition	int16u

### Sony Tag9404b Tags

Index1	Tag Name	Writable
12	ExposureProgram	int8u
14	IntelligentAuto	int8u
30	LensZoomPosition	int16u
32	FocusPosition2	int8u

#### Sony Tag9404c Tags

Index1	Tag Name	Writable
11	ExposureProgram	int8u
13	IntelligentAuto	int8u

### Sony Tag9405a Tags

Valid for SLT, NEX, ILCE-3000/3500 and several DSC models.

Tag Name	Writable
DistortionCorrParamsPresent	int8u
DistortionCorrection	int8u
LensFormat	int8u
LensMount	int8u
LensType2	int16u
LensType	int16u
VignettingCorrParams	int16s[16]
ChromaticAberrationCorrParams	int16s[32]
DistortionCorrParams	int16s[16]
	DistortionCorrParamsPresent DistortionCorrection LensFormat LensMount LensType2 LensType VignettingCorrParams ChromaticAberrationCorrParams

## Sony Tag9405b Tags

Valid for DSC-HX60V/HX80/HX90V/HX99/HX350/HX400V/QX30/RX0/RX10/RX10M2/RX10M3/RX10M4/RX100M3/RX100M4/RX100M5/RX100M5A/RX100M6/RX100M7/WX220/WX350, ILCE-7/7M2/7M3/7R/7RM2/7RM3/7RM4/7S/7SM2/9/9M2/5000/5100/6000/6100/6300/6400/6500/6600/QX1, ILCA-68/77M2/99M2.

Index1	Tag Name	Writable
4	SonyISO	int16u
6	BaseISO	int16u
10	StopsAboveBaseISO	int16u
14	SonyExposureTime2	int16u
16	ExposureTime	rational32u
20	SonyFNumber	int16u
22	SonyMaxApertureValue	int16u
36	SequenceImageNumber	int32u
52	ReleaseMode2	int8u
62	SonyImageWidthMax	int16u
64	SonyImageHeightMax	int16u
66	HighISONoiseReduction	int8u
68	LongExposureNoiseReduction	int8u
70	PictureEffect2	int8u
72	ExposureProgram	int8u
74	CreativeStyle	int8u
82	Sharpness	int8s
90	DistortionCorrParamsPresent	int8u
91	DistortionCorrection	int8u

93	LensFormat	int8u
94	LensMount	int8u
96	LensType2	int16u
98	LensType	int16u
100	DistortionCorrParams	int16s[16]
834	LensZoomPosition	int16u
842	VignettingCorrParams	int16s[16]
846	LensZoomPosition	int16u
848	VignettingCorrParams	int16s[16]
858	LensZoomPosition	int16u
860	VignettingCorrParams	int16s[16]
872	VignettingCorrParams	int16s[16]
892	ChromaticAberrationCorrParams	int16s[32]
900	ChromaticAberrationCorrParams	int16s[32]
924	ChromaticAberrationCorrParams	int16s[32]
944	ChromaticAberrationCorrParams	int16s[32]
952	ChromaticAberrationCorrParams	int16s[32]

## Sony Tag9406 Tags

Index1	Tag Name	Writable
5	BatteryTemperature	int8u
6	BatteryLevelGrip1	int8u
7	BatteryLevel	int8u
8	BatteryLevelGrip2	int8u

## Sony Tag9406b Tags

Index1	Tag Name	Writable
5	BatteryLevel	int8u
7	BatteryLevel2	int8u

## Sony Tag940a Tags

These tags are currently extracted for SLT models only.

Index1	Tag Name	Writable
4	AFPointsSelected	int32u

## Sony Tag940c Tags

E-mount cameras only.

Index1	Tag Name	Writable
8	LensMount2	int8u
9	LensType3	int16u
11	CameraE-mountVersion	int16u
13	LensE-mountVersion	int16u
20	LensFirmwareVersion	int16u~

### Sony AFInfo Tags

These tags are currently extracted for SLT models only.

Index1	Tag Name	Writable
2	AFType	int8u
4	AFStatusActiveSensor	int16s
5	FocusMode	int8u
7	AFPoint	int8u
8	AFPointInFocus	int8u
9	AFPointAtShutterRelease	int8u
10	AFAreaMode	int8u
11	FocusMode	int8u
16	AFPointsUsed	int8u[10]
17	AFStatus15	Sony AFStatus15

	AFStatus19	Sony AFStatus19
55	AFPoint	int8u
56	AFPointInFocus	int8u
57	AFPointAtShutterRelease	int8u
58	AFAreaMode	int8u
59	AFStatusActiveSensor	int16s
67	ExposureProgram	int8u
80	AFMicroAdj	int8s
125	AFStatus79	Sony AFStatus79
366	AFPointsUsed	int32u
381	AFMicroAdj	int8s
382	ExposureProgram	int8u

### Sony AFStatus19 Tags

AF Status information for models with 19-point AF.

Index1	Tag Name	Writable
0	AFStatusUpperFarLeft	int16s
2	AFStatusUpper-leftHorizontal	int16s
4	AFStatusFarLeftHorizontal	int16s
6	AFStatusLeftHorizontal	int16s
8	AFStatusLowerFarLeft	int16s
10	AFStatusLower-leftHorizontal	int16s
12	AFStatusUpper-leftVertical	int16s
14	AFStatusLeftVertical	int16s
16	AFStatusLower-leftVertical	int16s
18	AFStatusFarLeftVertical	int16s
20	AFStatusTopHorizontal	int16s
22	AFStatusNearRight	int16s
24	AFStatusCenterHorizontal	int16s
26	AFStatusNearLeft	int16s
28	AFStatusBottomHorizontal	int16s
30	AFStatusTopVertical	int16s
32	AFStatusUpper-middle	int16s
34	AFStatusCenterVertical	int16s
36	AFStatusLower-middle	int16s
38	AFStatusBottomVertical	int16s
40	AFStatusUpperFarRight	int16s
42	AFStatusUpper-rightHorizontal	int16s
44	AFStatusFarRightHorizontal	int16s
46	AFStatusRightHorizontal	int16s
48	AFStatusLowerFarRight	int16s
50	AFStatusLower-rightHorizontal	int16s
52	AFStatusFarRightVertical	int16s
54	AFStatusUpper-rightVertical	int16s
56	AFStatusRightVertical	int16s
58	AFStatusLower-rightVertical	int16s

## Sony AFStatus79 Tags

AF Status information for models with 79-point AF.

Index1	Tag Name	Writable
0	AFStatus_00_B4	int16s
2	AFStatus_01_C4	int16s
4	AFStatus_02_D4	int16s
6	AFStatus_03_E4	int16s
8	AFStatus_04_F4	int16s
10	AFStatus_05_G4	int16s
12	AFStatus_06_H4	int16s
14	AFStatus_07_B3	int16s
16	AFStatus_08_C3	int16s
18	AFStatus_09_D3	int16s
20	AFStatus_10_E3	int16s
22	AFStatus_11_F3	int16s
24	AFStatus_12_G3	int16s
26	AFStatus_13_H3	int16s

	ExifTool 13.24 Tag Names	
28	AFStatus_14_B2	int16s
30	AFStatus_15_C2	int16s
32	AFStatus_16_D2	int16s
34	AFStatus_17_E2	int16s
36	AFStatus_18_F2	int16s
38	AFStatus_19_G2	int16s
40	AFStatus_20_H2	int16s
42	AFStatus_21_C1	int16s
44	AFStatus_22_D1	int16s
46	AFStatus 23 E1	int16s
48	AFStatus_24_F1	int16s
50	AFStatus 25 G1	int16s
52	AFStatus_26_A7_Vertical	int16s
54	AFStatus_27_A6_Vertical	int16s
56	AFStatus_28_A5_Vertical	int16s
58	AFStatus_29_C7_Vertical	int16s
60	AFStatus_30_C6_Vertical	int16s
62	AFStatus_31_C5_Vertical	int16s
64	AFStatus_32_E7_Vertical	int16s
66	AFStatus_33_E6_Center_Vertical	int16s
68	AFStatus_34_E5_Vertical	int16s
70	AFStatus_35_G7_Vertical	int16s
72	AFStatus_36_G6_Vertical	int16s
74	AFStatus_37_G5_Vertical	int16s
74 76	AFStatus_38_I7_Vertical	int16s
78	AFStatus_30_17_vertical AFStatus_39_16_Vertical	int16s
80	AFStatus_40_I5_Vertical	int16s
82	AFStatus_40_13_verticar AFStatus_41_A7	int16s
84	AFStatus_41_A7 AFStatus_42_B7	int16s
86	AFStatus_43_C7	int16s
88	AFStatus_44_D7	int16s
90	AFStatus_45_E7	int16s
92	AFStatus_45_E7 AFStatus_46_F7	int16s
94	AFStatus_40_F7 AFStatus_47_G7	int16s
96	AFStatus_48_H7	int16s
98	AFStatus_49_17	int16s
100	AFStatus_50_A6	int16s
102	AFStatus_51_B6	int16s
104	AFStatus_52_C6	int16s
104	AFStatus_53_D6	int16s
108	AFStatus_54_E6_Center	int16s
110	AFStatus_55_F6	int16s
112	AFStatus_56_G6	int16s
114	AFStatus_57_H6	int16s
116	AFStatus_58_I6	int16s
118	AFStatus_59_A5	int16s
120	AFStatus_60_B5	int16s
122	AFStatus_61_C5	int16s
124	AFStatus_62_D5	int16s
126	AFStatus_63_E5	int16s
128	AFStatus_64_F5	int16s
130	AFStatus_65_G5	int16s
132	AFStatus_66_H5	int16s
134	AFStatus_67_I5	int16s
136	AFStatus_68_C11	int16s
138	AFStatus_69_D11	int16s
140	AFStatus_70_E11	int16s
142	AFStatus_71_F11	int16s
144	AFStatus_72_G11	int16s
146	AFStatus_73_B10	int16s
148	AFStatus_73_B10 AFStatus_74_C10	int16s
150	AFStatus_74_C10 AFStatus_75_D10	int16s
152	AFStatus_75_D10 AFStatus_76_E10	int16s
154	AFStatus_70_E10 AFStatus_77_F10	int16s
154	AFStatus_77_F10 AFStatus_78_G10	int16s
158	AFStatus_70_G10 AFStatus_79_H10	int16s
160	AFStatus_/9_H10 AFStatus_80_B9	int16s
162	AFStatus_81_C9	int16s
164	AFStatus_61_C9 AFStatus_82_D9	int16s
166	AFStatus_83_E9	int16s
±00	III 500005_05_85	1110100

### -- ExifTool 13.24 Tag Names --

168	AFStatus_84_F9	int16s
170	AFStatus_85_G9	int16s
172	AFStatus_86_H9	int16s
174	AFStatus_87_B8	int16s
176	AFStatus_88_C8	int16s
178	AFStatus_89_D8	int16s
180	AFStatus_90_E8	int16s
182	AFStatus_91_F8	int16s
184	AFStatus_92_G8	int16s
186	AFStatus_93_H8	int16s
188	AFStatus_94_E6_Center_F2-8	int16s

### Sony Tag940e Tags

E-mount models.

Index1	Tag Name	Writable
6662	TiffMeteringImageWidth	no
6663	TiffMeteringImageHeight	no
6664	TiffMeteringImage	no

### Sony Tag9416 Tags

Valid for the ILCE-1/6700/7CM2/7CR/7M4/7RM5/7SM3/9M3, ILME-FX3/FX30, ZV-E1/E10M2.

Index1	Tag Name	Writable
0	Tag9416_0000	no
4	SonyISO	no
6	StopsAboveBaseISO	no
10	SonyExposureTime2	no
12	ExposureTime	no
16	SonyFNumber2	no
18	SonyMaxApertureValue	no
29	SequenceImageNumber	no
43	ReleaseMode2	no
53	ExposureProgram	no
55	CreativeStyle	no
72	LensMount	no
73	LensFormat	no
74	LensMount	no
75	LensType2	no
77	LensType	no
79	DistortionCorrParams	no
112	PictureProfile	no
113	FocalLength	no
115	MinFocalLength	no
117	MaxFocalLength	no
2191	VignettingCorrParams	no
2193	VignettingCorrParams	no
2205	VignettingCorrParams	no
2229	APS-CSizeCapture	no
2231	APS-CSizeCapture	no
2277	APS-CSizeCapture	no
2324	ChromaticAberrationCorrParams	no
2326	ChromaticAberrationCorrParams	no
2373	ChromaticAberrationCorrParams	no

### Sony PIC Tags

The TextInfo data is extracted as a block to preserve the formatting, and some of the more interesting information is extracted as separate tags.

Tag ID	Tag Name	Writable
'BC:'	Barcode	no
'BarCode:'	Barcode	no

'Capt:'	SensorTemperature	no
'FWVer:'	FirmwareVersion	no
'IFD'	PIC_IFD	Sony
'Temp:'	CameraTemperature	no
'Temp:Clbt:'	BoardTemperature	no
'TextInfo1'	TextInfo1	no
'TextInfo2'	TextInfo2	no
'VR Enable C:'	VibrationReduction	no
'barcode:'	Barcode	no

#### Sony Ericsson Tags

Maker notes found in images from some Sony Ericsson phones.

Tag ID	Tag Name	Writable
0x0201	PreviewImageStart	int32u*
0x0202	PreviewImageLength	int32u*
0x2000	MakerNoteVersion	undef[4]

#### Sony SRF Tags

The maker notes in SRF (Sony Raw Format) images contain 7 IFD's with family 1 group names SRF0 through SRF6. SRF0 and SRF1 use the tags in this table, while SRF2 through SRF5 use the tags in the next table, and SRF6 uses standard EXIF tags. All information other than SRF0 is encrypted, but thanks to Dave Coffin the decryption algorithm is known. SRF images are written by the Sony DSC-F828 and DSC-V3.

Tag ID	Tag Name	Writable
0x0000	SRF2Key	no
$0 \times 0001$	DataKev	no

### Sony SR2Private Tags

The SR2 format uses the DNGPrivateData tag to reference a private IFD containing these tags. SR2 images are written by the Sony DSC-R1, but this information is also written to ARW images by other models.

Tag ID	Tag Name	Writable
0x7200	SR2SubIFDOffset	no
0x7201	SR2SubIFDLength	no
0x7221	SR2SubIFDKey	no
0x7240	IDC_IFD	SonyIDC
0x7241	IDC2_IFD	SonyIDC
0x7250	MRWInfo	MinoltaRaw

### Sony SRF2 Tags

These tags are found in the SRF2 through SRF5 IFD's.

Tag ID	Tag Name	Writable
$0 \times 0002$	SRF6Offset	no
$0 \times 0003$	SRFDataOffset?	no
$0 \times 0004$	RawDataOffset	no
$0 \times 0005$	RawDataLength	no
$0 \times 0043$	MaxApertureAtMaxFocal	no
$0 \times 0044$	MaxApertureAtMinFocal	no
$0 \times 0045$	MinFocalLength	no
$0 \times 0046$	MaxFocalLength	no
0x00c0	WBRedDaylight	no
0x00c1	WBGreenDaylight	no
0x00c2	WBBlueDaylight	no
0x00c3	WBRedCloudy	no
0x00c4	WBGreenCloudy	no
0x00c5	WBBlueCloudy	no
0x00c6	WBRedFluorescent	no

0x00c7	WBGreenFluorescent	no
0x00c8	WBBlueFluorescent	no
0x00c9	WBRedTungsten	no
0x00ca	WBGreenTungsten	no
0x00cb	WBBlueTungsten	no
0x00cc	WBRedFlash	no
0x00cd	WBGreenFlash	no
0x00ce	WBBlueFlash	no
0x00d0	WBRedAsShot	no
0x00d1	WBGreenAsShot	no
$0 \times 00 d2$	WBBlueAsShot	no

### Sony SR2SubIFD Tags

## Tags in the encrypted SR2SubIFD

Tag ID	Tag Name	Writable
0x7300	BlackLevel	int16u[4]!
0x7302	WB_GRBGLevelsAuto	int16s[4]!
0x7303	WB_GRBGLevels	int16s[4]!
$0 \times 7310$	BlackLevel	int16u[4]!
0x7312	WB_RGGBLevelsAuto	int16s[4]!
$0 \times 7313$	WB_RGGBLevels	int16s[4]!
$0 \times 7480$	WB_RGBLevelsDaylight	int16s[4]!
0x7481	WB_RGBLevelsCloudy	int16s[4]!
0x7482	WB_RGBLevelsTungsten	int16s[4]!
0x7483	WB_RGBLevelsFlash	int16s[4]!
0x7484	WB_RGBLevels4500K	int16s[4]!
0x7486	WB_RGBLevelsFluorescent	int16s[4]!
0x74a0	MaxApertureAtMaxFocal	no
0x74a1	MaxApertureAtMinFocal	no
0x74a2	MaxFocalLength	no
0x74a3	MinFocalLength	no
0x74c0	SR2DataIFD	Sony SR2DataIFD
0x7800	ColorMatrix	no
0x7820	WB_RGBLevelsDaylight	int16s[3]!
0x7821	WB_RGBLevelsCloudy	int16s[3]!
0x7822	WB_RGBLevelsTungsten	int16s[3]!
0x7823	WB_RGBLevelsFlash	int16s[3]!
0x7824	WB_RGBLevels4500K	int16s[3]!
0x7825	WB_RGBLevelsShade	int16s[3]!
0x7826	WB_RGBLevelsFluorescent	int16s[3]!
0x7827	WB_RGBLevelsFluorescentP1	int16s[3]!
0x7828	WB_RGBLevelsFluorescentP2	int16s[3]!
0x7829	WB_RGBLevelsFluorescentM1	int16s[3]!
0x782a	WB_RGBLevels8500K	int16s[3]!
0x782b	WB_RGBLevels6000K	int16s[3]!
0x782c	WB_RGBLevels3200K	int16s[3]!
0x782d	WB_RGBLevels2500K	int16s[3]!
0x787f	WhiteLevel	int16u[3]!
0x797d	VignettingCorrParams	no
0x7980	ChromaticAberrationCorrParams	no
0x7982	DistortionCorrParams	no

## Sony SR2DataIFD Tags

Tag ID	Tag Name	Writable
0x7770	ColorMode	no

### Sony PMP Tags

These tags are written in the proprietary-format header of PMP images from the DSC-F1.

Index1	Tag Name	Writable
8	JpgFromRawStart	no
12	${ t JpgFromRawLength}$	no

22	SonyImageWidth	no
24	SonyImageHeight	no
27	Orientation	no
29	ImageQuality	no
52	Comment	no
76	DateTimeOriginal	no
84	ModifyDate	no
102	ExposureTime	no
106	FNumber	no
108	ExposureCompensation	no
112	FocalLength	no
118	Flash	no

### Sony rtmd Tags

These tags are extracted from the 'rtmd' timed metadata of MP4 videos from some models when the ExtractEmbedded option is used.

Tag ID	Tag Name	Writable
0x8000	FNumber	no
0x8109	ExposureTime	no
0x810a	MasterGainAdjustment	no
0x810b	ISO	no
0x810c	${\tt ElectricalExtenderMagnification}$	no
0x8500	GPSVersionID	no
0x8501	GPSLatitudeRef	no
0x8502	GPSLatitude	no
0x8503	GPSLongitudeRef	no
0x8504	GPSLongitude	no
0x8507	GPSTimeStamp	no
0x8509	GPSStatus	no
0x850a	GPSMeasureMode	no
0x8512	GPSMapDatum	no
0x851d	GPSDateStamp	no
0xe303	WhiteBalance	no
0xe304	DateTime	no
0xe43b	PitchRollYaw	no
0xe44b	Accelerometer	no

### SonyIDC Tags

Tags written by the Sony Image Data Converter utility in ARW images.

Tag ID	Tag Name	Writable
0x0201	IDCPreviewStart	int32u*
0x0202	IDCPreviewLength	int32u*
0x8000	IDCCreativeStyle	int32u
0x8001	CreativeStyleWasChanged	int32u
0x8002	PresetWhiteBalance	int32u
0x8013	ColorTemperatureAdj	int16u
0x8014	PresetWhiteBalanceAdj	int32s
0x8015	ColorCorrection	int32s
0x8016	SaturationAdj	int32s
0x8017	ContrastAdj	int32s
0x8018	BrightnessAdj	int32s
0x8019	HueAdj	int32s
0x801a	SharpnessAdj	int32s
0x801b	SharpnessOvershoot	int32s
0x801c	SharpnessUndershoot	int32s
0x801d	SharpnessThreshold	int32s
0x801e	NoiseReductionMode	int16u
0x8021	GrayPoint	int16u[4]
0x8022	D-RangeOptimizerMode	int16u
0x8023	D-RangeOptimizerValue	int32s
0x8024	D-RangeOptimizerHighlight	int32s
0x8026	HighlightColorDistortReduct	int16u
0x8027	NoiseReductionValue	int32s
0x8028	EdgeNoiseReduction	int32s
0x8029	ColorNoiseReduction	int32s

0x802d	D-RangeOptimizerShadow	int32s
0x8030	PeripheralIllumCentralRadius	int32s
0x8031	PeripheralIllumCentralValue	int32s
0x8032	PeripheralIllumPeriphValue	int32s
0x8040	DistortionCompensation	int32s
0x9000	ToneCurveBrightnessX	int16u[n]
0x9001	ToneCurveRedX	int16u[n]
0x9002	ToneCurveGreenX	int16u[n]
0x9003	ToneCurveBlueX	int16u[n]
0x9004	ToneCurveBrightnessY	int16u[n]
0x9005	ToneCurveRedY	int16u[n]
0x9006	ToneCurveGreenY	int16u[n]
0x9007	ToneCurveBlueY	int16u[n]
0x900d	ChromaticAberrationCorrection	int32s
0x900e	InclinationCorrection	int32u
0x900f	InclinationAngle	int32s
0x9010	Cropping	int32u
0x9011	CropArea	int32u[4]
$0 \times 9012$	PreviewImageSize	int32u[2]
0x9013	PxShiftPeriphEdgeNR	int32s
$0 \times 9014$	PxShiftPeriphEdgeNRValue	int32s
$0 \times 9017$	WhitesAdj	int32s
0x9018	BlacksAdj	int32s
0x9019	HighlightsAdj	int32s
0x901a	ShadowsAdj	int32s
0xd000	CurrentVersion	int32u
0xd001	VersionIFD	SonyIDC
0xd100	VersionCreateDate	string
0xd101	VersionModifyDate	string

#### Unknown Tags

The following tags are decoded in unsupported maker notes. Use the Unknown (-u) option to display other unknown tags.

Tag ID	Tag Name	Writable
0x0e00	PrintIM	PrintIM

#### DNG Tags

The main DNG tags are found in the EXIF table. The tables below define only information found within structures of these main DNG tag values. See <a href="https://helpx.adobe.com/camera-raw/digital-negative.html">https://helpx.adobe.com/camera-raw/digital-negative.html</a> for the official DNG specification.

#### DNG AdobeData Tags

This information is found in the "Adobe" DNGPrivateData.

The maker notes ('MakN') are processed by ExifTool, but some information may have been lost by the Adobe DNG Converter. This is because the Adobe DNG Converter (as of version 6.3) doesn't properly handle information referenced from inside the maker notes that lies outside the original maker notes block. This information is lost when only the maker note block is copied to the DNG image. While this doesn't effect all makes of cameras, it is a problem for some major brands such as Olympus and Sony.

Other entries in this table represent proprietary information that is extracted from the original RAW image and restructured to a different (but still proprietary) Adobe format.

Tag ID	Tag Name	Writable
'CRW '	AdobeCRW	CanonRaw
'Koda'	AdobeKoda	Kodak IFD
'Leaf'	AdobeLeaf	Leaf SubIFD
'MRW '	AdobeMRW	MinoltaRaw
'MakN'	MakerNoteApple	Apple
	MakerNoteNikon	Nikon
	MakerNoteCanon	Canon

MakerNoteCasio Casio MakerNoteCasio2 Casio Type2 MakerNoteDJIInfo DJI Info MakerNoteDJI DJI MakerNoteFLIR FLIR MakerNoteFujiFilm FujiFilm MakerNoteGE FujiFilm MakerNoteGE2 MakerNoteHasselblad Unknown

MakerNoteHP ΗP HP Type2 MakerNoteHP2 HP Type4 MakerNoteHP4 нр Туреб MakerNoteHP6 MakerNoteISL Unknown MakerNoteJVC JVC MakerNoteJVCText JVC Text MakerNoteKodak1a Kodak MakerNoteKodak1b Kodak

Kodak Type2 MakerNoteKodak2 Kodak Type3 MakerNoteKodak3 MakerNoteKodak4 Kodak Type4 MakerNoteKodak5 Kodak Type5 Kodak Type6 MakerNoteKodak6a Kodak Type6 MakerNoteKodak6b MakerNoteKodak7 Kodak Type7 Kodak Type8 MakerNoteKodak8a Kodak Type8 MakerNoteKodak8b Kodak Type8 MakerNoteKodak8c MakerNoteKodak9 Kodak Type9 Kodak Type10 MakerNoteKodak10 Kodak Type11 MakerNoteKodak11 MakerNoteKodak12 Kodak Type11 MakerNoteKodakUnknown Kodak Unknown

MakerNoteKyocera Unknown MakerNoteMinolta Minolta MakerNoteMinolta2 Olympus MakerNoteMinolta3 undef MakerNoteMotorola Motorola MakerNoteNikon2 Nikon Type2 MakerNoteNikon3 Nikon MakerNoteNintendo Nintendo MakerNoteOlympus Olympus MakerNoteOlympus2 Olympus MakerNoteOlympus3 Olympus MakerNoteLeica Panasonic

MakerNoteLeica
MakerNoteLeica2
MakerNoteLeica3
MakerNoteLeica4
MakerNoteLeica5
MakerNoteLeica5
MakerNoteLeica6
MakerNoteLeica7
MakerNoteLeica7
MakerNoteLeica8
MakerNoteLeica8
MakerNoteLeica9
Panasonic Leica6
Panasonic Leica6
Panasonic Leica6
Panasonic Leica6
Panasonic Leica6

MakerNoteLeica9

MakerNoteLeica10

MakerNotePanasonic

MakerNotePanasonic2

MakerNotePanasonic3

MakerNotePanasonic3

MakerNotePentax

Panasonic

Panasonic

Type2

Panasonic

Panasonic

Panasonic

MakerNotePentax2

MakerNotePentax3

MakerNotePentax3

MakerNotePentax4

MakerNotePentax5

MakerNotePentax5

MakerNotePentax6

MakerNotePentax6

MakerNotePhaseOne

MakerNoteReconyx

MakerNoteReconyx

MakerNoteReconyx

MakerNoteReconyx2 Reconyx Type2
MakerNoteReconyx3 Reconyx Type3
MakerNoteRicohPentax Pentax

MakerNoteRicoh
MakerNoteRicoh
Ricoh
MakerNoteRicoh
MakerNoteRicoh
Ricoh Type2

#### -- ExifTool 13.24 Tag Names --

MakerNoteRicohText Ricoh Text MakerNoteSamsung1a undef MakerNoteSamsung1b Samsung MakerNoteSamsung2 Samsung Type2 MakerNoteSanyo Sanyo MakerNoteSanyoC4 Sanyo MakerNoteSanyoPatch Sanyo MakerNoteSigma Sigma MakerNoteSony Sony MakerNoteSony2 Olympus MakerNoteSony3 Olympus MakerNoteSony4 Sony PIC MakerNoteSony5 Sony MakerNoteSonyEricsson Sony Ericsson MakerNoteSonySRF Sony SRF MakerNoteUnknownText undef MakerNoteUnknownBinary undef MakerNoteUnknown Unknown Pano' AdobePano'RAF' Adobe PanasonicRaw FujiFilm RAF 'SR2 ' AdobeSR2 Sony SR2Private

#### DNG OriginalRaw Tags

This table defines tags extracted from the DNG OriginalRawFileData information.

Tag ID	Tag Name	Writable
0x0000	OriginalRawImage	no
$0 \times 0001$	OriginalRawResource	no
$0 \times 0002$	OriginalRawFileType	no
0x0003	OriginalRawCreator	no
$0 \times 0004$	OriginalTHMImage	no
$0 \times 0005$	OriginalTHMResource	no
0x0006	OriginalTHMFileType	no
$0 \times 0007$	OriginalTHMCreator	no

#### DNG ImageSeq Tags

Index1	Tag Name	Writable
0	SeqID	no
1	SeqType	no
2	SeqFrameInfo	no
3	SeqIndex	no
7	SeqCount	no
11	SegFinal	no

### DNG ProfileDynamicRange Tags

Index1	Tag Name	Writable
0	PDRVersion	no
2	DynamicRange	no
4	HintMaxOutputValue	no

### JSON Tags

Other than a few tags in the table below, JSON tags have not been predefined. However, ExifTool will read any existing tags from basic JSON-formatted files.

Tag Name	Writable
AdjustmentsSettingsStatisticsLightMap ON1_SettingsData	no PLIST
ON1_SettingsMetadataCreated	no
ON1_SettingsMetadataModified	no
ON1_SettingsMetadataName	no
ON1_SettingsMetadataPluginID	no

ON1_SettingsMetadataTimestamp	no
ON1_SettingsMetadataUsage	no
ON1 SettingsMetadataVisibleToUser	no

#### CBOR Tags

The tags below are extracted from CBOR (Concise Binary Object Representation) metadata. The C2PA specification uses this format for some metadata. As well as these tags, ExifTool will read any existing tags.

Tag Name	Writable
AuthorIdentifier	no
AuthorName	no
DocumentID	no
Format	no
InstanceID	no
Relationship	no
ThumbnailHash	no+
ThumbnailURL	no
Title	no

#### PLIST Tags

Apple Property List tags. ExifTool reads both XML and binary-format PLIST files, and will extract any existing tags even if they aren't listed below. These tags belong to the family 0 "PLIST" group, but family 1 group may be either "XML" or "PLIST" depending on whether the format is XML or binary.

Tag ID	Tag Name	Writable
'MetaData	List//DateTimeOriginal'	
	DateTimeOriginal	no
'MetaData	List//Duration' Duration	no
'MetaData	List//Geolocation/Latitude'	
	GPSLatitude	no
'MetaData	List//Geolocation/Longitude'	
	GPSLongitude	no
'MetaData	List//Geolocation/MapDatum'	
	GPSMapDatum	no
'XMLFileT	ype' XMLFileType	no
	ntData' AdjustmentData	PLIST
'cast//na		no+
	ors//name' Codirectors	no+
	s//name' Directors	no+
	s//name' Producers	no+
	iters//name' Screenwriters	no+
	on/rate' SlowMotionRate	no
	on/regions' SlowMotionRegions	no
'slowMoti	on/regions/timeRange/duration/epoch'	
	SlowMotionRegionsDurationEpoch	no
'slowMoti	on/regions/timeRange/duration/flags'	
	SlowMotionRegionsDurationFlags	no
'slowMotı	on/regions/timeRange/duration/timesc	
	SlowMotionRegionsDurationTimeScale	no
'slowMot1	on/regions/timeRange/duration/value'	
1 - 3	SlowMotionRegionsDurationValue	no
SIOWMOTI	on/regions/timeRange/start/epoch'	
1 - 7	SlowMotionRegionsStartTimeEpoch	no
SIOWMOTI	on/regions/timeRange/start/flags'	
1 ~ 1 ~ 1/4 ~ + - 1	SlowMotionRegionsStartTimeFlags	no
SIOWMOLI	on/regions/timeRange/start/timescale	
LalowMa+ i	SlowMotionRegionsStartTimeScale	no
SIOMMOLI	on/regions/timeRange/start/value'	20
Latudia//	SlowMotionRegionsStartTimeValue name' Studio	no
SLUGIO//	maille scuulu	no+

#### CanonRaw Tags

These tags apply to CRW-format Canon RAW files and information in the APPO "CIFF" segment of JPEG images. When writing CanonRaw/CIFF

information, the length of the information is preserved (and the new information is truncated or padded as required) unless Writable is "resize". Currently, only JpgFromRaw and ThumbnailImage are allowed to change size. See <a href="https://exiftool.org/canon\_raw.html">https://exiftool.org/canon\_raw.html</a> for a description of the Canon CRW format.

CRW images also support the addition of a CanonVRD trailer, which in turn supports XMP. This trailer is created automatically if necessary when ExifTool is used to write XMP to a CRW image.

Tag ID	Tag Name	Writable
00000	NullRecord	
$0 \times 00000$ $0 \times 0001$	FreeBytes	undef undef
0x0001	CanonColorInfol	no
0x0032 $0x0805$	CanonFileDescription	string[32]
0X0003	UserComment	string[32] string[256]
0x080a	CanonRawMakeModel	CanonRaw MakeModel
0x080b	CanonFirmwareVersion	string[32]
0x080c	ComponentVersion	string
0x080d	ROMOperationMode	string[8]
0x0810	OwnerName	string[32]
0x0815	CanonImageType	string[32]
0x0816	OriginalFileName	string[32]
0x0817	ThumbnailFileName	string[32]
0x100a	TargetImageType	int16u
0x1010	ShutterReleaseMethod	int16u
0x1011	ShutterReleaseTiming	int16u
0x1016	ReleaseSetting	int16u
0x101c	BaseISO	int16u
0x1028	CanonFlashInfo?	int16u[4]
0x1029	CanonFocalLength	Canon FocalLength
0x102a	CanonShotInfo	Canon ShotInfo
0x102c	CanonColorInfo2	no
0x102d	CanonCameraSettings	Canon CameraSettings
0x1030	WhiteSample	CanonRaw WhiteSample
0x1031	SensorInfo	Canon SensorInfo
0x1033	CustomFunctions10D	CanonCustom Functions10D
	CustomFunctionsD30	CanonCustom FunctionsD30
	CustomFunctionsD60	CanonCustom FunctionsD30
	CustomFunctionsUnknown	CanonCustom FuncsUnknown
0x1038	CanonAFInfo	Canon AFInfo
0x1093	CanonFileInfo	Canon FileInfo
0x10a9	ColorBalance	Canon ColorBalance
0x10ae	ColorTemperature	int16u
0x10b4	ColorSpace	int16u
0x10b5	RawJpgInfo	CanonRaw RawJpgInfo
0x1803	ImageFormat	CanonRaw ImageFormat
0x1804	RecordID	int32u
0x1806	SelfTimerTime	int32u
0x1807	TargetDistanceSetting	float
0x180b	SerialNumber	int32u
	UnknownNumber?	yes
0x180e	TimeStamp	CanonRaw TimeStamp
0x1810	ImageInfo	CanonRaw ImageInfo
0x1813	FlashInfo	CanonRaw FlashInfo
0x1814	MeasuredEV	float
0x1817	FileNumber	int32u
0x1818	ExposureInfo	CanonRaw ExposureInfo
0x1834	CanonModelID	int32u
0x1835	DecoderTable	CanonRaw DecoderTable
0x183b	SerialNumberFormat	int32u
	RawData	no
0x2005		700 g i 70 A
0x2007	JpgFromRaw	resize^
0x2007 0x2008	JpgFromRaw ThumbnailImage	resize^
0x2007 0x2008 0x2804	JpgFromRaw ThumbnailImage ImageDescription	resize^ CanonRaw
0x2007 0x2008 0x2804 0x2807	JpgFromRaw ThumbnailImage ImageDescription CameraObject	resize^ CanonRaw CanonRaw
0x2007 0x2008 0x2804 0x2807 0x3002	JpgFromRaw ThumbnailImage ImageDescription CameraObject ShootingRecord	resize^ CanonRaw CanonRaw CanonRaw
0x2007 0x2008 0x2804 0x2807	JpgFromRaw ThumbnailImage ImageDescription CameraObject	resize^ CanonRaw CanonRaw

	ExifTool 13.24 Tag	Names	
0x300a 0x300b			CanonRaw CanonRaw
CanonRaw	<u>MakeModel</u> <u>Tags</u>		
Index1	Tag Name		Writable
0 6	Make Model		string[6] string
CanonRaw	WhiteSample Tags		
Index2	3		Writable
1	WhiteSampleWidth		no
2	WhiteSampleHeight		no
3 4	WhiteSampleLeftBorder		no
<del>4</del> 5	WhiteSampleTopBorder WhiteSampleBits		no no
			110
	RawJpgInfo Tags		1
Index2			Writable
1	RawJpgQuality		int16u
2	RawJpgSize RawJpgWidth		int16u int16u
4	RawJpgHeight		int16u
<u>CanonRaw</u>	ImageFormat Tags		
Index4	Tag Name		Writable
0			 int32u
1	TargetCompressionRatio		float
	-		11040
	<u>TimeStamp</u> <u>Tags</u>		
Index4	Tag Name		Writable
0	DateTimeOriginal		int32u
1	TimeZoneCode		int32s
2	TimeZoneInfo		int32u
CanonRaw	<u>ImageInfo</u> <u>Tags</u>		
Index4	Tag Name		Writable
0	ImageWidth		no
1	ImageHeight		no
2	PixelAspectRatio		no
3	Rotation		int32s
4 5	ComponentBitDepth ColorBitDepth		no
6	ColorBW		no no
<u>CanonRaw</u>	FlashInfo Tags		
Index4	Tag Name		Writable
0	FlashGuideNumber		float
1	FlashThreshold		float
<u>CanonRaw</u>	ExposureInfo Tags		
Index4	Tag Name		Writable
			writable
0	ExposureCompensation		float
1	ShutterSpeedValue		float
2	ApertureValue		float

## <u>CanonRaw</u> <u>DecoderTable</u> <u>Tags</u>

Index4	Tag Name	Writable
0	DecoderTableNumber	no
2	CompressedDataOffset	no
3	CompressedDataLength	no

### KyoceraRaw Tags

Tags for Kyocera Contax N Digital RAW images.

Index1	Tag Name	Writable
1	FirmwareVersion	no
12	Model	no
25	Make	no
33	DateTimeOriginal	no
52	ISO	no
56	ExposureTime	no
60	WB_RGGBLevels	no
88	FNumber	no
104	MaxAperture	no
112	FocalLength	no
124	Lens	no

## MinoltaRaw Tags

These tags are used in Minolta RAW format (MRW) images.

Tag ID	Tag Name	Writable	
"\0PRD"	MinoltaPRD	MinoltaRaw	PRD
"\ORIF"	MinoltaRIF	MinoltaRaw	RIF
"\OTTW"	MinoltaTTW	EXIF	
"\0WBG"	MinoltaWBG	MinoltaRaw	WBG

### MinoltaRaw PRD Tags

Index1	Tag Name	Writable
0	FirmwareID	string[8]
8	SensorHeight	int16u
10	SensorWidth	int16u
12	ImageHeight	int16u
14	ImageWidth	int16u
16	RawDepth	int8u
17	BitDepth	int8u
18	StorageMethod	int8u
23	BayerPattern	int8u

### MinoltaRaw RIF Tags

Index1	Tag Name	Writable
1	Saturation	int8s
2	Contrast	int8s
3	Sharpness	int8s
4	WBMode	int8u~
5	ProgramMode	int8u
6	ISOSetting	int8u
7	ColorMode	int8u
8	WB_RBLevelsTungsten	int16u[2]
12	WB_RBLevelsDaylight	int16u[2]
16	WB_RBLevelsCloudy	int16u[2]
20	WB_RBLevelsCoolWhiteF	int16u[2]
24	WB_RBLevelsFlash	int16u[2]
28	WB_RBLevelsCustom	int16u[2]
32	WB_RBLevelsShade	int16u[2]
36	WB_RBLevelsDaylightF	int16u[2]
40	WB_RBLevelsDayWhiteF	int16u[2]

44	WB_RBLevelsWhiteF	int16u[2]
56	ColorFilter	int8s
57	BWFilter	int8u
58	ZoneMatching	int8u
59	Hue	int8s
60	ColorTemperature	int8u
74	ZoneMatching	int8u
76	ColorTemperature	int8u
77	ColorFilter	int8u
78	ColorTemperature	int8u
79	ColorFilter	int8u
80	RawDataLength	no

## MinoltaRaw WBG Tags

Index1	Tag Name	Writable
0	WBScale	int8u[4]
4	WB_GBRGLevels	int16u[4]
	WB_RGGBLevels	int16u[4]

### PanasonicRaw Tags

These tags are found in IFDO of Panasonic/Leica RAW, RW2 and RWL images.

Tag ID	Tag Name	Writable
0x0001	PanasonicRawVersion	undef
0x0001	SensorWidth	no
0x0003	SensorHeight	no
$0 \times 0004$	SensorTopBorder	no
0x0005	SensorLeftBorder	no
0x0006	SensorBottomBorder	no
0x0007	SensorRightBorder	no
0x0008	SamplesPerPixel	int16u!
$0 \times 0009$	CFAPattern	int16u!
0x000a	BitsPerSample	int16u!
0x000b	Compression	int16u!
0x000e	LinearityLimitRed	int16u
0x000f	LinearityLimitGreen	int16u
0x0010	LinearityLimitBlue	int16u
0x0011	RedBalance	int16u
$0 \times 0012$	BlueBalance	int16u
$0 \times 0013$	WBInfo	PanasonicRaw WBInfo
$0 \times 0017$	ISO	int16u
$0 \times 0018$	HighISOMultiplierRed	int16u
$0 \times 0019$	HighISOMultiplierGreen	int16u
0x001a	HighISOMultiplierBlue	int16u
0x001b	NoiseReductionParams	undef[n]!
0x001c	BlackLevelRed	int16u
0x001d	BlackLevelGreen	int16u
0x001e	BlackLevelBlue	int16u
$0 \times 0024$	WBRedLevel	int16u
$0 \times 0025$	WBGreenLevel	int16u
$0 \times 0026$	WBBlueLevel	int16u
0x0027	WBInfo2	PanasonicRaw WBInfo2
0x002d	RawFormat	int16u!
0x002e	JpgFromRaw	JPEG
0x002f	CropTop	int16u
$0 \times 0030$	CropLeft	int16u
0x0031	CropBottom	int16u
0x0032	CropRight	int16u
$0 \times 0037$	ISO	int32u
0x010f	Make	string
0x0110	Model	string
0x0111	StripOffsets	no
$0 \times 0112$	Orientation	int16u
0x0116	RowsPerStrip	no
$0 \times 0117$	StripByteCounts RawDataOffset	no
0x0118	KawDataUIISet	no

$0 \times 0119$	DistortionInfo	PanasonicRaw DistortionInfo
0x011c	Gamma	int16u
0x0120	CameraIFD	PanasonicRaw CameraIFD
0x0121	Multishot	int32u
0x0127	JpgFromRaw2	no
0x013b	Artist	string
0x02bc	ApplicationNotes	XMP
0x8298	Copyright	string
0x83bb	IPTC-NAA	IPTC
0x8769	ExifOffset	EXIF
0x8825	GPSInfo	GPS

## PanasonicRaw CameraIFD Tags

Tag ID	Tag Name	Writable
0x1001	 MultishotOn	no
$0 \times 11001$		no
0x1100 $0x1101$	FocusStepCount	no
0x1101 0x1102		
		no
		no
0x1200		no
0x1201	20110 1 / F 01 10110	no
0x1202	LensTypeModel	no
0x1203	FocalLengthIn35mmFormat	no
0x1301	ApertureValue	no
0x1302	ShutterSpeedValue	no
0x1303	SensitivityValue	no
0x1305	HighISOMode	no
0x1412	FacesDetected	no
0x3200	WB_CFA0_LevelDaylight	no
0x3201	WB_CFA1_LevelDaylight	no
0x3202	WB_CFA2_LevelDaylight	no
0x3203	WB_CFA3_LevelDaylight	no
0x3300	WhiteBalanceSet	no
0x3420	WB_RedLevelAuto	no
0x3421	WB_BlueLevelAuto	no
0x3501	Orientation	no
0x3600	WhiteBalanceDetected	no

## PanasonicRaw WBInfo Tags

Index2	Tag Name	Writable
0	NumWBEntries	int16u
1	WBType1	int16u
2	WB_RBLevels1	int16u[2]
4	WBType2	int16u
5	WB_RBLevels2	int16u[2]
7	WBType3	int16u
8	WB_RBLevels3	int16u[2]
10	WBType4	int16u
11	WB_RBLevels4	int16u[2]
13	WBType5	int16u
14	WB_RBLevels5	int16u[2]
16	WBType6	int16u
17	WB_RBLevels6	int16u[2]
19	WBType7	int16u
20	WB_RBLevels7	int16u[2]

## PanasonicRaw WBInfo2 Tags

Index2	Tag Name	Writable
0	NumWBEntries	int16u
1	WBType1	int16u
2	WB_RGBLevels1	int16u[3]
5	WBType2	int16u
6	WB_RGBLevels2	int16u[3]
9	WBType3	int16u

10	WB_RGBLevels3	int16u[3]
13	WBType4	int16u
14	WB_RGBLevels4	int16u[3]
17	WBType5	int16u
18	WB_RGBLevels5	int16u[3]
21	WВТуреб	int16u
22	WB_RGBLevels6	int16u[3]
25	WBType7	int16u
26	WB_RGBLevels7	int16u[3]

### PanasonicRaw DistortionInfo Tags

Lens distortion correction information.

Tag ID	Tag Name	Writable
$0 \times 0002$	DistortionParam02	int16s
$0 \times 0004$	DistortionParam04	int16s
$0 \times 0005$	DistortionScale	int16s
7.1	DistortionCorrection	int16s & 0x0f
0x0008	DistortionParam08	int16s
$0 \times 0009$	DistortionParam09	int16s
0x000b	DistortionParam11	int16s
0x000c	DistortionN?	int16s

### SigmaRaw Tags

These tags are used in Sigma and Foveon RAW (.X3F) images. Metadata is also extracted from the JpgFromRaw image if it exists (all models but the SD9 and SD10). Currently, metadata may only be written to the embedded JpgFromRaw.

Tag ID	Tag Name	Writable
'Header'	Header	SigmaRaw Header
'Header4'	Header4	SigmaRaw Header4
'HeaderExt'	HeaderExt	SigmaRaw HeaderExt
'IMA2'	PreviewImage	no
	JpgFromRaw	no
'IMAG'	PreviewImage	no
'PROP'	Properties	SigmaRaw Properties

### SigmaRaw Header Tags

Information extracted from the header of an X3F file.

Tag ID	Tag Name	Writable
$0 \times 0001$	FileVersion	no
$0 \times 0002$	ImageUniqueID	no
$0 \times 0006$	MarkBits	no
$0 \times 0007$	ImageWidth	no
0x0008	ImageHeight	no
$0 \times 0009$	Rotation	no
0x000a	WhiteBalance	no
$0 \times 0012$	SceneCaptureType	no

#### SigmaRaw Header4 Tags

Header information for version 4.0 or greater X3F.

Index4	Tag Name	Writable
1	FileVersion	no
10	ImageWidth	no
11	ImageHeight	no
12	Rotation	no

### SigmaRaw HeaderExt Tags

Extended header data found in version 2.1 and 2.2 files

Tag ID	Tag Name	Writable
0x0000	Unused	no
0x0001	ExposureAdjust	no
$0 \times 0002$	Contrast	no
0x0003	Shadow	no
$0 \times 0004$	Highlight	no
0x0005	Saturation	no
0x0006	Sharpness	no
$0 \times 0007$	RedAdjust	no
0x0008	GreenAdjust	no
0x0009	BlueAdjust	no
0x000a	X3FillLight	no

## SigmaRaw Properties Tags

Tag ID	Tag Name	Writable
'AEMODE'	MeteringMode	no
'AFAREA'	AFArea	no
'AFINFOCUS'	AFInFocus	no
'AFMODE'	FocusMode	no
'APERTURE'	FNumber	no
'AP DESC'	ApertureDisplayed	no
'BRACKET'	BracketShot	no
'BURST'	BurstShot	no
'CAMMANUF'	Make	no
'CAMMODEL'	Model	no
'CAMNAME'	CameraName	no
'CAMSERIAL'	SerialNumber	no
'CM_DESC'	SceneCaptureType	no
'COLORSPACE'	ColorSpace	no
'DRIVE'	DriveMode	no
'EVAL_STATE'	EvalState	no
'EXPCOMP'	ExposureCompensation	no
'EXPNET'	NetExposureCompensation	no
'EXPTIME'	IntegrationTime	no
'FIRMVERS'	FirmwareVersion	no
'FLASH'	FlashMode	no
'FLASHEXPCOMP'	FlashExpComp	no
'FLASHPOWER'	FlashPower	no
'FLASHTTLMODE'	FlashTTLMode	no
'FLASHTYPE'	FlashType	no
'FLENGTH'	FocalLength	no
'FLEQ35MM'	FocalLengthIn35mmFormat	no
'FOCUS'	Focus	no
'IMAGEBOARDID'	ImageBoardID	no
'IMAGERBOARDID'	ImagerBoardID	no
'IMAGERTEMP'	SensorTemperature	no
'ISO'	ISO	no
'LENSARANGE'	LensApertureRange	no
'LENSFRANGE'	LensFocalRange	no
'LENSMODEL'	LensType	no
'PMODE'	ExposureProgram	no
'RESOLUTION'	Quality	no
'SENSORID'	SensorID	no
'SHUTTER'	ExposureTime	no
'SH_DESC'	ShutterSpeedDisplayed	no
'TIME'	DateTimeOriginal	no
'VERSION_BF'	VersionBF	no
'WB_DESC'	WhiteBalance	no

## JFIF Tags

The following information is extracted from the JPEG JFIF header. See <a href="https://www.w3.org/Graphics/JPEG/jfif3.pdf">https://www.w3.org/Graphics/JPEG/jfif3.pdf</a>> for the JFIF 1.02 specification.

Index1	Tag Name	Writable

0	JFIFVersion	no:
2	ResolutionUnit	int8u:
3	XResolution	int16u:
5	YResolution	int16u:
7	ThumbnailWidth	no
8	ThumbnailHeight	no
9	ThumbnailTIFF	no

#### JFIF Extension Tags

Thumbnail images extracted from the JFXX segment.

Tag ID	Tag Name	Writable
$0 \times 0010$	ThumbnailImage	no
0x0011	ThumbnailTIFF	no
$0 \times 0013$	ThumbnailTIFF	no

### FlashPix Tags

The FlashPix file format, introduced in 1996, was developed by Kodak, Hewlett-Packard and Microsoft. Internally the FPX file structure mimics that of an old DOS disk with fixed-sized "sectors" (usually 512 bytes) and a "file allocation table" (FAT). No wonder this image format never became popular. However, some of the structures used in FlashPix streams are part of the EXIF specification, and are still being used in the APP2 FPXR segment of JPEG images by some digital cameras from manufacturers such as FujiFilm, Hewlett-Packard, Kodak and Sanyo.

ExifTool extracts FlashPix information from both FPX images and the APP2 FPXR segment of JPEG images. As well, FlashPix information is extracted from DOC, PPT, XLS (Microsoft Word, PowerPoint and Excel) documents, VSD (Microsoft Visio) drawings, and FLA (Macromedia/Adobe Flash project) files since these are based on the same file format as FlashPix (the Windows Compound Binary File format). Note that ExifTool identifies any unrecognized Windows Compound Binary file as a FlashPix (FPX) file. See <a href="http://graphcomp.com/info/specs/livepicture/fpx.pdf">http://graphcomp.com/info/specs/livepicture/fpx.pdf</a> for the FlashPix specification.

Note that Microsoft is not consistent with the time zone used for some date/time tags, and it may be either UTC or local time depending on the software used to create the file.

Tag ID	Tag Name	Writable
"\x01CompObj" "\x05Audio Info" "\x05Data Object"	CompObj AudioInfo DataObject formation" DocumentInfo Extensions GlobalInfo Image ImageInfo Operation ScreenNail n" SummaryInfo Transform AudioStream BasicFileInfo Contents CurrentUser ICC_Profile EmbeddedImage EmbeddedImageClass EmbeddedImagePreviewImage PreviewInfo	FlashPix CompObj FlashPix AudioInfo FlashPix DataObject FlashPix DocumentInfo FlashPix Extensions FlashPix GlobalInfo FlashPix Image FlashPix ImageInfo FlashPix Operation no FlashPix SummaryInfo FlashPix Transform no no XMP no ICC_Profile no no
'_eeJPG'	EmbeddedImage	no

### -- ExifTool 13.24 Tag Names --

'_eeLink'	LinkedFileName	no
'eePNG'	EmbeddedPNG	no

### FlashPix CompObj Tags

Index4	Tag Name	Writable
0	CompObjUserTypeLen	no
1	CompObjUserType	no

### FlashPix AudioInfo Tags

Tag ID	Tag Name	Writable
[no tags	known]	

### FlashPix DataObject Tags

Tag ID	Tag Name	Writable
0x10000	DataObjectID	no
0x10002	LockedPropertyList	no
0x10003	DataObjectTitle	no
0x10004	LastModifier	no
0x10005	RevisionNumber	no
0x10006	DataCreateDate	no
0x10007	DataModifyDate	no
0x10008	CreatingApplication	no
0x10100	DataObjectStatus	no
0x10101	CreatingTransform	no
0x10102	UsingTransforms	no
0x10000000	CachedImageHeight	no
0x10000001	CachedImageWidth	no

## FlashPix DocumentInfo Tags

The DocumentSummaryInformation property set includes a UserDefined property set for which only the Hyperlinks and HyperlinkBase tags are pre-defined. However, ExifTool will also extract any other information found in the UserDefined properties.

Tag ID	Tag Name	Writable
0x0002	Category	no
0x0003	PresentationTarget	no
$0 \times 0004$	Bytes	no
$0 \times 0005$	Lines	no
0x0006	Paragraphs	no
$0 \times 0007$	Slides	no
$0 \times 0008$	Notes	no
$0 \times 0009$	HiddenSlides	no
0x000a	MMClips	no
$0 \times 000 $ b	ScaleCrop	no
0x000c	HeadingPairs	no
0x000d	TitleOfParts	no
0x000e	Manager	no
0x000f	Company	no
$0 \times 0010$	LinksUpToDate	no
$0 \times 0011$	CharCountWithSpaces	no
$0 \times 0013$	SharedDoc	no
$0 \times 0016$	HyperlinksChanged	no
$0 \times 0017$	AppVersion	no
0x001a	ContentType	no
0x001b	ContentStatus	no
0x001c	Language	no
0x001d	DocVersion	no
'_PID_HLINKS'	Hyperlinks	no
'_PID_LINKBASE'	HyperlinkBase	no

Tag ID	Tag Name	Writable
$0 \times 0001$	ExtensionName	no
0x0002	ExtensionClassID	no
0x0003	ExtensionPersistence	no
$0 \times 0 0 0 4$	ExtensionCreateDate	no
0x0005	ExtensionModifyDate	no
0x0006	CreatingApplication	no
$0 \times 0007$	ExtensionDescription	no
0x1000	Storage-StreamPathname	no
0x2000	FlashPixStreamPathname	no
0x2001	FlashPixStreamFieldOffset	no
0x3000	PropertySetPathname	no
0x3001	PropertySetIDCodes	no
0x3002	PropertyVectorElements	no
0x4000	SubimageResolutions	no
0x10000000	UsedExtensionNumbers	no

# FlashPix GlobalInfo Tags

Tag ID	Tag Name	Writable
0x10002	LockedPropertyList	no
0x10003	TransformedImageTitle	no
0x10004	LastModifier	no
0x10100	VisibleOutputs	no
0x10101	MaximumImageIndex	no
0x10102	${ t MaximumTransformIndex}$	no
0x10103	MaximumOperationIndex	no

## FlashPix Image Tags

Tag ID	Tag Name	Writable
0x1000000	NumberOfResolutions	no
0x1000002	ImageWidth	no
0x1000003	ImageHeight	no
0x1000004	DefaultDisplayHeight	no
0x1000005	DefaultDisplayWidth	no
0x1000006	DisplayUnits	no
0x2000000	SubimageWidth	no
0x2000001	SubimageHeight	no
0x2000002	SubimageColor	no
0x2000003	SubimageNumericalFormat	no
0x2000004	DecimationMethod	no
0x2000005	DecimationPrefilterWidth	no
0x2000007	SubimageICC_Profile	no
0x3000001	JPEGTables	no
0x3000002	MaxJPEGTableIndex	no

## FlashPix ImageInfo Tags

Tag ID	Tag Name	Writable
0x21000000	FileSource	no
0x21000001	SceneType	no
0x21000002	CreationPathVector	no
0x21000003	SoftwareRelease	no
0x21000004	UserDefinedID	no
0x21000005	SharpnessApproximation	no
0x22000000	Copyright	no
0x22000001	OriginalImageBroker	no
0x22000002	DigitalImageBroker	no
0x22000003	Authorship	no
0x22000004	IntellectualPropertyNotes	no
0x23000000	TestTarget	no
0x23000002	GroupCaption	no
0x23000003	CaptionText	no
0x23000004	People	no

0x23000007	Things	no
0x2300000a	DateTimeOriginal	no
0x2300000b	Events	no
0x2300000c	Places	no
0x2300000f	ContentDescriptionNotes	no
0x24000000	Make	no
0x24000001	Model	no
0x24000002	SerialNumber	no
0x25000000	CreateDate	no
0x25000001	ExposureTime	no
0x25000001	FNumber	no
0x25000002	ExposureProgram	
		no
0x25000004	BrightnessValue	no
0x25000005	ExposureCompensation	no
0x25000006	SubjectDistance	no
0x25000007	MeteringMode	no
0x25000008	LightSource	no
0x25000009	FocalLength	no
0x2500000a	MaxApertureValue	no
0x2500000b	Flash	no
0x2500000c	FlashEnergy	no
0x2500000d	FlashReturn	no
0x2500000e	BackLight	no
0x2500000f	SubjectLocation	no
0x25000010	ExposureIndex	no
0x25000011	SpecialEffectsOpticalFilter	no
0x25000012	PerPictureNotes	no
0x26000000	SensingMethod	no
0x26000001	FocalPlaneXResolution	no
0x26000002	FocalPlaneYResolution	no
0x26000003	FocalPlaneResolutionUnit	no
0x26000003	SpatialFrequencyResponse	no
0x26000001	CFAPattern	
0x26000003	ISO	no
0x26000007		no
	Opto-ElectricConvFactor	no
0x27000000	FilmBrand	no
0x27000001	FilmCategory	no
0x27000002	FilmSize	no
0x27000003	FilmRollNumber	no
0x27000004	FilmFrameNumber	no
0x28000000	ScannerMake	no
0x28000001	ScannerModel	no
0x28000002	ScannerSerialNumber	no
0x28000003	ScanSoftware	no
0x28000004	ScanSoftwareRevisionDate	no
0x28000005	ServiceOrganizationName	no
0x28000006	ScanOperatorID	no
0x28000008	ScanDate	no
0x28000009	ModifyDate	no
0x2800000a	ScannerPixelSize	no
0x29000000	OriginalScannedImageSize	no
0x29000001	OriginalDocumentSize	no
0x29000002	OriginalMedium	no
0x29000003	TypeOfOriginal	no
	=11.00=0==3===	110

## FlashPix Operation Tags

Tag ID	Tag Name	Writable
0x10000	OperationID	no

### FlashPix SummaryInfo Tags

The Dictionary, CodePage and LocalIndicator tags are common to all FlashPix property tables, even though they are only listed in the SummaryInfo table.

Tag ID	Tag Name	Writable
0x0000	Dictionary	no

0x0001	CodePage	no
0x0002	Title	no
0x0003	Subject	no
$0 \times 0004$	Author	no
$0 \times 0005$	Keywords	no
0x0006	Comments	no
$0 \times 0007$	Template	no
0x0008	LastModifiedBy	no
$0 \times 0009$	RevisionNumber	no
0x000a	TotalEditTime	no
0x000b	LastPrinted	no
0x000c	CreateDate	no
0x000d	ModifyDate	no
0x000e	Pages	no
0x000f	Words	no
$0 \times 0010$	Characters	no
$0 \times 0011$	ThumbnailClip	no
$0 \times 0012$	Software	no
0x0013	Security	no
0x0022	CreatedBy	no
$0 \times 0023$	DocumentID	no
0x80000000	LocaleIndicator	no

## FlashPix Transform Tags

Tag ID	Tag Name	Writable
0x10000	TransformNodeID	no
0x10001	OperationClassID	no
0x10002	LockedPropertyList	no
0x10003	TransformTitle	no
0x10004	LastModifier	no
0x10005	RevisionNumber	no
0x10006	TransformCreateDate	no
0x10007	TransformModifyDate	no
0x10008	CreatingApplication	no
0x10100	InputDataObjectList	no
0x10101	OutputDataObjectList	no
0x10102	OperationNumber	no
0x10000000	ResultAspectRatio	no
0x10000001	RectangleOfInterest	no
0x10000002	Filtering	no
0x10000003	SpatialOrientation	no
0x10000004	ColorTwistMatrix	no
0x10000005	ContrastAdjustment	no

## FlashPix PreviewInfo Tags

Preview information written by some FujiFilm models.

Index1	Tag Name	Writable
13	PreviewImageWidth	no
23	PreviewImageHeight	no

## FlashPix SubimageHdr Tags

Index4	Tag Name	Writable
1	SubimageWidth	no
2	SubimageHeight	no
3	SubimageTileCount	no
4	SubimageTileWidth	no
5	SubimageTileHeight	no
6	NumChannels	no

## FlashPix WordDocument Tags

Tags extracted from the Microsoft Word document stream.

Tag ID	Tag Name	Writable
0x0000	Identification	no
0x0003	LanguageCode	no
$0 \times 0005$	DocFlags	no
9.1	System	no
9.2	Word97	no

### FlashPix DocTable Tags

Tags extracted from the Microsoft Word document table.

Tag Name	Writable
CommentBy	no
DOP	FlashPix DOP
LastSavedBy	no
ModifyDate	no

#### FlashPix DOP Tags

Microsoft office document properties.

Index1	Tag Name	Writable
20	CreateDate	no
24	ModifyDate	no
28	LastPrinted	no
32	RevisionNumber	no
34	TotalEditTime	no
38	Words	no
42	Characters	no
46	Pages	no
48	Paragraphs	no
56	Lines	no

#### MPF Tags

These tags are part of the CIPA Multi-Picture Format specification, and are found in the APP2 "MPF" segment of JPEG images. MPImage data referenced from this segment is stored as a JPEG trailer. The MPF tags are not writable, however the MPF segment may be deleted as a group (with "MPF:All") but then the JPEG trailer should also be deleted (with "Trailer:All"). See

<https://web.archive.org/web/20190713230858/http://www.cipa.jp/std/documents/e/DC007 E.pdf>

for the official specification.

Tag ID	Tag Name	Writable
0xb000	MPFVersion	no
0xb001	NumberOfImages	no
0xb002	MPImageList	MPF MPImage
0xb003	ImageUIDList	no
0xb004	TotalFrames	no
0xb101	MPIndividualNum	no
0xb201	PanOrientation	no
0xb202	PanOverlapH	no
0xb203	PanOverlapV	no
0xb204	BaseViewpointNum	no
0xb205	ConvergenceAngle	no
0xb206	BaselineLength	no
0xb207	VerticalDivergence	no
0xb208	AxisDistanceX	no
0xb209	AxisDistanceY	no
0xb20a	AxisDistanceZ	no
0xb20b	YawAngle	no
0xb20c	PitchAngle	no
0xb20d	RollAngle	no

The first MPF "Large Thumbnail" image is extracted as PreviewImage, and the rest of the embedded MPF images are extracted as MPImage#. The ExtractEmbedded (-ee) option may be used to extract information from these embedded images.

Index1	Tag Name	Writable
0.1	MPImageFlags	no
0.2	MPImageFormat	no
0.3	MPImageType	no
4	MPImageLength	no
8	MPImageStart	no
12	DependentImage1EntryNumber	no
14	DependentImage2EntryNumber	no

### InfiRay Tags

### InfiRay Version Tags

This table lists tags found in the InfiRay APP2 IJPEG version header, found in JPEGs taken with the P2 Pro camera app.

0 IJPEGVersion no 12 IJPEGOrgType no 13 IJPEGDispType no 14 IJPEGRotate no 15 IJPEGMirrorFlip no 16 ImageColorSwitchable no 17 ThermalColorPalette no 32 IRDataSize no 40 IRDataFormat no 42 IRImageWidth no 44 IRImageHeight no 45 TempDataSize no 56 TempDataFormat no 58 TempImageWidth no 58 TempImageWidth no 60 TempImageHeight no 61 TempImageHeight no 62 TempImageBpp no 64 VisibleDataSize no 72 VisibleDataFormat no 74 VisibleImageWidth no 76 VisibleImageHeight no 77 VisibleImageWidth no 78 VisibleImageHeight no	Index1	Tag Name	Writable
12IJPEGOrgTypeno13IJPEGDispTypeno14IJPEGRotateno15IJPEGMirrorFlipno16ImageColorSwitchableno17ThermalColorPaletteno32IRDataSizeno40IRDataFormatno42IRImageWidthno44IRImageHeightno46IRImageBppno56TempDataSizeno56TempImageWidthno60TempImageHeightno62TempImageBppno64VisibleDataSizeno72VisibleDataFormatno74VisibleImageWidthno75VisibleImageWidthno76VisibleImageWidthno			
13 IJPEGDispType no 14 IJPEGRotate no 15 IJPEGMirrorFlip no 16 ImageColorSwitchable no 17 ThermalColorPalette no 32 IRDataSize no 40 IRDataFormat no 42 IRImageWidth no 44 IRImageHeight no 46 IRImageBpp no 48 TempDataSize no 56 TempDataFormat no 58 TempImageWidth no 60 TempImageWidth no 60 TempImageHeight no 62 TempImageBpp no 64 VisibleDataSize no 72 VisibleDataFormat no 74 VisibleImageWidth no 76 VisibleImageWidth no	0	IJPEGVersion	no
14 IJPEGRotate no 15 IJPEGMirrorFlip no 16 ImageColorSwitchable no 17 ThermalColorPalette no 32 IRDataSize no 40 IRDataFormat no 42 IRImageWidth no 44 IRImageHeight no 46 IRImageBpp no 48 TempDataSize no 56 TempDataFormat no 58 TempImageWidth no 60 TempImageWidth no 60 TempImageHeight no 62 TempImageBpp no 64 VisibleDataSize no 72 VisibleDataFormat no 74 VisibleImageWidth no 76 VisibleImageWidth no	12	IJPEGOrgType	no
15 IJPEGMirrorFlip no 16 ImageColorSwitchable no 17 ThermalColorPalette no 32 IRDataSize no 40 IRDataFormat no 42 IRImageWidth no 44 IRImageHeight no 46 IRImageBpp no 48 TempDataSize no 56 TempDataFormat no 58 TempImageWidth no 60 TempImageWidth no 60 TempImageHeight no 62 TempImageBpp no 64 VisibleDataSize no 72 VisibleDataFormat no 74 VisibleImageWidth no 76 VisibleImageHeight no	13	IJPEGDispType	no
16ImageColorSwitchableno17ThermalColorPaletteno32IRDataSizeno40IRDataFormatno42IRImageWidthno44IRImageHeightno46IRImageBppno48TempDataSizeno56TempDataFormatno58TempImageWidthno60TempImageHeightno62TempImageBppno64VisibleDataSizeno72VisibleDataFormatno74VisibleImageWidthno76VisibleImageHeightno	14	IJPEGRotate	no
17 ThermalColorPalette no 32 IRDataSize no 40 IRDataFormat no 42 IRImageWidth no 44 IRImageHeight no 46 IRImageBpp no 48 TempDataSize no 56 TempDataFormat no 58 TempImageWidth no 60 TempImageHeight no 62 TempImageBpp no 64 VisibleDataSize no 72 VisibleDataFormat no 74 VisibleImageWidth no 76 VisibleImageHeight no	15	IJPEGMirrorFlip	no
IRDataSize no IRDataFormat no IRDataFormat no IRImageWidth no IRImageHeight no IRImageBpp no IRImageBpp no IRImageBpp no IRImageWidth no IRIMAGEWIDTE no IRIMAGEWIDTE no IRIMAGEMENT NO IRIMAGEMEN	16	ImageColorSwitchable	no
40 IRDataFormat no 42 IRImageWidth no 44 IRImageHeight no 46 IRImageBpp no 48 TempDataSize no 56 TempDataFormat no 58 TempImageWidth no 60 TempImageHeight no 62 TempImageBpp no 64 VisibleDataSize no 72 VisibleDataFormat no 74 VisibleImageWidth no 76 VisibleImageHeight no	17	ThermalColorPalette	no
42 IRImageWidth no 44 IRImageHeight no 46 IRImageBpp no 48 TempDataSize no 56 TempDataFormat no 58 TempImageWidth no 60 TempImageHeight no 62 TempImageBpp no 64 VisibleDataSize no 72 VisibleDataFormat no 74 VisibleImageWidth no 76 VisibleImageHeight no	32	IRDataSize	no
44 IRImageHeight no 46 IRImageBpp no 48 TempDataSize no 56 TempDataFormat no 58 TempImageWidth no 60 TempImageHeight no 62 TempImageBpp no 64 VisibleDataSize no 72 VisibleDataFormat no 74 VisibleImageWidth no 76 VisibleImageHeight no	40	IRDataFormat	no
46 IRImageBpp no 48 TempDataSize no 56 TempDataFormat no 58 TempImageWidth no 60 TempImageHeight no 62 TempImageBpp no 64 VisibleDataSize no 72 VisibleDataFormat no 74 VisibleImageWidth no 76 VisibleImageHeight no	42	IRImageWidth	no
48 TempDataSize no 56 TempDataFormat no 58 TempImageWidth no 60 TempImageHeight no 62 TempImageBpp no 64 VisibleDataSize no 72 VisibleDataFormat no 74 VisibleImageWidth no 76 VisibleImageHeight no	44	IRImageHeight	no
TempDataFormat no TempImageWidth no TempImageHeight no TempImageBpp no VisibleDataSize no VisibleDataFormat no VisibleImageWidth no VisibleImageHeight no	46	IRImageBpp	no
TempImageWidth no TempImageHeight no TempImageBpp no TempImageBpp no VisibleDataSize no VisibleDataFormat no VisibleImageWidth no VisibleImageHeight no	48	TempDataSize	no
60 TempImageHeight no 62 TempImageBpp no 64 VisibleDataSize no 72 VisibleDataFormat no 74 VisibleImageWidth no 76 VisibleImageHeight no	56	TempDataFormat	no
TempImageBpp no  YisibleDataSize no  VisibleDataFormat no  VisibleImageWidth no  VisibleImageHeight no	58	TempImageWidth	no
64 VisibleDataSize no 72 VisibleDataFormat no 74 VisibleImageWidth no 76 VisibleImageHeight no	60	TempImageHeight	no
72 VisibleDataFormat no 74 VisibleImageWidth no 76 VisibleImageHeight no	62	TempImageBpp	no
74 VisibleImageWidth no 76 VisibleImageHeight no	64	VisibleDataSize	no
76 VisibleImageHeight no	72	VisibleDataFormat	no
3 3	74	VisibleImageWidth	no
78 VisibleImageBpp no	76	VisibleImageHeight	no
	78	VisibleImageBpp	no

### InfiRay Factory Tags

This table lists tags found in the InfiRay APP4 IJPEG camera factory defaults and calibration data.

Index1	Tag Name	Writable
0	IJPEGTempVersion	no
4	FactDefEmissivity	no
5	FactDefTau	no
6	FactDefTa	no
8	FactDefTu	no
10	FactDefDist	no
12	FactDefA0	no
16	FactDefB0	no
20	FactDefA1	no
24	FactDefB1	no
28	FactDefP0	no
32	FactDefP1	no
36	FactDefP2	no
68	FactRelSensorTemp	no
70	FactRelShutterTemp	no
72	FactRelLensTemp	no

100	FactStatusGain	no
101	FactStatusEnvOK	no
102	FactStatusDistOK	no
103	FactStatusTempMap	no

### <u>InfiRay Picture Tags</u>

This table lists tags found in the InfiRay  $\mbox{APP5}$  IJPEG picture temperature information.

Index1	Tag Name	Writable
0	EnvironmentTemp	no
4	Distance	no
8	Emissivity	no
12	Humidity	no
16	ReferenceTemp	no
32	TempUnit	no
33	ShowCenterTemp	no
34	ShowMaxTemp	no
35	ShowMinTemp	no
36	TempMeasureCount	no

### <u>InfiRay MixMode Tags</u>

This table lists tags found in the InfiRay APP6 IJPEG visual-infrared mixing mode section.

Index1	Tag Name	Writable
0	MixMode	no
1	FusionIntensity	no
5	OffsetAdjustment	no
9	CorrectionAsix	no

#### InfiRay OpMode Tags

This table lists tags found in the InfiRay APP7 IJPEG camera operation mode section.

Index1	Tag Name	Writable
0	WorkingMode	no
1	IntegralTime	no
5	IntegratTimeHdr	no
9	GainStable	no
10	TempControlEnable	no
11	DeviceTemp	no

### <u>InfiRay Isothermal Tags</u>

This table lists tags found in the InfiRay APP8 IJPEG picture isothermal information.

Index1	Tag Name	Writable
0	IsothermalMax	no
4	IsothermalMin	no
8	ChromaBarMax	no
12	ChromaBarMin	no

#### InfiRay Sensor Tags

This table lists tags found in the InfiRay APP9 IJPEG sensor information chunk.

Index1	Tag Name	Writable
0	IRSensorManufacturer	no
64	IRSensorName	no

128	IRSensorPartNumber	no
192	IRSensorSerialNumber	no
256	IRSensorFirmware	no
320	IRSensorAperture	no
324	IRFocalLength	no
384	VisibleSensorManufacturer	no
448	VisibleSensorName	no
512	VisibleSensorPartNumber	no
576	VisibleSensorSerialNumber	no
640	VisibleSensorFirmware	no
704	VisibleSensorAperture	no
708	VisibleFocalLength	no

### Stim Tags

These tags are part of the CIPA Stereo Still Image specification, and are found in the APP3 "Stim" segment of JPEG images. See <a href="https://web.archive.org/web/20190718152459/http://www.cipa.jp/std/documents/e/DC-006 E.pdf">https://www.cipa.jp/std/documents/e/DC-006 E.pdf</a>

for the official specification.

Tag ID	Tag Name	Writable
0x0000	StimVersion	no
$0 \times 0001$	ApplicationData	no
$0 \times 0002$	ImageArrangement	no
$0 \times 0003$	ImageRotation	no
$0 \times 0004$	ScalingFactor	no
$0 \times 0005$	CropXSize	no
$0 \times 0006$	CropYSize	no
$0 \times 0007$	CropX	Stim CropX
0x0008	CropY	Stim CropY
$0 \times 0009$	ViewType	no
0x000a	RepresentativeImage	no
0x000b	ConvergenceBaseImage	no
0x000c	AssumedDisplaySize	no
0x000d	AssumedDistanceView	no
0x000e	RepresentativeDisparityNear	no
0x000f	RepresentativeDisparityFar	no
$0 \times 0010$	InitialDisplayEffect	no
$0 \times 0011$	ConvergenceDistance	no
$0 \times 0012$	CameraArrangementInterval	no
$0 \times 0013$	ShootingCount	no

### Stim CropX Tags

Index1	Tag Name	Writable
0	CropXCommonOffset	no
2	CropXViewpointNumber	no
3	CropXOffset	no
7	CropXViewpointNumber2	no
8	CropXOffset2	no

### Stim CropY Tags

Index1	Tag Name	Writable
0	CropYCommonOffset	no
2	CropYViewpointNumber	no
3	CropYOffset	no
7	CropYViewpointNumber2	no
8	CropYOffset2	no

### Scalado Tags

Tags extracted from the JPEG APP4 "SCALADO" segment found in images from HTC, LG and Samsung phones. (Presumably written by Scalado mobile software, <http://www.scalado.com/>.)

Tag ID	Tag Name	Writable

'HGHT'	PreviewImageHeight	no
'QUAL'	PreviewQuality	no
'SPMO'	DataLength?	no
'WDTH'	PreviewImageWidth	no

### Qualcomm Tags

The tags below have been observed in the JPEG APP7 "Qualcomm Camera Attributes" segment written by some cameras such as the HP iPAQ Voice Messenger. ExifTool will extract any information found from this segment, even if it is not listed in this table.

Tag Name	Writable
AECAggressiveness	no
AECCurrentExpIndex	no
AECCurrentSensorLuma AECEnable	no
	no
AECExposureIndexAdjStep AECHighLumaRegionCount	no no
AECHighLumaRegionThreshold	no
AECIndoorIdx	no
AECLumaTarget	no
AECLumaTolerance	no
AECMode	no
AECOdoorIdx	no
AECOutdoorBrightDiscarded	no
AECOutdoorBrightEnable	no
AECOutdoorBrightReduction	no
AECOutdoorBrightThresholdHI	no
AECOutdoorBrightThresholdLO	no
AECOutdoorGammaIndex	no
AECSnapshotDigitalGain	no
AECSnapshotExposureTimeMs	no
AECSnapshotLineCount	no
AECKsnapshotSensorGain	no
AECVfeLuma AEPoundary	no
AFBoundary AFCollectEndStat	no no
AFEnable	no
AFFarEnd	no
AFFineSrchPoints	no
AFFineStep	no
AFFocusTime	no
AFGrossStep	no
AFMode	no
AFNearEnd	no
AFPosDefMacro	no
AFPosDefNorm	no
AFPosition	no
AFProcess	no
AFREnable	no
AFRFaster0ExpMod	no
AFRFaster0Trigger	no
AFRFaster1ExpMod	no
AFRFaster1Trigger	no
AFRFaster2ExpMod	no
AFRFaster2Trigger AFRFaster3ExpMod	no no
AFRFaster3Trigger	no
AFRFaster4ExpMod	no
AFRFaster4Trigger	no
AFRPossibleFrameCnt	no
AFRSlower0ExpMod	no
AFRSlower0Trigger	no
AFRSlower1ExpMod	no
AFRSlower1Trigger	no
AFRSlower2ExpMod	no
AFRSlower2Trigger	no
AFRSlower3ExpMod	no
AFRSlower3Trigger	no

	EXILIOOI	13.24	Iag	Names	
AFRSlower4ExpMod					no
AFRSlower4Trigger					no
AFResetLensAfterSna	n				
	.р				no
AFStepsNearFar					no
AFStepsNearInfinity					no
AFTestMode					no
AFTracePositions00					no
AFTracePositions01					
					no
AFTracePositions02					no
AFTracePositions03					no
AFTracePositions04					no
AFTracePositions05					no
AFTracePositions06					
					no
AFTracePositions07					no
AFTracePositions08					no
AFTracePositions09					no
AFTracePositions10					no
AFTracePositions11					
					no
AFTracePositions12					no
AFTracePositions13					no
AFTracePositions14					no
AFTracePositions15					no
AFTracePositions16					
					no
AFTracePositions17					no
AFTracePositions18					no
AFTracePositions19					no
AFTracePositions20					no
AFTracePositions21					
					no
AFTracePositions22					no
AFTracePositions23					no
AFTracePositions24					no
AFTracePositions25					no
AFTracePositions26					no
AFTracePositions27					no
AFTracePositions28					no
AFTracePositions29					no
AFTracePositions30					no
AFTracePositions31					no
AFTracePositions32					
					no
AFTracePositions33					no
AFTracePositions34					no
AFTracePositions35					no
AFTracePositions36					no
AFTracePositions37					
					no
AFTracePositions38					no
AFTracePositions39					no
AFTracePositions40					no
AFTracePositions41					no
AFTracePositions42					
					no
AFTracePositions43					no
AFTracePositions44					no
AFTracePositions45					no
AFTracePositions46					no
AFTracePositions47					
					no
AFTracePositions48					no
AFTracePositions49					no
AFTraceStats00					no
AFTraceStats01					no
AFTraceStats02					no
AFTraceStats03					no
AFTraceStats04					no
AFTraceStats05					no
AFTraceStats06					no
AFTraceStats07					no
AFTraceStats08					no
AFTraceStats09					no
AFTraceStats10					no
AFTraceStats11					no
AFTraceStats12					no
AFTraceStats13					
Ar II accolatolo					no

		ExifTool	13.24	Tag	Names	
AFTraceStats14						no
AFTraceStats15						no
AFTraceStats16						no
AFTraceStats17						no
AFTraceStats18						no
AFTraceStats19						no
AFTraceStats20						no
AFTraceStats21						no
AFTraceStats22						no
AFTraceStats23						no
AFTraceStats24						no
AFTraceStats25						no
AFTraceStats26						no
AFTraceStats27						no
AFTraceStats28						no
AFTraceStats29						no
AFTraceStats30						no
AFTraceStats31						no
AFTraceStats32						no
AFTraceStats33						no
AFTraceStats34						no
AFTraceStats35						no
AFTraceStats36						no
AFTraceStats37						no
AFTraceStats38						no
AFTraceStats39						no
AFTraceStats40						no
AFTraceStats41						no
AFTraceStats42						no
AFTraceStats43						no
AFTraceStats44						no
AFTraceStats45						no
AFTraceStats46						no
AFTraceStats47						no
AFTraceStats48						no
AFTraceStats49						no
AFUndershootProt	ect	-				no
AFVfeHorzOffset						no
AFVfeHorzWidth						no
AFVfeMetricMax						no
AFVfeVertHeight						no
AFVfeVertOffset						no
ASF3EdgeDetect						no
ASF3EdgeFilterAl	L1					no
ASF3EdgeFilterA1	_2					no
ASF3EdgeFilterA1	L3					no
ASF3EdgeFilterA2	21					no
ASF3EdgeFilterA2	22					no
ASF3EdgeFilterA2	23					no
ASF3EdgeFilterA3	31					no
ASF3EdgeFilterA3	32					no
ASF3EdgeFilterA3	33					no
ASF3Enable						no
ASF3LowerThresho	old					no
ASF3NoiseFilterA	11					no
ASF3NoiseFilterA	12					no
ASF3NoiseFilterA	113					no
ASF3NoiseFilterA	121					no
ASF3NoiseFilterA	122					no
ASF3NoiseFilterA	123					no
ASF3NoiseFilterA	431					no
ASF3NoiseFilterA	132					no
ASF3NoiseFilterA	433					no
ASF3UpperThresho	old					no
ASF5BrtLoThres						no
ASF5BrtShrpDegF1	L					no
ASF5BrtShrpDegF2	2					no
ASF5BrtSmthPerce	ent					no
ASF5BrtUpThres						no
ASF5Enable						no

	ExifTool	13.24	Tag	Names	
ASF5ExposureIndex1					no
ASF5ExposureIndex2					no
ASF5Filter1A11					no
ASF5Filter1A12					no
ASF5Filter1A13					
					no
ASF5Filter1A14					no
ASF5Filter1A15					no
ASF5Filter1A21					no
ASF5Filter1A22					no
ASF5Filter1A23					no
ASF5Filter1A24					no
ASF5Filter1A25					no
ASF5Filter1A31					no
ASF5Filter1A32					no
ASF5Filter1A33					no
ASF5Filter1A34					no
ASF5Filter1A35					no
ASF5Filter1A41					no
ASF5Filter1A42					no
ASF5Filter1A43					no
ASF5Filter1A44					no
ASF5Filter1A45					
ASF5Filter1A51					no
					no
ASF5Filter1A52					no
ASF5Filter1A53					no
ASF5Filter1A54					no
ASF5Filter1A55					no
ASF5Filter2A11					no
ASF5Filter2A12					no
ASF5Filter2A13					no
ASF5Filter2A14					no
ASF5Filter2A15					no
ASF5Filter2A21					no
ASF5Filter2A22					no
ASF5Filter2A23					no
ASF5Filter2A24					no
ASF5Filter2A25					no
ASF5Filter2A31					no
ASF5Filter2A32					no
ASF5Filter2A33					no
ASF5Filter2A34					no
ASF5Filter2A35					
ASF5Filter2A41					no
ASF5Filter2A41					no
					no
ASF5Filter2A43					no
ASF5Filter2A44					no
ASF5Filter2A45					no
ASF5Filter2A51					no
ASF5Filter2A52					no
ASF5Filter2A53					no
ASF5Filter2A54					no
ASF5Filter2A55					no
ASF5FilterMode					no
ASF5LowLoThres					no
ASF5LowShrpDegF1					no
ASF5LowShrpDegF2					no
ASF5LowSmthPrcnt					no
ASF5LowUpThres					no
ASF5LumaFilter00					no
ASF5LumaFilter01					no
ASF5LumaFilter02					no
ASF5LumaFilter03					no
ASF5LumaFilter04					
ASF5LumaFilter05					no
					no
ASF5LumaFilter06					no
ASF5LumaFilter07					no
ASF5LumaFilter08					no
ASF5MaxExposureInde	ex				no
ASF5NrmLoThres					no
ASF5NrmShrpDegF1					no

	ExifTool	13.24	Tag	Names	
ASF5NrmShrpDegF2					no
ASF5NrmSmthPrcnt					no
ASF5NrmUpThres					no
ASF5NrmizeFactor1 ASF5NrmizeFactor2					no
AWBAggressiveness					no no
AWBAgwGridDist2Thre	esh				no
AWBAlgorithm					no
AWBAveBgRatio					no
AWBAveRgRatio					no
AWBBlueGainAdjRef1 AWBBlueGainAdjRef2					no
AWBBlueGainAdjRef3					no no
AWBBlueGainAdjRef4					no
AWBBlueGainAdjRef5					no
AWBBlueGainAdjRef6					no
AWBBlueGainAdjRef7					no
AWBBlueGainAdjRef8					no
AWBBlueGainRef1 AWBBlueGainRef2					no no
AWBBlueGainRef3					no
AWBBlueGainRef4					no
AWBBlueGainRef5					no
AWBBlueGainRef6					no
AWBBlueGainRef7					no
AWBBlueGainRef8 AWBCcBias					no
AWBCCB1as AWBCompactClusterR2	2				no no
AWBEnable	_				no
AWBGreenOffsetBg					no
AWBGreenOffsetRg					no
AWBIndoorSampleInfl	Luence				no
AWBLoVfeC1					no
AWBLoVfeC2 AWBLoVfeC3					no no
AWBLoVfeC4					no
AWBLoVfeM1					no
AWBLoVfeM2					no
AWBLoVfeM3					no
AWBLOVfeM4					no
AWBLoVfeMaxY AWBLoVfeMinY					no no
AWBLOWLigColCorEna					no
AWBMaxBGain					no
AWBMaxGGain					no
AWBMaxRGain					no
AWBMinBGain AWBMinGGain					no
AWBMINGGain AWBMinRGain					no no
AWBNormVfeC1					no
AWBNormVfeC2					no
AWBNormVfeC3					no
AWBNormVfeC4					no
AWBNormVfeM1					no
AWBNormVfeM2 AWBNormVfeM3					no
AWBNormVfeM4					no no
AWBNormVfeMaxY					no
AWBNormVfeMinY					no
AWBOudorVfeC1					no
AWBOudorVfeC2					no
AWBOudorVfeC3 AWBOudorVfeC4					no
AWBOudorVfeM1					no no
AWBOudorVfeM2					no
AWBOudorVfeM3					no
AWBOudorVfeM4					no
AWBOudorVfeMaxY					no
AWBOutdoorSampleInf	Fluenco				no
AWBOutdoorSampleInf	Tuence				no

	ExifTool	13.24	Tag	Names	
AWBPrevWbBgain					no
AWBPrevWbGgain					no
AWBPrevWbRgain					no
AWBRedGainAdjRef1					no
AWBRedGainAdjRef2					no
AWBRedGainAdjRef3					no
AWBRedGainAdjRef4					no
AWBRedGainAdjRef5					no
AWBRedGainAdjRef6					no
AWBRedGainAdjRef7					no
AWBRedGainAdjRef8 AWBRedGainRef1					no
AWBRedGainRef1					no
AWBRedGainRef3					no
AWBRedGainRef4					no no
AWBRedGainRef5					no
AWBRedGainRef6					no
AWBRedGainRef7					no
AWBRedGainRef8					no
AWBSampleDecision					no
AWBSnapshotBGain					no
AWBSnapshotRGain					no
AntiBadingPixelClk					no
AntiBadingPixelClk	PerLine				no
AntibandingEnable					no
BlckLvlEvenCols					no
BlckLvlOddCols					no
CamMclkHz					no
ChroSupChroThres1					no
ChroSupChroThres2 ChroSupLumaThres1					no no
ChroSupLumaThres2					no
ChroSupLumaThres3					no
ChroSupLumaThres4					no
ChromSupress					no
ClipToAfRato					no
CurrResol					no
DayltConvChrmA_M					no
DayltConvChrmA_P					no
DayltConvChrmB_M					no
DayltConvChrmB_P					no
DayltConvChrmC_M					no
DayltConvChrmC_P DayltConvChrmD_M					no
DayltConvChrmD_P					no no
DayltConvChrmKCb					no
DayltConvChrmKCr					no
DayltConvLumaK					no
DayltConvLumaV0					no
DayltConvLumaV1					no
DayltConvLumaV2					no
DefConvChrmA_M					no
DefConvChrmA_P					no
DefConvChrmB_M					no
DefConvChrmB_P					no
DefConvChrmC_M DefConvChrmC P					no
DefConvChrmD M					no
DefConvChrmD P					no no
DefConvChrmKCb					no
DefConvChrmKCr					no
DefConvLumaK					no
DefConvLumaV0					no
DefConvLumaV1					no
DefConvLumaV2					no
DefCorC0					no
DefCorC1					no
DefCorC2					no
DefCorC3					no
DefCorC4					no

		ExifTool	13.24	Tag	Names	
DefCorC5						no
DefCorC6						no
DefCorC7						no
DefCorC8						no
DefCorK0						no
DefCorK1						no
DefCorK2						no
DefLumaGammaMode DefRgbGammaMode	9					no
DefectPixCorEnal	21.0					no
DefectPixMaxThre						no no
DefectPixMinThre						no
DiscardFrstFrm	5611					no
FrmSkipPttrn						no
GammaEnable						no
HJREnable						no
HJRMaxNumFrames						no
HJROneToTwoOffs						no
HJRTextureThresl		d				no
HJR_NReductionF						no
HJR_NReductionTe		ıre				no
IncandConvChrmA_ IncandConvChrmA	_					no
IncandConvChrmB	_					no no
IncandConvChrmB	_					no
IncandConvChrmC						no
IncandConvChrmC	_					no
IncandConvChrmD	_ _M					no
IncandConvChrmD_	_P					no
IncandConvChrmK	Cb					no
IncandConvChrmK(	Cr					no
IncandConvLumaK	_					no
IncandConvLumaV						no
IncandConvLumaVI						no
LADetect	۷					no no
LAEnable						no
MaxPrviewFps						no
MaxVideoFps						no
NghtshtFps						no
NightshotMode						no
OutlierDistance						no
PclkInvert						no
PrviewFps						no
PrviewResol						no
R2ABlueCtbl00 R2ABlueCtbl01						no
R2ABlueCtbl01						no
R2ABlueCtbl02						no no
R2ABlueCtbl04						no
R2ABlueCtbl05						no
R2ABlueCtbl06						no
R2ABlueCtbl07						no
R2ABlueCtbl08						no
R2ABlueCtbl09						no
R2ABlueCtbl10						no
R2ABlueCtbl11						no
R2ABlueCtbl12						no
R2ABlueCtbl13 R2ABlueCtbl14						no
R2ABlueCtbl14 R2ABlueCtbl15						no no
R2ABlueCtbl16						no
R2ABlueCtbl17						no
R2ABlueCtbl18						no
R2ABlueCtbl19						no
R2ABlueCtbl20						no
R2ABlueCtbl21						no
R2ABlueCtbl22						no
R2ABlueCtbl23						no
R2ABlueCtbl24						no

	 ExifTool	13.24	Tag	Names	
R2ABlueCtbl25					no
R2ABlueCtbl26					no
R2ABlueCtbl27					no
R2ABlueCtbl28					no
R2ABlueCtbl29					no
R2ABlueCtbl30					no
R2ABlueCtbl31					no
R2ABlueStbl00					no
R2ABlueStbl01					no
R2ABlueStbl02					no
R2ABlueStbl03					no
R2ABlueStbl04					no
R2ABlueStbl05					no
R2ABlueStb106					no
R2ABlueStbl07					no
R2ABlueStbl08					no
R2ABlueStb109					no
R2ABlueStbl10					no
R2ABlueStbl11					no
R2ABlueStbl12					no
R2ABlueStbl13					no
R2ABlueStbl14					no
R2ABlueStbl15					no
R2ABlueStbl16					no
R2ABlueStbl17					no
R2ABlueStbl18					no
R2ABlueStbl19					no
R2ABlueStbl20					no
R2ABlueStbl21					no
R2ABlueStbl22					no
R2ABlueStbl23					no
R2ABlueStbl24					no
R2ABlueStbl25					no
R2ABlueStbl26					no
R2ABlueStbl27					no
R2ABlueStbl28					no
R2ABlueStbl29					no
R2ABlueStbl30					no
R2ABlueStbl31					no
R2ACx					no
R2ACy					no
R2AGreenCtbl00					no
R2AGreenCtbl01					no
R2AGreenCtbl02					no
R2AGreenCtbl03					no
R2AGreenCtbl04					no
R2AGreenCtbl05					no
R2AGreenCtbl06					no
R2AGreenCtbl07					no
R2AGreenCtbl08					no
R2AGreenCtbl09					no
R2AGreenCtbl10					no
R2AGreenCtbl11					no
R2AGreenCtbl12					no
R2AGreenCtbl13					no
R2AGreenCtbl14					no
R2AGreenCtbl15					no
R2AGreenCtbl16					no
R2AGreenCtbl17					no
R2AGreenCtbl18					no
R2AGreenCtbl19					no
R2AGreenCtbl20					no
R2AGreenCtbl21					no
R2AGreenCtbl22					no
R2AGreenCtbl23					no
R2AGreenCtbl24					no
R2AGreenCtbl25					no
R2AGreenCtbl26					no
R2AGreenCtbl27					no
R2AGreenCtbl28					no

	 ExifTool	13.24	Tag	Names	
R2AGreenCtbl29					no
R2AGreenCtbl30					no
R2AGreenCtbl31					no
R2AGreenStbl00					no
R2AGreenStbl01					no
R2AGreenStbl02					no
R2AGreenStbl03					no
R2AGreenStbl04					no
R2AGreenStbl05					no
R2AGreenStbl06					no
R2AGreenStbl07					no
R2AGreenStbl08					no
R2AGreenStbl09					no
R2AGreenStbl10					no
R2AGreenStbl11					no
R2AGreenStbl12					no
R2AGreenStbl13					no
R2AGreenStbl14					no
R2AGreenStbl15					no
R2AGreenStbl16					no
R2AGreenStbl17					no
R2AGreenStbl18					no
R2AGreenStbl19					no
R2AGreenStbl20					no
R2AGreenStbl21					no
R2AGreenStbl22					no
R2AGreenStbl23					no
R2AGreenStbl24					no
R2AGreenStbl25					no
R2AGreenStbl26					no
R2AGreenStbl27					no
R2AGreenStbl28					no
R2AGreenStbl29					no
R2AGreenStbl30					no
R2AGreenStbl31					no
R2AHeight					no
R2AIntervals					no
R2ARedCtbl00					no
R2ARedCtbl01					no
R2ARedCtbl02					no
R2ARedCtbl03					no
R2ARedCtbl04					no
R2ARedCtbl05					no
R2ARedCtbl06					no
R2ARedCtbl07					no
R2ARedCtbl08					no
R2ARedCtbl09					no
R2ARedCtbl10					no
R2ARedCtbl11					no
R2ARedCtbl12					no
R2ARedCtbl13					no
R2ARedCtbl14					no
R2ARedCtbl15					no
R2ARedCtbl16					no
R2ARedCtbl17					no
R2ARedCtbl18					no
R2ARedCtbl19					no
R2ARedCtbl20					no
R2ARedCtbl21					no
R2ARedCtbl22					no
R2ARedCtbl23					no
R2ARedCtbl24					no
R2ARedCtbl25					no
R2ARedCtbl26					no
R2ARedCtbl27					no
R2ARedCtbl28					no
R2ARedCtbl29					no
R2ARedCtbl30					no
R2ARedCtbl31					no
R2ARedStbl00					no

	 ExifTool	13.24	Tag	Names	
R2ARedStbl01					no
R2ARedStbl02					no
R2ARedStbl03					no
R2ARedStbl04 R2ARedStbl05					no no
R2ARedStb105					no
R2ARedStb107					no
R2ARedStbl08					no
R2ARedStbl09					no
R2ARedStbl10					no
R2ARedStbl11					no
R2ARedStbl12 R2ARedStbl13					no
R2ARedStb113					no no
R2ARedStbl15					no
R2ARedStbl16					no
R2ARedStbl17					no
R2ARedStbl18					no
R2ARedStbl19					no
R2ARedStbl20 R2ARedStbl21					no
R2ARedStb121 R2ARedStb122					no no
R2ARedStb123					no
R2ARedStbl24					no
R2ARedStbl25					no
R2ARedStbl26					no
R2ARedStbl27					no
R2ARedStbl28					no
R2ARedStbl29 R2ARedStbl30					no no
R2ARedStb130					no
R2ATb100					no
R2ATbl01					no
R2ATbl02					no
R2ATb103					no
R2ATb104					no
R2ATb105 R2ATb106					no
R2ATb100 R2ATb107					no no
R2ATb108					no
R2ATbl09					no
R2ATbl10					no
R2ATbl11					no
R2ATbl12					no
R2ATbl13 R2ATbl14					no
R2ATb114 R2ATb115					no no
R2ATbl16					no
R2ATbl17					no
R2ATbl18					no
R2ATbl19					no
R2ATb120					no
R2ATb121					no
R2ATb122 R2ATb123					no
R2ATb123					no no
R2ATb125					no
R2ATb126					no
R2ATbl27					no
R2ATb128					no
R2ATb129					no
R2ATbl30					no
R2ATbl31 R2AWidth					no no
R2D65BlueCtbl00					no
R2D65BlueCtbl01					no
R2D65BlueCtbl02					no
R2D65BlueCtbl03					no
R2D65BlueCtbl04					no
R2D65BlueCtbl05					no

		ExifTool	13.24	Tag	Names	
R2D65BlueCtbl06						no
R2D65BlueCtbl07						no
R2D65BlueCtbl08						no
R2D65BlueCtbl09						no
R2D65BlueCtbl10						no
R2D65BlueCtbl11						no
R2D65BlueCtbl12						no
R2D65BlueCtbl13						no
R2D65BlueCtbl14						no
R2D65BlueCtbl15						no
R2D65BlueCtbl16						no
R2D65BlueCtbl17						no
R2D65BlueCtbl18						no
R2D65BlueCtbl19						no
R2D65BlueCtbl20						no
R2D65BlueCtbl21						no
R2D65BlueCtbl22						no
R2D65BlueCtbl23						no
R2D65BlueCtbl24						no
R2D65BlueCtbl25						no
R2D65BlueCtbl26						no
R2D65BlueCtbl27						no
R2D65BlueCtbl28						no
R2D65BlueCtbl29						no
R2D65BlueCtbl30						no
R2D65BlueCtbl31						no
R2D65BlueStbl00						no
R2D65BlueStbl01						no
R2D65BlueStbl02						no
R2D65BlueStbl03						no
R2D65BlueStbl04						no
R2D65BlueStbl05						no
R2D65BlueStbl06						no
R2D65BlueStbl07						no
R2D65BlueStbl08						no
R2D65BlueStbl09						no
R2D65BlueStbl10						no
R2D65BlueStbl11						no
R2D65BlueStbl12						no
R2D65BlueStbl13						no
R2D65BlueStbl14						no
R2D65BlueStbl15						no
R2D65BlueStbl16						no
R2D65BlueStbl17						no
R2D65BlueStbl18						no
R2D65BlueStbl19						no
R2D65BlueStbl20						no
R2D65BlueStbl21						no
R2D65BlueStbl22						no
R2D65BlueStbl23						no
R2D65BlueStbl24						no
R2D65BlueStbl25						no
R2D65BlueStbl26						no
R2D65BlueStbl27						no
R2D65BlueStbl28						no
R2D65BlueStbl29						no
R2D65BlueStbl30						no
R2D65BlueStbl31						no
R2D65Cx						no
R2D65Cy	_					no
R2D65GreenCtbl00						no
R2D65GreenCtbl03						no
R2D65GreenCtbl02						no
R2D65GreenCtbl03						no
R2D65GreenCtbl04						no
R2D65GreenCtbl0						no
R2D65GreenCtbl06						no
R2D65GreenCtbl0						no
R2D65GreenCtbl08						no
R2D65GreenCtbl09	9					no

	EXILIOOI	13.24	Tag	Names	
R2D65GreenCtbl10					no
R2D65GreenCtbl11					
					no
R2D65GreenCtbl12					no
R2D65GreenCtbl13					no
R2D65GreenCtbl14					no
R2D65GreenCtbl15					no
R2D65GreenCtbl16					
					no
R2D65GreenCtbl17					no
R2D65GreenCtbl18					no
R2D65GreenCtbl19					no
R2D65GreenCtbl20					no
R2D65GreenCtbl21					no
R2D65GreenCtbl22					
					no
R2D65GreenCtbl23					no
R2D65GreenCtbl24					no
R2D65GreenCtbl25					no
R2D65GreenCtbl26					no
R2D65GreenCtbl27					no
R2D65GreenCtbl28					
					no
R2D65GreenCtbl29					no
R2D65GreenCtbl30					no
R2D65GreenCtbl31					no
R2D65GreenStbl00					no
R2D65GreenStbl01					no
R2D65GreenStb102					no
R2D65GreenStbl03					no
R2D65GreenStbl04					no
R2D65GreenStbl05					no
R2D65GreenStbl06					no
R2D65GreenStbl07					no
R2D65GreenStbl08					no
R2D65GreenStb109					
					no
R2D65GreenStbl10					no
R2D65GreenStbl11					no
R2D65GreenStbl12					no
R2D65GreenStbl13					no
R2D65GreenStbl14					no
R2D65GreenStbl15					no
R2D65GreenStbl16					no
R2D65GreenStbl17					no
R2D65GreenStbl18					no
R2D65GreenStbl19					no
R2D65GreenStbl20					no
R2D65GreenStbl21					no
R2D65GreenStbl22					
					no
R2D65GreenStbl23					no
R2D65GreenStbl24					no
R2D65GreenStbl25					no
R2D65GreenStbl26					no
R2D65GreenStbl27					no
R2D65GreenStbl28					no
R2D65GreenStb129					
					no
R2D65GreenStbl30					no
R2D65GreenStbl31					no
R2D65Height					no
R2D65Intervals					no
R2D65RedCtbl00					no
R2D65RedCtbl01					
					no
R2D65RedCtbl02					no
R2D65RedCtbl03					no
R2D65RedCtbl04					no
R2D65RedCtbl05					no
R2D65RedCtbl06					no
R2D65RedCtbl07					no
R2D65RedCtbl08					
					no
R2D65RedCtbl09					no
R2D65RedCtbl10					no
R2D65RedCtbl11					no
R2D65RedCtbl12					no
R2D65RedCtbl13					no

	 ExifTool	13.24	Tag	Names	
R2D65RedCtbl14					no
R2D65RedCtbl15					no
R2D65RedCtbl16					no
R2D65RedCtbl17					no
R2D65RedCtbl18					no
R2D65RedCtbl19					no
R2D65RedCtbl20					no
R2D65RedCtbl21					no
R2D65RedCtbl22					no
R2D65RedCtbl23					no
R2D65RedCtbl24					no
R2D65RedCtbl25					no
R2D65RedCtbl26					no
R2D65RedCtbl27					no
R2D65RedCtbl28					no
R2D65RedCtbl29					no
R2D65RedCtbl30					no
R2D65RedCtbl31					no
R2D65RedStb100					no
R2D65RedStb101					no
R2D65RedStb102					no
R2D65RedStb103					no
R2D65RedStb104					no
R2D65RedStb105					no
R2D65RedStb106					no
R2D65RedStb107					no
R2D65RedStb107					no
R2D65RedStb109					no
R2D65RedStb110					no
R2D65RedStb111					no
R2D65RedStbl12					no
R2D65RedStbl13					no
R2D65RedStbl14					no
R2D65RedStbl15					no
R2D65RedStbl16					no
R2D65RedStb117					no
R2D65RedStb117					no
R2D65RedStbl19					no
R2D65RedStb120					no
R2D65RedStbl21					no
R2D65RedStb122					no
R2D65RedStb123					no
R2D65RedStb124					no
R2D65RedStb125					no
R2D65RedStb126					no
R2D65RedStb127					no
R2D65RedStb128					no
R2D65RedStb129					no
R2D65RedStb129					no
R2D65RedStb130					no
R2D65Tb100					no
R2D65Tb100					no
R2D65Tb101					no
R2D65Tb102					no
R2D65Tb103					no
R2D65Tb104					no
R2D65Tb105					
R2D65Tb107					no no
R2D65Tb107					
R2D65Tb106					no
R2D65Tb109					no
R2D65Tb110 R2D65Tb111					no
R2D65Tb111 R2D65Tb112					no
R2D65Tb112 R2D65Tb113					no
					no
R2D65Tbl14 R2D65Tbl15					no
					no
R2D65Tbl16					no
R2D65Tbl17					no
R2D65Tbl18 R2D65Tbl19					no
Y\\\\\\\\\\\\\\\\\\\\\\\\\\\\\\\\\\\\					no

		ExifTool	13.24	Tag	Names	
R2D65Tbl20						no
R2D65Tb121						no
R2D65Tb122						no
R2D65Tb123						no
R2D65Tb124						no
R2D65Tb125						no
R2D65Tb126						no
R2D65Tb127						no
R2D65Tb128						no
R2D65Tbl29						no
R2D65Tbl30						no
R2D65Tbl31						no
R2D65Width						no
R2TL84BlueCtbl00	)					no
R2TL84BlueCtbl03						no
R2TL84BlueCtbl02	2					no
R2TL84BlueCtbl03	3					no
R2TL84BlueCtbl04						no
R2TL84BlueCtbl0						no
R2TL84BlueCtbl06						no
R2TL84BlueCtbl0						no
R2TL84BlueCtbl08						no
R2TL84BlueCtbl09						no
R2TL84BlueCtbl1(	-					no
R2TL84BlueCtbl11						no
R2TL84BlueCtbl12						no
R2TL84BlueCtbl1						no
R2TL84BlueCtbl14						no
R2TL84BlueCtbl1						no
R2TL84BlueCtbl16R2TL84BlueCtbl1						no
R2TL84BlueCtbl1						no
R2TL84BlueCtbl19						no
R2TL84BlueCtbl1						no no
R2TL84BlueCtbl2						no
R2TL84BlueCtbl2						no
R2TL84BlueCtbl23						no
R2TL84BlueCtbl2						no
R2TL84BlueCtbl2						no
R2TL84BlueCtbl26						no
R2TL84BlueCtbl2	7					no
R2TL84BlueCtbl28	3					no
R2TL84BlueCtbl29	9					no
R2TL84BlueCtbl30	)					no
R2TL84BlueCtbl33	L					no
R2TL84BlueStbl00	)					no
R2TL84BlueStbl03	L					no
R2TL84BlueStbl02						no
R2TL84BlueStbl03						no
R2TL84BlueStbl04						no
R2TL84BlueStbl0						no
R2TL84BlueStbl06						no
R2TL84BlueStbl0						no
R2TL84BlueStbl08						no
R2TL84BlueStbl09						no
R2TL84BlueStbl10 R2TL84BlueStbl11						no
R2TL84BlueStb11						no
R2TL84BlueStbl13						no no
R2TL84BlueStbl1						no
R2TL84BlueStbl1						no
R2TL84BlueStbl16						no
R2TL84BlueStbl1						no
R2TL84BlueStbl18						no
R2TL84BlueStbl19						no
R2TL84BlueStbl2						no
R2TL84BlueStbl2						no
R2TL84BlueStbl22						no
R2TL84BlueStbl23	3					no
R2TL84BlueStbl24	4					no

	ExifTool	13.24	Tag	Names	
R2TL84BlueStbl25					no
R2TL84BlueStbl26					no
R2TL84BlueStbl27					no
R2TL84BlueStbl28					no
R2TL84BlueStbl29					no
R2TL84BlueStbl30					no
R2TL84BlueStbl31					no
R2TL84Cx					no
R2TL84Cy					no
R2TL84GreenCtbl00					no
R2TL84GreenCtbl01					no
R2TL84GreenCtbl02					no
R2TL84GreenCtbl03					no
R2TL84GreenCtbl04 R2TL84GreenCtbl05					no
R2TL84GreenCtbl06					no no
R2TL84GreenCtbl07					no
R2TL84GreenCtbl08					no
R2TL84GreenCtbl09					no
R2TL84GreenCtbl10					no
R2TL84GreenCtbl11					no
R2TL84GreenCtbl12					no
R2TL84GreenCtbl13					no
R2TL84GreenCtbl14					no
R2TL84GreenCtbl15					no
R2TL84GreenCtbl16					no
R2TL84GreenCtbl17					no
R2TL84GreenCtbl18					no
R2TL84GreenCtbl19					no
R2TL84GreenCtbl20 R2TL84GreenCtbl21					no no
R2TL84GreenCtbl22					no
R2TL84GreenCtbl23					no
R2TL84GreenCtbl24					no
R2TL84GreenCtbl25					no
R2TL84GreenCtbl26					no
R2TL84GreenCtbl27					no
R2TL84GreenCtbl28					no
R2TL84GreenCtbl29					no
R2TL84GreenCtbl30					no
R2TL84GreenCtbl31					no
R2TL84GreenStbl00					no
R2TL84GreenStbl01 R2TL84GreenStbl02					no
R2TL84GreenStb103					no no
R2TL84GreenStb104					no
R2TL84GreenStbl05					no
R2TL84GreenStbl06					no
R2TL84GreenStbl07					no
R2TL84GreenStbl08					no
R2TL84GreenStbl09					no
R2TL84GreenStbl10					no
R2TL84GreenStbl11					no
R2TL84GreenStbl12					no
R2TL84GreenStbl13					no
R2TL84GreenStbl14					no
R2TL84GreenStbl15 R2TL84GreenStbl16					no no
R2TL84GreenStbl17					no
R2TL84GreenStbl18					no
R2TL84GreenStbl19					no
R2TL84GreenStbl20					no
R2TL84GreenStbl21					no
R2TL84GreenStbl22					no
R2TL84GreenStbl23					no
R2TL84GreenStbl24					no
R2TL84GreenStbl25					no
R2TL84GreenStbl26					no
R2TL84GreenStbl27					no
R2TL84GreenStbl28					no

	EXILIOOI	13.24	Tag	Names	
R2TL84GreenStbl29					no
R2TL84GreenStbl30					no
R2TL84GreenStbl31					no
R2TL84Height					no
R2TL84Intervals					
					no
R2TL84RedCtbl00					no
R2TL84RedCtbl01					no
R2TL84RedCtbl02					no
R2TL84RedCtbl03					no
R2TL84RedCtbl04					no
R2TL84RedCtbl05					no
R2TL84RedCtbl06					no
R2TL84RedCtbl07					no
R2TL84RedCtbl08					no
R2TL84RedCtbl09					no
R2TL84RedCtbl10					no
R2TL84RedCtbl11					
					no
R2TL84RedCtbl12					no
R2TL84RedCtbl13					no
R2TL84RedCtbl14					no
R2TL84RedCtbl15					no
R2TL84RedCtbl16					no
R2TL84RedCtbl17					no
R2TL84RedCtbl18					no
R2TL84RedCtbl19					no
R2TL84RedCtbl20					no
R2TL84RedCtbl21					no
R2TL84RedCtbl22					no
R2TL84RedCtbl23					
					no
R2TL84RedCtbl24					no
R2TL84RedCtbl25					no
R2TL84RedCtbl26					no
R2TL84RedCtbl27					no
R2TL84RedCtbl28					no
R2TL84RedCtbl29					no
R2TL84RedCtbl30					no
R2TL84RedCtbl31					no
R2TL84RedStbl00					no
R2TL84RedStbl01					no
R2TL84RedStb102					no
R2TL84RedStb103					no
R2TL84RedStb104					no
R2TL84RedStb105					no
R2TL84RedStbl06					no
R2TL84RedStbl07					no
R2TL84RedStbl08					no
R2TL84RedStbl09					no
R2TL84RedStbl10					no
R2TL84RedStbl11					no
R2TL84RedStbl12					no
R2TL84RedStbl13					no
R2TL84RedStbl14					no
R2TL84RedStbl15					no
R2TL84RedStb115					no
R2TL84RedStb117					
					no
R2TL84RedStbl18					no
R2TL84RedStbl19					no
R2TL84RedStbl20					no
R2TL84RedStbl21					no
R2TL84RedStbl22					no
R2TL84RedStbl23					no
R2TL84RedStbl24					no
R2TL84RedStbl25					no
R2TL84RedStb126					no
R2TL84RedStb127					no
R2TL84RedStb127					
					no
R2TL84RedStbl29					no
R2TL84RedStbl30					no
R2TL84RedStbl31					no
R2TL84Tbl00					no

		ExifTool	13.24	Tag	Names	
R2TL84Tbl01						no
R2TL84Tbl02						no
R2TL84Tb103						no
R2TL84Tbl04 R2TL84Tbl05						no no
R2TL84Tb105						no
R2TL84Tb107						no
R2TL84Tbl08						no
R2TL84Tbl09						no
R2TL84Tbl10						no
R2TL84Tbl11 R2TL84Tbl12						no
R2TL84Tb112						no no
R2TL84Tbl14						no
R2TL84Tbl15						no
R2TL84Tbl16						no
R2TL84Tbl17						no
R2TL84Tbl18						no
R2TL84Tbl19 R2TL84Tbl20						no no
R2TL84Tbl21						no
R2TL84Tb122						no
R2TL84Tbl23						no
R2TL84Tbl24						no
R2TL84Tb125						no
R2TL84Tbl26 R2TL84Tbl27						no no
R2TL84Tb127						no
R2TL84Tb129						no
R2TL84Tbl30						no
R2TL84Tbl31						no
R2TL84Width						no
RolloffEnable SensorFmt						no no
SensorType						no
SensrFulHght						no
SensrFulWdth						no
SensrQtrHght						no
SensrQtrWdth						no
SnapshotResol TL84ConvChrmA M						no no
TL84ConvChrmA P						no
TL84ConvChrmB_M						no
TL84ConvChrmB_P						no
TL84ConvChrmC_M						no
TL84ConvChrmC_P						no
TL84ConvChrmD_M TL84ConvChrmD P						no
TL84ConvChrmKCb						no no
TL84ConvChrmKCr						no
TL84ConvLumaK						no
TL84ConvLumaV0						no
TL84ConvLumaV1						no
TL84ConvLumaV2						no
VideoFps YhiYloConvChrmA	М					no no
YhiYloConvChrmA	_					no
YhiYloConvChrmB						no
YhiYloConvChrmB	_					no
YhiYloConvChrmC	_					no
YhiYloConvChrmC	_					no
YhiYloConvChrmD YhiYloConvChrmD	_					no no
YhiYloConvChrmK	_					no
YhiYloConvChrmK						no
YhiYloConvLumaK						no
YhiYloConvLumaV						no
YhiYloConvLumaV						no
YhiYloConvLumaV YhiYloCorC0	۷					no
1111 1 1 OCOT CO						no

YhiYloCorCl	no
YhiYloCorC2	no
YhiYloCorC3	no
YhiYloCorC4	no
YhiYloCorC5	no
YhiYloCorC6	no
YhiYloCorC7	no
YhiYloCorC8	no
YhiYloCorK0	no
YhiYloCorK1	no
YhiYloCorK2	no

#### Qualcomm DualCamera Tags

Found in JPEG APP4 "Qualcomm Dual Camera Attributes" written by some Nokia phones.

Tag Name	Writable
AF_ROIHeight	no
AF_ROILeft	no
AF ROITop	no
AF ROIWidth	no
CAMIFCropHeight	no
CAMIFCropLeft	no
CAMIFCropTop	no
CAMIFCropWidth	no
CAMIF_ROIMapHeight	no
CAMIF_ROIMapLeft	no
CAMIF_ROIMapTop	no
CAMIF_ROIMapWidth	no
CPPCropHeight	no
CPPCropLeft	no
CPPCropTop	no
CPPCropWidth	no
CPP_ROIMapHeight	no
CPP_ROIMapLeft	no
CPP_ROIMapTop	no
CPP_ROIMapWidth	no
${\tt CurrentPipelineMirrorFlipSetting}$	no
CurrentPipelineRotationSetting	no
DDMCropHeight	no
DDMCropLeft	no
DDMCropTop	no
DDMCropWidth	no
FocalLengthRatio	no
ISPCropHeight	no
ISPCropLeft	no
ISPCropTop	no
ISPCropWidth	no
ISP_ROIMapHeight	no
ISP_ROIMapLeft	no
ISP_ROIMapTop	no
ISP_ROIMapWidth	no
SensorCropHeight	no
SensorCropLeft	no
SensorCropTop	no
SensorCropWidth	no
SensorROIMapHeight	no
SensorROIMapLeft	no
SensorROIMapTop	no
SensorROIMapWidth	no

## Jpeg2000 Tags

The tags below are found in JPEG 2000 images and the C2PA CAI JUMBF metadata in various file types (see below). Note that ExifTool currently writes only EXIF, IPTC and XMP tags in Jpeg2000 images, and EXIF and XMP in JXL images. ExifTool will read/write Brotli-compressed EXIF and XMP in JXL images, but the API Compress option must be set to create new EXIF and XMP in compressed format.

C2PA (Coalition for Content Provenance and Authenticity) CAI (Content Authenticity Initiative) JUMBF (JPEG Universal Metadata Box Format) metdata is currently extracted from JPEG, PNG, TIFF-based (eg. TIFF, DNG), QuickTime-based (eg. MP4, MOV, HEIF, AVIF), RIFF-based (eg. WAV, AVI, WebP), PDF, SVG and GIF files, and ID3v2 metadata. The suggested ExifTool command-line arguments for reading C2PA metadata are "-jumbf:all -G3 -b -j -u -struct". This metadata may be deleted from writable JPEG, PNG, WebP, TIFF-based, and QuickTime-based files by deleting the JUMBF group with "-jumbf:all=". The C2PA JUMBF metadata may be extracted as a block via the JUMBF tag. See <a href="https://c2pa.org/specifications/">https://c2pa.org/specifications/</a> for the C2PA specification.

Tag ID	Tag Name	Writable	
'Exif'	EXIF	EXIF	
'asoc'	Association	Jpeg2000	
'bfdb'	BinaryDataType	no	
'bfil'	BinaryFilter	no	
'bidb'	BinaryData	no	
'bpcc'	BitsPerComponent	no	
'brob'	BrotliXMP	XMP	
	BrotliEXIF	EXIF	
	BrotliJUMB	Jpeg2000	
'c2sh'	C2PASaltHash	no	
'cbor'	CBORData	CBOR	
'cdef'	ComponentDefinition	no	
'cgrp'	ColorGroup	no	
'chck'	DigitalSignature	no	
'cmap'	ComponentMapping	no	
'colr'	ColorSpecification	Jpeg2000	ColorSpec
'comp'	Composition	no	
'copt'	CompositionOptions	no	
'cref'	Cross-Reference	no	
'creg'	CodestreamRegistration	no	
'drep'	DesiredReproductions	no	
'dtbl'	DataReference	no	
'flst'	FragmentList	no	
'free'	Free	no	
'ftbl'	FragmentTable	no	
'ftyp'	FileType	Jpeg2000	FileType
'gtso'	GraphicsTechnologyStandardOutput	no	
'hrgm'	GainMapImage	no	
'ihdr'	ImageHeader	Jpeg2000	ImageHeader
'inst'	InstructionSet	no	
'jP '	JP2Signature	no	
'jp2c'	ContiguousCodestream	no	
	PreviewImage	no	
'jp2h'	JP2Header	Jpeg2000	
'jp2i'	IntellectualProperty	XMP	
'jpch'	CodestreamHeader	Jpeg2000	
'jplh'	CompositingLayerHeader	Jpeg2000	
'json'	JSONData	JSON	
'jumb'	JUMBFBox	Jpeg2000	TT 100
'jumd'	JUMBFDescr	Jpeg2000	JUMD
'jxlc'	JXLCodestream	no	
'jxlp'	PartialJXLCodestream	no	
'lbl '	Label	no	
'mdat'	MediaData	no	
'mp7b' 'nlst'	MPEG7Binary NumberList	no	
'opct'	Opacity	no	
'pclr'	Palette	no	
'prfl'	Profile	no no	
'res '	Resolution	Jpeg2000	
'resc'	CaptureResolution		CaptureResolution
'resd'	DisplayResolution		DisplayResolution
'roid'	ROIDescription	no	PIDPIGINGBOIGGIOII
'rreq'	ReaderRequirements	no	
'uinf'	UUIDInfo	Jpeg2000	
V		-F-051000	

'ulst'	UUIDList	no
'url '	URL	no
'uuid'	UUID-EXIF	EXIF
	UUID-EXIF2	EXIF
	UUID-EXIF_bad	EXIF
	UUID-IPTC	IPTC
	UUID-IPTC2	IPTC
	UUID-XMP	XMP
	UUID-GeoJP2	EXIF
	UUID-Photoshop	Photoshop
	UUID-C2PAClaimSignature	CBOR
	UUID-Signature	no
	UUID-Unknown	no
'xml '	XML	XMP XML
	XMP	_
		XMP

### Jpeg2000 ColorSpec Tags

The table below contains tags in the color specification (colr) box. This box may be rewritten by writing either ICC\_Profile, ColorSpace or ColorSpecData. When writing, any existing colr boxes are replaced with the newly created colr box.

NOTE: Care must be taken when writing this color specification because writing a specification that is incompatible with the image data may make the image undisplayable.

Index1	Tag Name	Writable
0	ColorSpecMethod	int8s!
1	ColorSpecPrecedence	int8s!
2	ColorSpecApproximation	int8s!
3	ICC_Profile	ICC_Profile
	ColorSpace	int32u!
	ColorSpecData	undef[\$size-3]!

# <u>Jpeg2000 FileType Tags</u>

Index4	Tag Name	Writable
0	MajorBrand	no
1	MinorVersion	no
2	CompatibleBrands	no+

#### <u>Jpeq2000</u> <u>ImageHeader</u> <u>Tags</u>

Index1	Tag Name	Writable
0	ImageHeight	no
4	ImageWidth	no
8	NumberOfComponents	no
10	BitsPerComponent	no
11	Compression	no

### Jpeg2000 JUMD Tags

Information extracted from the  ${\tt JUMBF}$  description box.

Tag ID	Tag Name	Writable
'id'	JUMDID	no
'label'	JUMDLabel	no
'sig'	JUMDSignature	no
'toggles'	JUMDToggles?	no
'type'	JUMDType	no

### Jpeg2000 CaptureResolution Tags

Index1 Tag Name

Writable

CaptureYResolution	no
CaptureXResolution	no
CaptureYResolutionUnit	no
CaptureXResolutionUnit	no
	CaptureXResolution CaptureYResolutionUnit

### Jpeg2000 DisplayResolution Tags

Index1	Tag Name	Writable
0	DisplayYResolution	no
4	DisplayXResolution	no
8	DisplayYResolutionUnit	no
9	DisplayXResolutionUnit	no

#### APP12 Tags

### APP12 PictureInfo Tags

The JPEG APP12 "Picture Info" segment was used by some older cameras, and contains ASCII-based meta information. Below are some tags which have been observed Agfa and Polaroid images, however ExifTool will extract information from any tags found in this segment.

Tag ID	Tag Name	Writable
' 'Aperture'	Aperture	no
'ColorMode'	ColorMode	no
'ContTake'	ContTake	no
'ExpBias'	ExposureCompensation	no
'FNumber'	FNumber	no
'FWare'	FirmwareVersion	no
'Flash'	Flash	no
'FocusMode'	FocusMode	no
'FocusPos'	FocusPos	no
'ID'	ID	no
'ImageSize'	ImageSize	no
'LightS'	LightS	no
'Macro'	Macro	no
'Protect'	Protect	no
'Quality'	Quality	no
'Resolution'	Resolution	no
'Serial#'	SerialNumber	no
'Shutter'	ExposureTime	no
'StrobeTime'	StrobeTime	no
'TimeDate'	DateTimeOriginal	no
'Type'	CameraType	no
'Version'	Version	no
'Ytarget'	YTarget	no
'Zoom'	Zoom	no
'ZoomPos'	ZoomPos	no
'shtr'	ExposureTime	no
'ylevel'	YLevel	no

## APP12 Ducky Tags

Photoshop uses the JPEG APP12 "Ducky" segment to store some information in "Save for Web" images.

Tag Name	Writable
Quality	int32u/
Comment	string/
Copyright	string/
	Quality Comment

### AFCP Tags

AFCP stands for AXS File Concatenation Protocol, and is a poorly designed protocol for appending information to the end of files. This can be used as an auxiliary technique to store IPTC information in images, but is incompatible with some file formats.

ExifTool will read and write (but not create) AFCP IPTC information in  $\mbox{\tt JPEG}$  and  $\mbox{\tt TIFF}$  images.

See

for the AFCP specification.

Tag ID	Tag Name	Writable
'IPTC'	IPTC	IPTC
'Nail'	ThumbnailImage	no
'PrVw'	PreviewImage	no
'TEXT'	Text	no

## DarwinCore Tags

Tags defined in the Darwin Core (dwc) XMP namespace. See <a href="http://rs.tdwg.org/dwc/index.htm">http://rs.tdwg.org/dwc/index.htm</a> for the official specification.

These tags belong to the ExifTool XMP-dwc family 1 group.

Tag Name	Writable
DCTermsLocation	DarwinCore DCTermsLocation Struct
DCContinent	string_
DCCoordinatePrecision	string_
DCCoordinateUncertaintyInMeters	string_
DCCountry	string_
DCCountryCode	string_
DCCounty	string
DCDecimalLatitude	string
DCDecimalLongitude	string_
DCFootprintSpatialFit	string
DCFootprintSRS	string
DCFootprintWKT	string
DCGeodeticDatum	string
DCGeoreferencedBy	string_
DCGeoreferencedDate	string_
DCGeoreferenceProtocol	string_
DCGeoreferenceRemarks	string_
DCGeoreferenceSources	string
DCGeoreferenceVerificationStatus	string
DCHigherGeography	string_
DCHigherGeographyID	string
DCIsland	string_
DCIslandGroup	string
DCLocality	string
DCLocationAccordingTo	string
DCLocationID	string
DCLocationRemarks	string_
DCMaximumDepthInMeters	string
DCMaximumDistanceAboveSurfaceInMeters	string_
DCMaximumElevationInMeters	string_ string
DCMinimumDepthInMeters	string_ string_
DCMinimumDistanceAboveSurfaceInMeters	string_ string_
DCMinimumElevationInMeters	
	string_
DCMunicipality DCDointRadiusCratialFit	string_
DCPointRadiusSpatialFit	string_
DCStateProvince DCVerbatimCoordinates	string_
	string_
DCVerbatimCoordinateSystem	string_
DCVerbatimDepth	string_
DCVerbatimElevation	string_
DCVerbatimLatitude	string_
DCVerbatimLocality	string_
DCVerbatimLongitude	string_
DCVerbatimSRS	string_
DCVerticalDatum	string_
DCWaterBody	string_
DCEvent	DarwinCore Event Struct

```
EventDay
                                              integer_
EventEarliestDate
                                              date_
EventEndDayOfYear
                                              integer_
EventDate
                                              date
EventID
                                              string/
EventRemarks
                                              lang-alt_
EventTime
                                              string_
EventFieldNotes
                                              string
EventFieldNumber
                                              string_
EventHabitat
                                              string_
EventLatestDate
                                              date_
EventMonth
                                              integer_
EventParentEventID
                                              string_
EventSampleSizeUnit
                                              string_
EventSampleSizeValue
                                              string_
EventSamplingEffort
                                              string_
EventSamplingProtocol
                                              string
EventStartDayOfYear
                                              integer_
EventVerbatimEventDate
                                              string_
EventYear
                                              integer_
FossilSpecimen
                                              DarwinCore MaterialSample Struct
FossilSpecimenMaterialSampleID
                                             DarwinCore GeologicalContext Struct
GeologicalContext
GeologicalContextBed
                                              string
EarliestAgeOrLowestStage
                                              string
                                              string
EarliestEonOrLowestEonothem
EarliestEpochOrLowestSeries
                                              strina
EarliestEraOrLowestErathem
                                              string
EarliestPeriodOrLowestSystem
                                              string
GeologicalContextFormation
                                              string
GeologicalContextID
                                              string
GeologicalContextGroup
                                              strina
HighestBiostratigraphicZone
                                              strina
LatestAgeOrHighestStage
                                              string
LatestEonOrHighestEonothem
                                              string
LatestEpochOrHighestSeries
                                              string
LatestEraOrHighestErathem
                                              string_
LatestPeriodOrHighestSystem
                                              string
LithostratigraphicTerms
                                              string
LowestBiostratigraphicZone
                                              string_
GeologicalContextMember
                                              string
HumanObservation
                                              DarwinCore Event Struct
                                              integer_
HumanObservationDay
HumanObservationEarliestDate
                                              date
HumanObservationEndDayOfYear
                                              integer
                                              date_
HumanObservationEventDate
HumanObservationEventID
                                              string/
HumanObservationEventRemarks
                                              lang-alt
HumanObservationEventTime
                                              string_
HumanObservationFieldNotes
                                              string
HumanObservationFieldNumber
                                              string
HumanObservationHabitat
                                              string
HumanObservationLatestDate
                                              date
HumanObservationMonth
                                              integer
HumanObservationParentEventID
                                             string
HumanObservationSampleSizeUnit
                                             string
HumanObservationSampleSizeValue
                                             string
HumanObservationSamplingEffort
                                             string
HumanObservationSamplingProtocol
                                              strina
HumanObservationStartDayOfYear
                                              integer
{\tt HumanObservationVerbatimEventDate}
                                              string_
HumanObservationYear
                                              integer_
Identification
                                              DarwinCore Identification Struct
DateIdentified
                                              date_
IdentificationID
                                              string_
IdentificationQualifier
                                              string_
IdentificationReferences
                                              string_
IdentificationRemarks
                                              string_
IdentificationVerificationStatus
                                              string
```

string\_

IdentifiedBy

```
IdentifiedByID
                                              string_
TypeStatus
                                              string
VerbatimIdentification
                                              string_
LivingSpecimen
                                              DarwinCore MaterialSample Struct
LivingSpecimenMaterialSampleID
                                              string
                                              DarwinCore Event Struct
MachineObservation
MachineObservationDay
                                              integer_
MachineObservationEarliestDate
                                              date
MachineObservationEndDayOfYear
                                              integer_
MachineObservationEventDate
                                              date_
MachineObservationEventID
                                              string/_
MachineObservationEventRemarks
                                              lang-alt_
MachineObservationEventTime
                                              string_
MachineObservationFieldNotes
                                              string_
MachineObservationFieldNumber
                                              string_
MachineObservationHabitat
                                              string_
MachineObservationLatestDate
                                              date
MachineObservationMonth
                                              integer
MachineObservationParentEventID
                                              string_
MachineObservationSampleSizeUnit
                                              string
MachineObservationSampleSizeValue
                                              string
MachineObservationSamplingEffort
                                              string_
MachineObservationSamplingProtocol
                                              string
MachineObservationStartDayOfYear
                                              integer
MachineObservationVerbatimEventDate
                                              string_
MachineObservationYear
                                              integer
MaterialSample
                                              DarwinCore MaterialSample Struct
MaterialSampleID
                                              string
MeasurementOrFact
                                             DarwinCore MeasurementOrFact Struct
MeasurementAccuracy
                                              string
MeasurementDeterminedBy
                                              string
MeasurementDeterminedDate
                                              date
MeasurementID
                                              string
MeasurementMethod
                                              string
MeasurementRemarks
                                              string
MeasurementType
                                              string
MeasurementUnit
                                              string_
MeasurementValue
                                              string
Occurrence
                                              DarwinCore Occurrence Struct
OccurrenceAssociatedMedia
                                              string_
OccurrenceAssociatedOccurrences
                                              string
OccurrenceAssociatedReferences
                                              string_
OccurrenceAssociatedSequences
                                              string
OccurrenceAssociatedTaxa
                                              string
OccurrenceBehavior
                                              string
OccurrenceCatalogNumber
                                              string
OccurrenceDegreeOfEstablishment
                                              string
OccurrenceDisposition
                                              string
OccurrenceEstablishmentMeans
                                              string_
OccurrenceGeoreferenceVerificationStatus
                                              string
OccurrenceIndividualCount
                                              string
OccurrenceIndividualID
                                              string
OccurrenceLifeStage
                                              string
OccurrenceDetails
                                              string
OccurrenceID
                                              string
OccurrenceRemarks
                                              string
OccurrenceStatus
                                              string
OccurrenceOrganismQuantity
                                              string
OccurrenceOrganismQuantityType
                                              string
OccurrenceOtherCatalogNumbers
                                              string
OccurrencePathway
                                              string_
OccurrencePreparations
                                              string_
{\tt OccurrencePreviousIdentifications}
                                              string
OccurrenceRecordedBy
                                              string_
OccurrenceRecordedByID
                                              string_
OccurrenceRecordNumber
                                              string_
OccurrenceReproductiveCondition
                                              string_
OccurrenceSex
                                              string
                                              DarwinCore Organism Struct
Organism
OrganismAssociatedOccurrences
                                              string_
```

OrganismAssociatedOrganisms	string
OrganismID	string_
OrganismName	string_
OrganismRemarks	string
OrganismScope	string_
OrganismPreviousIdentifications	string_
PreservedSpecimen	DarwinCore MaterialSample Struct
PreservedSpecimenMaterialSampleID	string
Record	DarwinCore Record Struct
RecordBasisOfRecord	string
RecordCollectionCode	string_
RecordCollectionID	string_
RecordDataGeneralizations	string_
RecordDatasetID	string_
RecordDatasetName	string_
RecordDynamicProperties	string_
RecordInformationWithheld	string_
RecordInstitutionCode	string_
RecordInstitutionID	string_
RecordOwnerInstitutionCode	string_
ResourceRelationship	DarwinCore ResourceRelationship Struct
RelatedResourceID	string_
RelationshipAccordingTo	string_
Relationship ${ t EstablishedDate}$	date_
RelationshipOfResource	string_
RelationshipOfResourceID	string_
RelationshipRemarks	string_
ResourceID	string_
ResourceRelationshipID	string_
Taxon	DarwinCore Taxon Struct
TaxonAcceptedNameUsage	string_
TaxonAcceptedNameUsageID	string_
TaxonClass	string_
TaxonCultivarEpithet	string_
TaxonFamily	string_
TaxonGenus	string_
TaxonHigherClassification	string_
TaxonInfraspecificEpithet	string_
TaxonKingdom	string_
TaxonNameAccordingTo	string_
TaxonNameAccordingToID	string_
TaxonNamePublishedIn	string_
TaxonNamePublishedInID	string_
TaxonNamePublishedInYear	string_
TaxonNomenclaturalCode	string_
TaxonNomenclaturalStatus	string_
TaxonOrder	string_
TaxonOriginalNameUsage	string_
TaxonOriginalNameUsageID	string_
TaxonParentNameUsage	string_
TaxonParentNameUsageID TaxonPhylum	string_ string
TaxonScientificName	string_ string
TaxonScientificNameAuthorship	string_ string_
TaxonScientificNameID	string_ string_
TaxonSpecificEpithet	string_ string_
TaxonSubgenus	string_ string_
TaxonConceptID	string_ string
TaxonID	string_ string_
TaxonTaxonomicStatus	string_ string_
TaxonRank	string_ string
TaxonRemarks	string_ string_
TaxonVerbatimTaxonRank	string_ string_
TaxonVernacularName	lang-alt_
2 322022 V CEETAO WE WE TAKE	14115 416_
DarwinCore DCTermsLocation Struct	

Writable

string

Field Name

Continent

	tring
<u>-</u>	tring
<del>-</del>	tring
2	tring
	tring
	tring
	tring
<del>-</del>	tring
	tring
±	tring
	tring
-	tring
	tring
	tring
	tring
Island	tring
	tring
4	tring
LocationAccordingTo s	tring
LocationID s	tring
	tring
MaximumDepthInMeters s	tring
MaximumDistanceAboveSurfaceInMeters s	tring
	tring
MinimumDepthInMeters s	tring
MinimumDistanceAboveSurfaceInMeters s	tring
	tring
	tring
PointRadiusSpatialFit s	tring
	tring
VerbatimCoordinateSystem s	tring
VerbatimCoordinates s	tring
VerbatimDepth s	tring
VerbatimElevation s	tring
VerbatimLatitude s	tring
VerbatimLocality s	tring
VerbatimLongitude s	tring
	tring
VerticalDatum s	tring
WaterBody s	tring

# DarwinCore Event Struct

Field Name	Writable
Day	integer
EarliestDate	date
EndDayOfYear	integer
EventDate	date
EventID	string
EventRemarks	lang-alt
EventTime	string
FieldNotes	string
FieldNumber	string
Habitat	string
LatestDate	date
Month	integer
ParentEventID	string
SampleSizeUnit	string
SampleSizeValue	string
SamplingEffort	string
SamplingProtocol	string
StartDayOfYear	integer
VerbatimEventDate	string
Year	integer

## <u>DarwinCore</u> <u>MaterialSample</u> <u>Struct</u>

Field Name	Writable
MaterialSampleID	string

## <u>DarwinCore</u> <u>GeologicalContext</u> <u>Struct</u>

Field Name	Writable
Bed	string
EarliestAgeOrLowestStage	string
EarliestEonOrLowestEonothem	string
EarliestEpochOrLowestSeries	string
EarliestEraOrLowestErathem	string
EarliestPeriodOrLowestSystem	string
Formation	string
GeologicalContextID	string
Group	string
HighestBiostratigraphicZone	string
LatestAgeOrHighestStage	string
LatestEonOrHighestEonothem	string
LatestEpochOrHighestSeries	string
LatestEraOrHighestErathem	string
LatestPeriodOrHighestSystem	string
LithostratigraphicTerms	string
LowestBiostratigraphicZone	string
Member	string

## <u>DarwinCore</u> <u>Identification</u> <u>Struct</u>

Field Name	Writable
DateIdentified	date
IdentificationID	string
IdentificationQualifier	string
IdentificationReferences	string
IdentificationRemarks	string
IdentificationVerificationStatus	string
IdentifiedBy	string
IdentifiedByID	string
TypeStatus	string
VerbatimIdentification	string

## DarwinCore MeasurementOrFact Struct

Field Name	Writable
MeasurementAccuracy	string
MeasurementDeterminedBy	string
MeasurementDeterminedDate	date
MeasurementID	string
MeasurementMethod	string
MeasurementRemarks	string
MeasurementType	string
MeasurementUnit	string
MeasurementValue	string

## DarwinCore Occurrence Struct

Field Name	Writable
AssociatedMedia	string
AssociatedOccurrences	string
AssociatedReferences	string
AssociatedSequences	string
AssociatedTaxa	string
Behavior	string
CatalogNumber	string
DegreeOfEstablishment	string

Disposition	string
EstablishmentMeans	string
GeoreferenceVerificationStatus	string
IndividualCount	string
IndividualID	string
LifeStage	string
OccurrenceDetails	string
OccurrenceID	string
OccurrenceRemarks	string
OccurrenceStatus	string
OrganismQuantity	string
OrganismQuantityType	string
OtherCatalogNumbers	string
Pathway	string
Preparations	string
PreviousIdentifications	string
RecordNumber	string
RecordedBy	string
RecordedByID	string
ReproductiveCondition	string
Sex	string

# <u>DarwinCore</u> <u>Organism</u> <u>Struct</u>

Field Name	Writable
AssociatedOccurrences	string
AssociatedOrganisms	string
OrganismID	string
OrganismName	string
OrganismRemarks	string
OrganismScope	string
PreviousIdentifications	string

# <u>DarwinCore</u> <u>Record</u> <u>Struct</u>

m' 11 x	** '. 17
Field Name	Writable
BasisOfRecord	string
CollectionCode	string
CollectionID	string
DataGeneralizations	string
DatasetID	string
DatasetName	string
DynamicProperties	string
InformationWithheld	string
InstitutionCode	string
InstitutionID	string
OwnerInstitutionCode	string

# <u>DarwinCore</u> <u>ResourceRelationship</u> <u>Struct</u>

Field Name	Writable
RelatedResourceID	string
RelationshipAccordingTo	string
RelationshipEstablishedDate	date
RelationshipOfResource	string
RelationshipOfResourceID	string
RelationshipRemarks	string
ResourceID	string
ResourceRelationshipID	string

# <u>DarwinCore</u> <u>Taxon</u> <u>Struct</u>

Field Name	Writable
AcceptedNameUsage AcceptedNameUsageID Class	string string string

CultivarEpithet	string
Family	string
Genus	string
HigherClassification	string
InfraspecificEpithet	string
Kingdom	string
NameAccordingTo	string
NameAccordingToID	string
NamePublishedIn	string
NamePublishedInID	string
NamePublishedInYear	string
NomenclaturalCode	string
NomenclaturalStatus	string
Order	string
OriginalNameUsage	string
OriginalNameUsageID	string
ParentNameUsage	string
ParentNameUsageID	string
Phylum	string
ScientificName	string
ScientificNameAuthorship	string
ScientificNameID	string
SpecificEpithet	string
Subgenus	string
TaxonConceptID	string
TaxonID	string
TaxonRank	string
TaxonRemarks	string
TaxonomicStatus	string
VerbatimTaxonRank	string
VernacularName	lang-alt

### FotoStation Tags

The following tables define information found in the FotoWare FotoStation trailer.

Tag ID	Tag Name	Writable
0x0001	IPTC	IPTC
$0 \times 0002$	SoftEdit	FotoStation SoftEdit
0x0003	ThumbnailImage	yes
$0 \times 0004$	PreviewImage	yes

## FotoStation SoftEdit Tags

Index4	Tag Name	Writable
0	OriginalImageWidth	int32s
1	OriginalImageHeight	int32s
2	ColorPlanes	int32s
3	XYResolution	int32s
4	Rotation	int32s
6	CropLeft	int32s
7	CropTop	int32s
8	CropRight	int32s
9	CropBottom	int32s
11	CropRotation	int32s

#### PhotoMechanic Tags

The Photo Mechanic trailer contains data in an IPTC-format structure, with soft edit information stored under record number 2.

Record	Tag Name	Writable
2	SoftEdit	PhotoMechanic SoftEdit

# PhotoMechanic SoftEdit Tags

Tag ID	Tag Name	Writable

209	RawCropLeft	int32s
210	RawCropTop	int32s
211	RawCropRight	int32s
212	RawCropBottom	int32s
213	ConstrainedCropWidth	int32s
214	ConstrainedCropHeight	int32s
215	FrameNum	int32s
216	Rotation	int32s
217	CropLeft	int32s
218	CropTop	int32s
219	CropRight	int32s
220	CropBottom	int32s
221	Tagged	int32s
222	ColorClass	int32s
223	Rating	int32s
236	PreviewCropLeft	int32s
237	PreviewCropTop	int32s
238	PreviewCropRight	int32s
239	PreviewCropBottom	int32s

#### PhotoMechanic XMP Tags

Below is a list of the observed PhotoMechanic XMP tags. The actual namespace prefix is "photomechanic" but ExifTool shortens this in the family 1 group name.

These tags belong to the ExifTool XMP-photomech family 1 group.

Tag Name	Writable
ColorClass	integer
CountryCode	string/
CreatorIdentity	string+
EditStatus	string
PMVersion	string
Prefs	string
Tagged	boolean
TimeCreated	string/

#### Microsoft Tags

# Microsoft XMP Tags

Microsoft Photo 1.0 schema XMP tags. This is likely not a complete list, but represents tags which have been observed in sample images. The actual namespace prefix is "MicrosoftPhoto", but ExifTool shortens this in the family 1 group name.

These tags belong to the ExifTool XMP-microsoft family 1 group.

Tag Name	Writable
CameraSerialNumber	string
CreatorAppID	string
CreatorOpenWithUIOptions	string
DateAcquired	date
FlashManufacturer	string
FlashModel	string
ItemSubType	string
LastKeywordIPTC	string+
LastKeywordXMP	string+
LensManufacturer	string
LensModel	string/
RatingPercent	string

#### Microsoft MP Tags

Microsoft Photo 1.2 schema XMP tags which have been observed.

These tags belong to the ExifTool XMP-MP family 1 group.

Tag Name	Writable
RegionInfoDateRegionsValid	date_
RegionInfoMP	Microsoft RegionInfo Struct
RegionInfoRegions	Microsoft Regions Struct_+
RegionPersonDisplayName	string_+
RegionPersonEmailDigest	string_+
RegionPersonLiveIdCID	string_+
RegionPersonSourceID	string_+
RegionRectangle	string_+

### Microsoft RegionInfo Struct

Field Name	Writable
DateRegionsValid	date
Regions	Microsoft Regions Struct+

### Microsoft Regions Struct

Note that PersonLiveIdCID element is called PersonLiveCID according to the Microsoft specification, but in practice their software actually writes PersonLiveIdCID, so ExifTool uses this too.

Field Name	Writable
PersonDisplayName	string
PersonEmailDigest	string
PersonLiveIdCID	string
PersonSourceID	string
Rectangle	string

#### Microsoft MP1 Tags

Microsoft Photo 1.1 schema XMP tags which have been observed.

These tags belong to the ExifTool XMP-MP1 family 1 group.

Tag Name	Writable
Brightness	string/
CameraModelID	string/
Contrast	string/
ExposureCompensation	string/
PanoramicStitchCameraMotion	string
PanoramicStitchMapType	string
PanoramicStitchPhi0	real
PanoramicStitchPhi1	real
PanoramicStitchTheta0	real
PanoramicStitchThetal	real
PipelineVersion	string
StreamType	string
WhiteBalance0	real
WhiteBalance1	real
WhiteBalance2	real

### Microsoft Stitch Tags

Information found in the Microsoft custom EXIF tag 0x4748, as written by Windows Live Photo Gallery.

Index4	Tag Name	Writable
0	PanoramicStitchVersion	int32u
1	PanoramicStitchCameraMotion	int32u
2	PanoramicStitchMapType	int32u
3	PanoramicStitchTheta0	float
4	PanoramicStitchTheta1	float
5	PanoramicStitchPhi0	float
6	PanoramicStitchPhi1	float

## Microsoft Xtra Tags

Tags found in the Microsoft "Xtra" atom of QuickTime videos. Tag ID's are not shown because some are unruly GUID's. Currently most of these tags are not writable because the Microsoft documentation is poor and samples were not available, but more tags may be made writable in the future if samples are provided. Note that writable tags in this table are are flagged to "Avoid", which means that other more common tags will be written instead if possible unless the Microsoft group is specified explicitly.

Tag Name	Writable
Tag Name	writable
Abstract	no
AccountName	no
AcquisitionTime	no
AcquisitionTimeDay	no
AcquisitionTimeMonth	no
AcquisitionTimeYear	no
AcquisitionTimeYearMonth	
	no
AcquisitionTimeYearMonthDay AlbumArtist	no Unicode/
AlbumArtist	·
AlbumArtistSortOrder	no
AlbumCoverURL	no Unicode/
AlbumID	
AlbumIDAlbumArtist	no
AlbumTitle	no Unicode/
AlbumTitle	
	no
AlbumTitleSortOrder	no
AlternateSourceURL	no
Anniversary Artist	no
	no
AssistantsName	no
AssistantsPhone	no
Attachments	no
Attributes	no
AudioBitrate	no
AudioFormat	no
AudioSampleRate	no
AudioSampleSize	no
Author	no
Author	no
AuthorSortOrder	no
AuthorURL	Unicode/
AutoSummary	no
AverageLevel	no
BccAddresses	no
BccNames	no
Beats-per-minute	no
BeatsPerMinute	no
BillingInformation	no
Birthday	no
BitDepth	no
Bitrate	no
Bitrate	no
BroadcastDate	no
BusinessAddress	no
BusinessCity	no
BusinessCountry-Region	no
BusinessFax	no
BusinessHomePage	no
BusinessPOBox	no
BusinessPhone	no
BusinessPostalCode	no
BusinessStateOrProvince	no
BusinessStreet	no
BuyNow	no
BuyTickets	no

EXILIOOI IS.24 Tag Names	
CDTrackEnabled	no
CallLetters	no
CallbackNumber	no
CameraMaker	no
CameraManufacturer	no
CameraModel	no
CameraModel	no
CarPhone	no
Category	Unicode/+
Category	no
CcAddresses	no
CcNames	no
CellPhone	no
ChannelNumber	no
Channels	no
Channels	no
ChapterNum	no
Children	no
City	no
ClientID	no
ClosedCaptioning	no
Color	no
Comment	no
Comments	no
Company	no
CompanyMainPhone	no
Complete	no
Composer	Unicode/
Composers	no
Computer	no
Conductor	Unicode/+
Conductors	no
ContactNames	no
ContentDistributor	Unicode/
ContentDistributorDuration	no
ContentDistributorType	no
ContentGroupDescription	no
ContentType	no
Contributors	no
ConversationID	no
Copyright	no
Copyright	no
Count	no
Country-Region	no
Creator	no
CurrentBitrate	no
DLNAServerUDN	no
DLNASourceURI	no
DRMIndividualizedVersion	no
DRMKeyID	no
DTCPIPHost	no
DTCPIPPort	no
DVDID	no
DataRate	no
Date	no
DateAccessed	no
DateAcquired	vt filetime/
DateAcquired	no
DateCompleted	
DateCreated	no no
DateImported	
DateLastSaved	no
	no
DateModified DatePictureTaken	no
	no
DateReceived DateReleased	no
	no
DateSent	no
DateVisited	no
Department Description	no Unicode/
DEBOLIDOL	onreode/

		ExifTool	13.24	Tag	Names		
Description						1	10
Description						1	no
Dimensions						1	no
Director						Ţ	Jnicode/
Directors						1	no
DisplayArtist						1	no
Division						1	no
DocumentID						1	no
DueDate						1	no
Duration							no
Duration							10
Duration							10
E-mail2 E-mail3							10
E-mailAddress							10 10
E-mailDisplayNam	۵						10
E-mailList							10
EncodedBy							Unicode/
EncodedBy							10
EncodingTime							date/
EndDate						1	no
EntryType						1	no
EpisodeName						1	no
Event						1	no
Event						1	no
ExifVersion						1	no
ExposureBias							10
ExposureProgram							10
ExposureTime							10
F-stop FileAs							10 10
FileCount							10
FileSize							10
FileType							10
FileVersion							10
FirstName						1	10
FlagColor						1	no
FlagStatus						1	no
FlashMode						1	no
FocalLength						1	no
FocalLength35mm							10
Folder FolderName							10
FolderName FolderPath							10
FormatTag							10 10
FourCC							10
FrameHeight							10
FrameRate							10
FrameRate						1	no
FrameWidth						1	no
Free-busyStatus						1	no
Frequency						1	no
FromAddresses						1	no
FromNames							10
FullName							10
Gender							10
Genre							10
Genre GenreID							10 10
GivenName							10
HasAttachments							10
HasFlaq							no
Hobbies						1	no
HomeAddress						1	10
HomeCity						1	10
HomeCountry-Regi	on					1	no
HomeFax						1	no
HomePOBox							10
HomePhone							10
HomePostalCode						1	10

ExifTool 13.24 Tag Names	
HomeStateOrProvince	no
HomeStreet	no
HorizontalResolution	no
IMAddresses	no
ISOSpeed	no
Importance	no
Incomplete	no
InitialKey	Unicode/
InitialKey	no
Initials	no
IsAttachment	no
IsCompleted	no
IsDeleted	no
IsNetworkFeed	no
IsOnline	no
IsProtected	no
IsRecurring	no
IsVBR	no
JobTitle	no
Keywords	no
Kinds	no
Label	no
Language	no
Language	no
LastName	no
LastPrinted	no
LeadPerformer	no
LegalTrademarks	no
LensMaker	no
LensModel	no
LibraryID	no
LibraryName	no
LightSource	no
LinkStatus	no
LinkTarget	no
Location Location	no
	no
Lyrics MCDI	no
MailingAddress	no
MaxAperture	no
MediaClassPrimaryID	no GUID/
MediaClassSecondaryID	GUID/
MediaContentTypes	no
MediaCreated	no
MediaOriginalBroadcastDateTime	no
MediaOriginalChannel	no
MediaStationName	no
MediaType	no
MeteringMode	no
MiddleName	no
Mileage	no
ModifiedBy	no
Mood	Unicode/
Mood	no
MoreInfo	no
Name	no
Nickname	no
OfficeLocation	no
OfflineAvailability	no
OfflineStatus	no
OptionalAttendeeAddresses	no
OptionalAttendees	no
OrganizerAddress	no
OrganizerName	no
Orientation	no
OriginalAlbumTitle	Unicode/
OriginalArtist	Unicode/
OriginalLyricist	Unicode/
OtherAddress	no

	EXILIOOI	13.24	Tag	Names	
OtherCity					no
OtherCountry-Reg	rion				
	31011				no
OtherPOBox					no
OtherPostalCode					no
OtherStateOrProv	vince				no
OtherStreet					no
Owner					
					no
POBox					no
Pager					no
Pages					no
ParentalRating					Unicode/
ParentalRating					no
ParentalRatingRe	eason				no
PartOfSet					no
PartOfSet					no
PartOfSet					no
Participants					no
Path					no
PeakValue					no
PerceivedType					no
Period					Unicode/
					·
Period					no
PersonalTitle					no
PixelAspectRatio	X				no
PixelAspectRatio	Y				no
PlaylistIndex	-				no
PostalCode					no
PrimaryE-mail					no
PrimaryPhone					no
Priority					no
Producer					Unicode/+
					,
Producers					no
ProductName					no
ProductVersion					no
Profession					no
ProgramDescripti	on				no
ProgramMode	.011				
•					no
ProgramName					no
Project					no
PromotionURL					Unicode/
Protected					no
ProtectionType					
					no
Provider					no
Provider					Unicode/
ProviderLogoURL					no
ProviderRating					no
ProviderStyle					no
ProviderURL					no
Publisher					Unicode/
Publisher					no
RadioBand					no
RadioFormat					no
Rating					_
•					no
RatingOrg					no
ReadStatus					no
RecordingTime					no
RecordingTime					no
	7				
RecordingTimeDay					no
RecordingTimeMor					no
RecordingTimeYea	ar				no
RecordingTimeYea	arMonth				no
RecordingTimeYea					no
ReleaseDate	ay				
					no
ReleaseDateDay					no
ReleaseDateMonth	l				no
ReleaseDateYear					no
ReleaseDateYearM	Month				no
ReleaseDateYearM	_				_
	ioiiciiDay				no
ReminderTime					no
RequestState					no

RequiredAttendeeAddresses	no
RequiredAttendees	no
Rerun	no
Resources SAP	no
Saturation	no no
SearchRanking	no
SenderAddress	no
SenderName	no
Sensitivity	no
ShadowFilePath	no
Shared	no
SharedUserRating	int64u/
SharedWith	no
Size	no
Slides	no
Source SourceURL	no no
SpaceFree	no
SpaceUsed	no
Spouse	no
StartDate	no
StateOrProvince	no
StationCallSign	no
StationName	no
Status	no
Status	no
Store	no
Street	no
Subject Subject	no no
SubjectDistance	no
SubscriptionContentID	no
Subtitle	Unicode/
Subtitle	no
SubtitleDescription	no
Suffix	no
Summary	no
Sync01	no
Sync02	no
Sync03	no
	20.0
Sync04	no
Sync05	no
Sync05 Sync06	no no
Sync05 Sync06 Sync07	no
Sync05 Sync06	no no no
Sync05 Sync06 Sync07 Sync08	no no no no
Sync05 Sync06 Sync07 Sync08 Sync09 Sync10 Sync11	no no no no no
Sync05 Sync06 Sync07 Sync08 Sync09 Sync10 Sync11 Sync12	no no no no no no
Sync05 Sync06 Sync07 Sync08 Sync09 Sync10 Sync11 Sync12 Sync13	no
Sync05 Sync06 Sync07 Sync08 Sync09 Sync10 Sync11 Sync12 Sync13 Sync14	no n
Sync05 Sync06 Sync07 Sync08 Sync09 Sync10 Sync11 Sync12 Sync13 Sync14 Sync15	no n
Sync05 Sync06 Sync07 Sync08 Sync09 Sync10 Sync11 Sync12 Sync13 Sync14 Sync15 Sync16	no n
Sync05 Sync06 Sync07 Sync08 Sync09 Sync10 Sync11 Sync12 Sync12 Sync13 Sync14 Sync15 Sync16 Sync01y	no n
Sync05 Sync06 Sync07 Sync08 Sync09 Sync10 Sync11 Sync12 Sync13 Sync14 Sync15 Sync16	no n
Sync05 Sync06 Sync07 Sync08 Sync09 Sync10 Sync11 Sync12 Sync15 Sync14 Sync15 Sync16 Sync0nly SyncState	no n
Sync05 Sync06 Sync07 Sync08 Sync09 Sync10 Sync11 Sync12 Sync15 Sync15 Sync14 Sync15 Sync16 Sync0nly SyncState TTY-TTDPhone	no n
Sync05 Sync06 Sync07 Sync08 Sync09 Sync10 Sync11 Sync12 Sync13 Sync14 Sync15 Sync16 Sync0nly SyncState TTY-TTDPhone TaskOwner Telex Temporary	no n
Sync05 Sync06 Sync07 Sync08 Sync09 Sync10 Sync11 Sync12 Sync13 Sync14 Sync15 Sync16 SyncOnly SyncState TTY-TTDPhone TaskOwner Telex Temporary Title	no n
Sync05 Sync06 Sync07 Sync08 Sync09 Sync10 Sync11 Sync12 Sync13 Sync14 Sync15 Sync16 Sync0nly SyncState TTY-TTDPhone TaskOwner Telex Temporary Title Title	no n
Sync05 Sync06 Sync07 Sync08 Sync09 Sync10 Sync11 Sync12 Sync13 Sync14 Sync15 Sync16 Sync0nly SyncState TTY-TTDPhone TaskOwner Telex Temporary Title Title TitleNum	no n
Sync05 Sync07 Sync08 Sync09 Sync10 Sync11 Sync12 Sync13 Sync14 Sync15 Sync16 Sync0nly SyncState TTY-TTDPhone TaskOwner Telex Temporary Title Title TitleNum TitleSortOrder	no n
Sync05 Sync07 Sync08 Sync09 Sync10 Sync11 Sync12 Sync13 Sync14 Sync15 Sync16 Sync0nly SyncState TTY-TTDPhone TaskOwner Telex Temporary Title Title TitleNum TitleSortOrder ToAddresses	no n
Sync06 Sync07 Sync08 Sync09 Sync10 Sync11 Sync12 Sync13 Sync14 Sync15 Sync16 Sync0nly SyncState TTY-TTDPhone TaskOwner Telex Temporary Title Title TitleNum TitleSortOrder ToAddresses ToDoTitle	no n
Sync05 Sync06 Sync07 Sync08 Sync09 Sync10 Sync11 Sync12 Sync13 Sync14 Sync15 Sync16 Sync0nly SyncState TTY-TTDPhone TaskOwner Telex Temporary Title Title TitleNum TitleSortOrder ToAddresses ToDoTitle ToNames	no n
Sync06 Sync07 Sync08 Sync09 Sync10 Sync11 Sync12 Sync13 Sync14 Sync15 Sync16 Sync0nly SyncState TTY-TTDPhone TaskOwner Telex Temporary Title Title TitleNum TitleSortOrder ToAddresses ToDoTitle	no n
Sync06 Sync07 Sync08 Sync09 Sync10 Sync11 Sync12 Sync13 Sync14 Sync15 Sync16 Sync0nly SyncState TTY-TTDPhone TaskOwner Telex Temporary Title Title TitleNum TitleSortOrder ToAddresses ToDoTitle ToNames TotalBitrate	no n

_	
TotalFileSize	no
TotalSize	no
TrackNumber	no
TrackNumber	no
TrackingID	no
Type	no
Туре	no
URL	no
UniqueFileIdentifier	no
Untitled0	no
Untitled1	no
Untitled2	no
UserCustom1	no
UserCustom2	no
UserEffectiveRating	no
UserLastPlayedTime	no
UserPlayCount	no
UserPlaycountAfternoon	no
UserPlaycountEvening	no
UserPlaycountMorning	no
UserPlaycountNight	no
UserPlaycountWeekday	no
UserPlaycountWeekend	no
UserRating	no
UserServiceRating	no
UserWebURL	no
VerticalResolution	no
VideoBitrate	no
VideoCompression	no
VideoFormat	no
VideoFrameRate	no
VideoHeight	no
VideoWidth	no
WMCollectionGroupID	no
WMCollectionID	no
WMContentID	no
WMShadowFileSourceDRMType	no
WMShadowFileSourceFileType	no
Webpage	no
WhiteBalance	no
WindowsFileName	no
WordCount	no
Writer	Unicode
Writers	no
Year	no
Year	no
	-

# GIMP Tags

The GNU Image Manipulation Program (GIMP) writes these tags in its native XCF (eXperimental Computing Facilty) images.

Tag ID	Tag Name	Writable
'header'	Header	GIMP Header
0x0011	Compression	no
0x0013	Resolution	GIMP Resolution
$0 \times 0014$	Tattoo	no
0x0015	Parasites	GIMP Parasite
$0 \times 0016$	Units	no

# <u>GIMP Header Tags</u>

Index1	Tag Name	Writable
9	XCFVersion	no
14	ImageWidth	no
18	ImageHeight	no
22	ColorMode	no

# GIMP Resolution Tags

Index4	Tag Name	Writable
0	XResolution	no
1	YResolution	no

#### GIMP Parasite Tags

Tag ID	Tag Name	Writable
'exif-data'	ExifData	EXIF
'gimp-comment'	Comment	no
'gimp-image-metadata'	XML	XMP XML
'gimp-metadata'	XMP	XMP
'icc-profile'	ICC_Profile	ICC_Profile
'icc-profile-name'	ICCProfileName	no
'iptc-data'	IPTCData	IPTC
'jpeg-exif-data'	JPEGExifData	EXIF

#### MIE Tags

MIE is a flexible format which may be used as a stand-alone meta information format, for encapsulation of other files and information, or as a trailer appended to other file formats. The tables below represent currently defined MIE tags, however ExifTool will also extract any other information present in a MIE file.

When writing MIE information, some special features are supported:

- 1) String values may be written as ASCII (ISO 8859-1) or UTF-8. ExifTool automatically detects the presence of wide characters and treats the string appropriately. Internally, UTF-8 text may be converted to UTF-16 or UTF-32 and stored in this format in the file if it is more compact.
- 2) All MIE string-value tags support localized text. Localized values are written by adding a language/country code to the tag name in the form "TAG-xx\_YY", where "TAG" is the tag name, "xx" is a 2-character lower case ISO 639-1 language code, and "YY" is a 2-character upper case ISO 3166-1 alpha 2 country code (eg. "Title-en\_US"). But as usual, the user interface is case-insensitive, and ExifTool will write the correct case to the file.
- 3) Some numerical MIE tags allow units of measurement to be specified. For these tags, units may be added in brackets immediately following the value (eg. 55(mi/h)). If no units are specified, the default units are written.
- 4) ExifTool writes compressed metadata to MIE files if the Compress (-z) option is used and Compress::Zlib is available.

See <a href="https://exiftool.org/MIE1.1-20070121.pdf">https://exiftool.org/MIE1.1-20070121.pdf</a>> for the official MIE specification.

Tag ID	Tag Name	Writable
'OType'	SubfileType MIEVersion	string string
'1Directory' '1Name' '2MIME'	SubfileDirectory SubfileName SubfileMIMEType	string string string
'Meta' 'data'	Meta SubfileData	MIE Meta undef
'rsrc' 'zmd5'	SubfileResource MD5Digest	undef string
'zmie'	TrailerSignature	undef

# MIE Meta Tags

Tag ID	Tag Name	Writable

## -- ExifTool 13.24 Tag Names --

'Audio' Audio MIE Audio 'Camera' Camera MIE Camera 'Document' Document MIE Doc 'EXIF' EXIF EXIF 'Geo' MIE Geo Geo ICC\_Profile 'ICCProfile' ICC\_Profile 'ID3' ID3 'IPTC' IPTC IPTC 'Image' MIE Image Image MakerNotes 'MakerNotes' MIE MakerNotes Preview Thumbnail 'Preview' MIE Preview 'Thumbnail' MIE Thumbnail 'Video' Video MIE Video 'XMP' XMP XMP

## MIE Audio Tags

For the Audio group (and any other group containing a 'data' element), tags refer to the contained data if present, otherwise they refer to the main SubfileData. The "OType" and "1Name" elements should exist only if "data" is present.

Tag ID	Tag Name	Writable
'0Type'	RelatedAudioFileType	string
'1Name'	RelatedAudioFileName	string
'Channels'	Channels	int8u
'Compression'	AudioCompression	string
'Duration'	Duration	rational64u~
'SampleBits'	SampleBits	int16u
'SampleRate'	SampleRate	int32u
'data'	RelatedAudioFile	undef

#### MIE Camera Tags

Tag ID	Tag Name	Writable
'Brightness'	Brightness	int8s
'ColorBalance'	ColorBalance	rational64u[3]
'ColorTemperature'	ColorTemperature	int32u
'Contrast'	Contrast	int8s
'DigitalZoom'	DigitalZoom	rational64u
'ExposureComp'	ExposureCompensation	rational64s
'ExposureMode'	ExposureMode	string
'ExposureTime'	ExposureTime	rational64u
'FirmwareVersion'	FirmwareVersion	string
'Flash'	Flash	MIE Flash
'FocusMode'	FocusMode	string
'ISO'	ISO	int16u
'ISOSetting'	ISOSetting	int16u
'ImageNumber'	ImageNumber	int32u
'ImageQuality'	ImageQuality	string
'ImageStabilization'	ImageStabilization	int8u
'Lens'	Lens	MIE Lens
'Make'	Make	string
'MeasuredEV'	MeasuredEV	rational64s
'Model'	Model	string
'Orientation'	Orientation	MIE Orient
'OwnerName'	OwnerName	string
'Saturation'	Saturation	int8s
'SensorSize'	SensorSize	rational64u[2]
'SerialNumber'	SerialNumber	string
'Sharpness'	Sharpness	int8s
'ShootingMode'	ShootingMode	string

## MIE Flash Tags

Tag ID	Tag Name	Writable
'ExposureComp'	FlashExposureComp	rational64s

## -- ExifTool 13.24 Tag Names --

'Fired'	FlashFired	int8u
'GuideNumber'	FlashGuideNumber	string
'Make'	FlashMake	string
'Mode'	FlashMode	string
'Model'	FlashModel	string
'SerialNumber'	FlashSerialNumber	string
'Type'	FlashType	string

## MIE Lens Tags

All recorded lens parameters (focal length, aperture, etc) include the effects of the extender if present.

Tag ID	Tag Name	Writable
'Extender'	Extender	MIE Extender
'FNumber'	FNumber	rational64u
'FocalLength'	FocalLength	rational64u
'FocusDistance'	FocusDistance	rational64u
'Make'	LensMake	string
'MaxAperture'	MaxAperture	rational64u
'MaxApertureAtMaxFocal'	MaxApertureAtMaxFocal	rational64u
'MaxFocalLength'	MaxFocalLength	rational64u
'MinAperture'	MinAperture	rational64u
'MinFocalLength'	MinFocalLength	rational64u
'Model'	LensModel	string
'OpticalZoom'	OpticalZoom	rational64u
'SerialNumber'	LensSerialNumber	string

## MIE Extender Tags

Tag ID	Tag Name	Writable
'Magnification' 'Make'	ExtenderMagnification ExtenderMake	rational64s string
'Model' 'SerialNumber'	ExtenderModel ExtenderSerialNumber	string string

## MIE Orient Tags

These tags describe the camera orientation.

Tag ID	Tag Name	Writable
'Azimuth' 'Declination' 'Elevation' 'RightAscension' 'Rotation'	Azimuth Declination Elevation RightAscension Rotation	rational64s rational64s rational64s rational64s rational64s

## MIE Doc Tags

Information describing the main document, image or file.

Tag ID	Tag Name	Writable
'Author'	Author	string
'Comment'	Comment	string
'Contributors'	Contributors	string+
'Copyright'	Copyright	string
'CreateDate'	CreateDate	string
'EMail'	Email	string
'Keywords'	Keywords	string+
'ModifyDate'	ModifyDate	string
'OriginalDate'	DateTimeOriginal	string
'Phone'	PhoneNumber	string
'References'	References	string+
'Software'	Software	string
'Title'	Title	string
'URL'	URL	string

# MIE Geo Tags

Information related to geographic location.

Tag ID	Tag Name	Writable
'Address'	Address	string
'City'	City	string
'Country'	Country	string
'GPS'	GPS	MIE GPS
'PostalCode'	PostalCode	string
'State'	State	string
'UTM'	UTM	MIE UTM

## MIE GPS Tags

Tag ID	Tag Name	Writable
'Altitude'	GPSAltitude	rational64s
'Bearing'	GPSDestBearing	rational64s
'DateTime'	GPSDateTime	string
'Datum'	GPSMapDatum	string
'Differential'	GPSDifferential	int8u
'Distance'	GPSDestDistance	rational64s
'Heading'	GPSTrack	rational64s
'Latitude'	GPSLatitude	rational64s[n]
'Longitude'	GPSLongitude	rational64s[n]
'MeasureMode'	GPSMeasureMode	int8u
'Satellites'	GPSSatellites	string
'Speed'	GPSSpeed	rational64s

# MIE UTM Tags

Tag ID	Tag Name	Writable
'Datum' 'Easting'	UTMMapDatum UTMEasting	string string
'Northing'	UTMNorthing	string
'Zone'	UTMZone	int8s

# MIE Image Tags

Tag ID	Tag Name	Writable
'0Type'	FullSizeImageType	string
'1Name'	FullSizeImageName	string
'BitDepth'	BitDepth	int16u
'ColorSpace'	ColorSpace	string
'Components'	ComponentsConfiguration	string
'Compression'	CompressionRatio	rational32u
'ImageSize'	ImageSize	int16u[n]
'OriginalImageSize'	OriginalImageSize	int16u[n]
'Resolution'	Resolution	rational64u[n]
'data'	FullSizeImage	undef

## MIE MakerNotes Tags

MIE maker notes are contained within separate groups for each manufacturer to avoid name conflicts.

Tag ID	Tag Name	Writable
'Canon'	Canon	MIE Canon
'Casio'	Casio	MIE Unknown
'FujiFilm'	FujiFilm	MIE Unknown
'Kodak'	Kodak	MIE Unknown
'KonicaMinolta'	KonicaMinolta	MIE Unknown
'Nikon'	Nikon	MIE Unknown
'Olympus'	Olympus	MIE Unknown

## -- ExifTool 13.24 Tag Names --

'Panasonic'	Panasonic	MIE Unknown
'Pentax'	Pentax	MIE Unknown
'Ricoh'	Ricoh	MIE Unknown
'Sigma'	Sigma	MIE Unknown
'Sony'	Sony	MIE Unknown

## MIE Canon Tags

Tag ID	Tag Name	Writable
'VRD'	CanonVRD	CanonVRD

## MIE Unknown Tags

Tag ID	Tag Name	Writable
[no tags	known]	

## MIE Preview Tags

Tag ID	Tag Name	Writable
'0Type'	PreviewImageType	string
'1Name'	PreviewImageName	string
'ImageSize'	PreviewImageSize	int16u[n]
'data'	PreviewImage	undef

## MIE Thumbnail Tags

Tag ID	Tag Name	Writable
'0Type'	ThumbnailImageType	string
'1Name'	ThumbnailImageName	string
'ImageSize'	ThumbnailImageSize	int16u[n]
'data'	ThumbnailImage	undef

## MIE Video Tags

Tag ID	Tag Name	Writable
'0Type'	RelatedVideoFileType	string
'1Name'	RelatedVideoFileName	string
'Codec'	Codec	string
'Duration'	Duration	rational64u~
'data'	RelatedVideoFile	undef

# Trailer Tags

## Trailer Vivo Tags

Information written in JPEG trailer by some Vivo phones.

Tag Name	Writable
HDRImage	no
HiddenData	no
JSONInfo	no

## Trailer OnePlus Tags

Information written in JPEG trailer by some OnePlus phones.

Tag ID	Tag Name	Writable
'JSONInfo'	JSONInfo	no
'private.emptyspace'	OnePlusTrailerLen?	no
'watermark.device'	Device	no

## Trailer Google Tags

Google-defined information written in the trailer of JPEG images by

some phones. This information is referenced by DirectoryItem entries in the XMP. Note that some of this information may also be referenced from other metadata formats, and hence may be extracted twice. For example, MotionPhotoVideo may also exist within a Samsung trailer as EmbbededVideoFile, or GainMapImage may also exist in an MPF trailer as MPImage2.

Tag ID	Tag Name	Writable
'Confidence'	ConfidenceMapImage	no
'Depth'	DepthMapImage	no
'GainMap'	GainMapImage	no
'MotionPhoto'	MotionPhotoVideo	no
'android/confidencemap'	ConfidenceMapImage	no
'android/depthmap'	DepthMapImage	no

#### **GIF Tags**

This table lists information extracted from GIF images. See <a href="http://www.w3.org/Graphics/GIF/spec-gif89a.txt">http://www.w3.org/Graphics/GIF/spec-gif89a.txt</a> for the official GIF89a specification.

Tag Name	Writable
Comment Duration Extensions	yes no GIF Extensions
FrameCount	no
GIFVersion	no
ScreenDescriptor	GIF Screen
Text	no
TransparentColor	no

#### GIF Extensions Tags

Tags extracted from GIF89a application extensions.

Tag ID	Tag Name	Writable
'C2PA_GIF/'	JUMBF	Jpeg2000
'ICCRGBG1/012'	ICC_Profile	ICC_Profile
'MIDICTRL/Jon'	MIDIControl	GIF MIDIControl
'MIDISONG/Dm7'	MIDISong	no
'NETSCAPE/2.0'	Animation	GIF Animation
'XMP Data/XMP'	XMP	XMP

### GIF MIDIControl Tags

Information extracted from the MIDI control block extension.

Index1	Tag Name	Writable
0	MIDIControlVersion	no
1	SequenceNumber	no
2	MelodicPolyphony	no
3	PercussivePolyphony	no
4	ChannelUsage	no
6	DelayTime	no

#### GIF Animation Tags

Information extracted from the "NETSCAPE2.0" animation extension.

Index1	Tag Name	Writable
1	AnimationIterations	no

# GIF Screen Tags

Information extracted from the GIF logical screen descriptor.

## -- ExifTool 13.24 Tag Names --

Index1	Tag Name	Writable
0	ImageWidth	no
2	ImageHeight	no
4.1	HasColorMap	no
4.2	ColorResolutionDepth	no
4.3	BitsPerPixel	no
5	BackgroundColor	no
6	PixelAspectRatio	no

## BMP Tags

There really isn't much meta information in a BMP file as such, just a bit of image related information.

Index1	Tag Name	Writable
0	BMPVersion	no
4	ImageWidth	no
8	ImageHeight	no
12	Planes	no
14	BitDepth	no
16	Compression	no
20	ImageLength	no
24	PixelsPerMeterX	no
28	PixelsPerMeterY	no
32	NumColors	no
36	NumImportantColors	no
40	RedMask	no
44	GreenMask	no
48	BlueMask	no
52	AlphaMask	no
56	ColorSpace	no
60	RedEndpoint	no
72	GreenEndpoint	no
84	BlueEndpoint	no
96	GammaRed	no
100	GammaGreen	no
104	GammaBlue	no
108	RenderingIntent	no
112	ProfileDataOffset	no
116	ProfileSize	no

## BMP OS2 Tags

Information extracted from OS/2-format BMP images.

Index1	Tag Name	Writable
0	BMPVersion	no
4	ImageWidth	no
6	ImageHeight	no
8	Planes	no
10	BitDepth	no

## BMP Extra Tags

Extra information extracted from some BMP images.

Tag Name	Writable
EmbeddedJPG	no
EmbeddedPNG	no
ICC_Profile	ICC_Profile
LinkedProfileName	no

# BPG Tags

The information listed below is extracted from BPG (Better Portable Graphics) images. See <a href="http://bellard.org/bpg/">http://bellard.org/bpg/</a> for the specification.

Index1 Tag Name

Writable

4	PixelFormat	no
4.1	Alpha	no
4.2	BitDepth	no
4.3	ColorSpace	no
4.4	Flags	no
6	ImageWidth	no
7	ImageHeight	no
8	ImageLength	no

#### BPG Extensions Tags

Tag ID	Tag Name	Writable
0x0001	EXIF	EXIF
$0 \times 0002$	ICC_Profile	ICC_Profile
0x0003	XMP	XMP
$0 \times 0004$	ThumbnailBPG	no
$0 \times 0005$	AnimationControl?	no

#### WPG Tags

Tags extracted from WordPerfect Graphics (WPG) images.

Tag Name	Writable
ImageHeightInches	no
ImageWidthInches	no
Records	no+
RecordsV2	no+
WPGVersion	no

#### ICO Tags

Information extracted from Windows ICO (icon) and CUR (cursor) files.

Index1	Tag Name	Writable
2	ImageType	no
4	ImageCount	no
6	IconDir	ICO IconDir

# ICO IconDir Tags

Index1	Tag Name	Writable
0	ImageWidth	no
1	ImageHeight	no
2	NumColors	no
4	ColorPlanes	no
	HotspotX	no
6	BitsPerPixel	no
	HotspotY	no
8	ImageLength	no

### PICT Tags

The PICT format contains no true meta information, except for the possible exception of the LongComment opcode. By default, only ImageWidth, ImageHeight and X/YResolution are extracted from a PICT image. Tags in the following table represent image opcodes. Extraction of these tags is experimental, and is only enabled with the Verbose or Unknown options.

Tag ID	Tag Name	Writable
0x0000	Nop	no
0x0001	ClipRgn	no
$0 \times 0002$	BkPat	no
0x0003	TxFont	no
$0 \times 0004$	TxFace	no
0x0005	TxMode	no
0x0006	SpExtra	no

	ExifTool 13.24 Tag Names	
$0 \times 0007$	PnSize	no
$0 \times 0008$	PnMode	no
0x0009 0x000a	PnPat FillPat	no
0x000a 0x000b	OvSize	no no
0x000c	Origin	no
0x000d	TxSize	no
0x000e	FgColor	no
0x000f	BkColor	no
$0 \times 0010$ $0 \times 0011$	TxRatio VersionOp	no no
0x0011	BkPixPat	no
0x0013	PnPixPat	no
$0 \times 0014$	FillPixPat	no
0x0015	PnLocHFrac	no
0x0016 0x0017	ChExtra Reserved	no no
0x0017 0x001a	RGBFgCol	no
0x001b	RGBBkCol	no
0x001c	HiliteMode	no
0x001d	HiliteColor	no
0x001e 0x001f	DefHilite OpColor	no
0x0011 0x0020	Line	no no
0x0021	LineFrom	no
0x0022	ShortLine	no
0x0023	ShortLineFrom	no
$0 \times 0024$ $0 \times 0028$	Reserved LongText	no
0x0028 $0x0029$	DHText	no no
0x002a	DVText	no
0x002b	DHDVText	no
0x002c	FontName	no
0x002d 0x002e	LineJustify GlyphState	no no
0x002f	Reserved	no
0x0030	FrameRect	no
0x0031	PaintRect	no
0x0032 0x0033	EraseRect	no no
0x0033	InvertRect FillRect	no
0x0035	Reserved	no
$0 \times 0038$	FrameSameRect	no
$0 \times 0039$	PaintSameRect	no
0x003a 0x003b	EraseSameRect InvertSameRect	no no
0x003c	FillSameRect	no
0x003d	Reserved	no
$0 \times 0.040$	FrameRRect	no
$0 \times 0041$ $0 \times 0042$	PaintRRect EraseRRect	no
0x0042 $0x0043$	InvertRRect	no no
$0 \times 0044$	FillRRect	no
$0 \times 0045$	Reserved	no
$0 \times 0048$	FrameSameRRect	no
0x0049 0x004a	PaintSameRRect EraseSameRRect	no no
0x004a	InvertSameRRect	no
0x004c	FillSameRRect	no
0x004d	Reserved	no
$0 \times 0050$	FrameOval	no
$0 \times 0051$ $0 \times 0052$	PaintOval EraseOval	no no
0x0052 $0x0053$	InvertOval	no
0x0054	FillOval	no
0x0055	Reserved	no
$0 \times 0.058$	FrameSameOval PaintSameOval	no
0x0059 0x005a	PaintSameOval EraseSameOval	no no
0x005b	InvertSameOval	no

0x005c	FillSameOval	no
0x005d	Reserved	no
0x0060	FrameArc	no
0x0061	PaintArc	no
0x0061	EraseArc	_
		no
0x0063	InvertArc	no
$0 \times 0064$	FillArc	no
$0 \times 0065$	Reserved	no
0x0068	FrameSameArc	no
$0 \times 0069$	PaintSameArc	no
0x006a	EraseSameArc	no
0x006b	InvertSameArc	no
0x006c	FillSameArc	no
0x006d	Reserved	no
		_
$0 \times 0070$	FramePoly	no
$0 \times 0071$	PaintPoly	no
$0 \times 0072$	ErasePoly	no
$0 \times 0073$	InvertPoly	no
$0 \times 0074$	FillPoly	no
$0 \times 0075$	Reserved	no
$0 \times 0078$	FrameSamePoly	no
0x0079	PaintSamePoly	no
0x007a	EraseSamePoly	no
$0 \times 007b$	InvertSamePoly	no
0x007c	FillSamePoly	no
0x007d	Reserved	no
$0 \times 0080$	FrameRgn	no
$0 \times 0081$	PaintRgn	no
$0 \times 0082$	EraseRgn	no
0x0083	InvertRqn	no
$0 \times 0084$	FillRqn	no
0x0085	Reserved	no
0x0088	FrameSameRqn	_
	5	no
0x0089	PaintSameRgn	no
0x008a	EraseSameRgn	no
0x008b	InvertSameRgn	no
0x008c	FillSameRgn	no
0x008d	Reserved	no
$0 \times 0090$	BitsRect	no
0x0091	BitsRqn	no
0x0092	Reserved	no
0x0098	PackBitsRect	no
0x0099	PackBitsRgn	
		no
0x009a	DirectBitsRect	no
0x009b	DirectBitsRgn	no
0x009c	Reserved	no
0x009d	Reserved	no
0x009e	Reserved	no
0x009f	Reserved	no
0x00a0	ShortComment	no
0x00a1	LongComment	Photoshop
		ICC Profile
0x00a2	Reserved	no
0x00b0	_	
	Reserved	no
0x00d0	Reserved	no
0x00ff	OpEndPic	no
$0 \times 0100$	Reserved	no
$0 \times 0200$	Reserved	no
0x02ff	Version	no
$0 \times 0300$	Reserved	no
0x0bff	Reserved	no
0x0c00	HeaderOp	no
0x0c01	Reserved	no
0x0001 0x7f00	Reserved	
	_	no
0x8000	Reserved	no
0x8100	Reserved	no
0x8200	CompressedQuickTime	no
0x8201	UncompressedQuickTime	no
0xffff	Reserved	no

#### PNG Tags

Tags extracted from PNG images. See <a href="http://www.libpng.org/pub/png/spec/1.2/">http://www.libpng.org/pub/png/spec/1.2/</a>> for the official PNG 1.2 specification.

According to the specification, a PNG file should end at the IEND chunk, however ExifTool will preserve any data found after this when writing unless it is specifically deleted with "-Trailer:All=". When reading, a minor warning is issued if this trailer exists, and ExifTool will attempt to parse this data as additional PNG chunks.

Also according to the PNG specification, there is no restriction on the location of text-type chunks (tEXt, zTXt and iTXt). However, certain utilities (including some Apple and Adobe utilities) won't read the XMP iTXt chunk if it comes after the IDAT chunk, and at least one utility won't read other text chunks here. For this reason, when writing, ExifTool 11.63 and later create new text chunks (including XMP) before IDAT, and move existing text chunks to before IDAT.

The PNG format contains CRC checksums that are validated when reading with either the Verbose or Validate option. When writing, these checksums are validated by default, but the FastScan option may be used to bypass this check if speed is more of a concern.

Tag ID	Tag Name	Writable
'IHDR'	ImageHeader	PNG ImageHeader
'PLTE'	Palette	no
'acTL'	AnimationControl	PNG AnimationControl
'bKGD'	BackgroundColor	no
'cHRM'	PrimaryChromaticities	PNG PrimaryChromaticities
'cICP'	CICodePoints	PNG CICodePoints
'caBX'	JUMBF	Jpeg2000
'cpIp'	OLEInfo	FlashPix
'dSIG'	DigitalSignature	no
'eXIf'	eXIf	EXIF
'fRAc'	FractalParameters	no
'gAMA'	Gamma	yes!
'gIFg'	GIFGraphicControlExtension	no
'gIFt'	GIFPlainTextExtension	no
'gIFx'	GIFApplicationExtension	no
'gdAT'	GainMapImage	no
'hIST'	PaletteHistogram	no
'iCCP'	ICC_Profile	ICC_Profile
'iCCP-name'	ProfileName	yes
'iDOT'	AppleDataOffsets	no
'iTXt'	InternationalText	PNG TextualData
'meTa'	МеТа	XMP XML
'oFFs'	ImageOffset	no
'pCAL'	PixelCalibration	no
'pHYs'	PhysicalPixel	PNG PhysicalPixel
'sBIT'	SignificantBits	no
'sCAL'	SubjectScale	PNG SubjectScale
'sPLT'	SuggestedPalette	no
'sRGB'	SRGBRendering	yes!
'sTER'	StereoImage	PNG StereoImage
'seAl'	SEAL	XMP SEAL
'tEXt'	TextualData	PNG TextualData
'tIME'	ModifyDate	yes
'tRNS'	Transparency	no
'tXMP'	XMP	XMP
'vpAg'	VirtualPage	PNG VirtualPage
'zTXt'	CompressedText	PNG TextualData
'zxIf'	zxIf	EXIF

### PNG ImageHeader Tags

Index1	Tag Name	Writable
0	ImageWidth	no

4	ImageHeight	no
8	BitDepth	no
9	ColorType	no
10	Compression	no
11	Filter	no
12	Interlace	no

#### PNG AnimationControl Tags

Tags found in the Animation Control chunk. See <a href="https://wiki.mozilla.org/APNG\_Specification">https://wiki.mozilla.org/APNG\_Specification</a> for details.

Index4	Tag Name	Writable
0	AnimationFrames	no
1	AnimationPlays	no

### PNG PrimaryChromaticities Tags

Index4	Tag Name	Writable
0	WhitePointX	no
1	WhitePointY	no
2	RedX	no
3	RedY	no
4	GreenX	no
5	GreenY	no
6	BlueX	no
7	BlueY	no

#### PNG CICodePoints Tags

These tags are found in the PNG cICP chunk and belong to the PNG-cICP family 1 group.

Index1	Tag Name	Writable
0	ColorPrimaries	no
1	TransferCharacteristics	no
2	MatrixCoefficients	no
3	VideoFullRangeFlag	no

#### PNG TextualData Tags

The PNG TextualData format allows arbitrary tag names to be used. The tags listed below are the only ones that can be written (unless new user-defined tags are added via the configuration file), however ExifTool will extract any other TextualData tags that are found. All TextualData tags (including tags not listed below) are removed when deleting all PNG tags.

These tags may be stored as tEXt, zTXt or iTXt chunks in the PNG image. By default ExifTool writes new string-value tags as as uncompressed tEXt, or compressed zTXt if the Compress (-z) option is used and Compress::Zlib is available. Alternate language tags and values containing special characters (unless the Latin character set is used) are written as iTXt, and compressed if the Compress option is used and Compress::Zlib is available. Raw profile information is always created as compressed zTXt if Compress::Zlib is available, or tEXt otherwise. Standard XMP is written as uncompressed iTXt. User-defined tags may set an 'iTXt' flag in the tag definition to be written only as iTXt.

Alternate languages are accessed by suffixing the tag name with a '-', followed by an RFC 3066 language code (eg. "PNG:Comment-fr", or "Title-en-US"). See <a href="http://www.ietf.org/rfc/rfc3066.txt">http://www.ietf.org/rfc/rfc3066.txt</a> for the RFC 3066 specification.

Some of the tags below are not registered as part of the PNG specification, but are included here because they are generated by other software such as ImageMagick.

Tag ID	Tag Name	Writable
	7	
'Artist'	Artist	string
'Author'	Author	string
'Collection'	Collection	string
'Comment'	Comment	string
'Copyright'	Copyright	string
'Creation Time'	CreationTime	string
'Description'	Description	string
'Disclaimer'	Disclaimer	string
'Document'	Document	string
'Label'	Label	string
'Make'	Make	string
'Model'	Model	string
'Raw profile type 8bim'	Photoshop_Profile	Photoshop
'Raw profile type APP1'	APP1_Profile	EXIF
		XMP
'Raw profile type exif'	EXIF_Profile	EXIF
'Raw profile type icc'	ICC_Profile	ICC_Profile
'Raw profile type icm'	ICC Profile	ICC Profile
'Raw profile type iptc'	IPTC Profile	Photoshop
'Raw profile type xmp'	XMP Profile	XMP
'Software'	_ Software	string
'Source'	Source	string
'TimeStamp'	TimeStamp	string
'Title'	Title	string
'URL'	URL	string
'Warning'	PNGWarning	string
'XML:com.adobe.xmp'	XMP	XMP
'aesthetic_score'	AestheticScore	string
'create-date'	CreateDate	string
'modify-date'	ModDate	string
'parameters'	Parameters	string
Parameters	rarameters	act tild

## PNG PhysicalPixel Tags

These tags are found in the PNG pHYs chunk and belong to the PNG-pHYs family 1 group. They are all created together with default values if necessary when any of these tags is written, and may only be deleted as a group.

Index1	Tag Name	Writable
0	PixelsPerUnitX	int32u
4	PixelsPerUnitY	int32u
8	PixelUnits	int8u

## PNG SubjectScale Tags

Index1	Tag Name	Writable
0	SubjectUnits	no
1	SubjectPixelWidth	no
2	SubjectPixelHeight	no

# PNG StereoImage Tags

Index1	Tag Name	Writable
0	StereoMode	no

## PNG VirtualPage Tags

Tag Name	Writable
VirtualImageWidth	no
VirtualImageHeight	no
VirtualPageUnits	no
	 VirtualImageWidth VirtualImageHeight

# MNG Tags

This table contains definitions for tags found in MNG and JNG images. MNG is a superset of PNG and JNG, so a MNG image may contain any of these tags as well as any PNG tags. Conversely, only some of these tags are valid for JNG images.

Tag ID	Tag Name	Writable
'BACK'	Background	MNG Background
'BASI'	BasisObject	MNG BasisObject
'CLIP'	ClipObjects	MNG ClipObjects
'CLON'	CloneObject	MNG CloneObject
'DBYK'	DropByKeyword	no
'DEFI'	DefineObject	MNG DefineObject
'DHDR'	DeltaPNGHeader	MNG DeltaPNGHeader
'DISC'	DiscardObjects	no
'DROP'	DropChunks	no
'FRAM'	Frame	no
'JHDR'	JNGHeader	MNG JNGHeader
'LOOP'	Loop	MNG Loop
'MAGN'	MagnifyObject	MNG MagnifyObject
'MHDR'	MNGHeader	MNG MNGHeader
'MOVE'	MoveObjects	MNG MoveObjects
'ORDR'	OrderingRestrictions	no
'PAST'	PasteImage	MNG PasteImage
'PPLT'	PartialPalette	no
'PROM'	PromoteParent	MNG PromoteParent
'SAVE'	SaveObjects	no
'SEEK'	SeekPoint	no
'SHOW'	ShowObjects	MNG ShowObjects
'TERM'	TerminationAction	MNG TerminationAction
'eXPi'	ExportImage	MNG ExportImage
'fPRI'	FramePriority	MNG FramePriority
'nEED'	ResourcesNeeded	no
'pHYg'	GlobalPixelSize	PNG PhysicalPixel

## MNG Background Tags

Index1	Tag Name	Writable
0	BackgroundColor	no
6	MandatoryBackground	no
7	BackgroundImageID	no
9	BackgroundTiling	no

## MNG BasisObject Tags

Index1	Tag Name	Writable
0	ImageWidth	no
4	ImageHeight	no
8	BitDepth	no
9	ColorType	no
10	Compression	no
11	Filter	no
12	Interlace	no
13	RedSample	no
17	GreenSample	no
21	BlueSample	no
25	AlphaSample	no
26	Viewable	no

## MNG ClipObjects Tags

Index1	Tag Name	Writable
0	FirstObject	no
2	LastObject	no
4	DeltaType	no
5	ClipBoundary	no

# MNG CloneObject Tags

Index1	Tag Name	Writable
0	SourceID	no
2	CloneID	no
4	CloneType	no
5	DoNotShow	no
6	ConcreteFlag	no
7	LocalDeltaType	no
8	DeltaXY	no

# MNG DefineObject Tags

Index1	Tag Name	Writable
0	ObjectID	no
2	DoNotShow	no
3	ConcreteFlag	no
4	XYLocation	no
12	ClippingBoundary	no

# MNG DeltaPNGHeader Tags

Index1	Tag Name	Writable
0	ObjectID	no
2	ImageType	no
3	DeltaType	no
4	BlockSize	no
12	BlockLocation	no

## MNG JNGHeader Tags

Index1	Tag Name	Writable
0	ImageWidth	no
4	ImageHeight	no
8	ColorType	no
9	BitDepth	no
10	Compression	no
11	Interlace	no
12	AlphaBitDepth	no
13	AlphaCompression	no
14	AlphaFilter	no
15	AlphaInterlace	no

# MNG Loop Tags

Index1	Tag Name	Writable
0	NestLevel	no
1	IterationCount	no
5	TerminationCondition	no
6	IterationMinMax	no
14	SignalNumber	no

## MNG MagnifyObject Tags

Index1	Tag Name	Writable
0	FirstObjectID	no
2	LastObjectID	no
4	XMethod	no
5	XMag	no
7	YMag	no
9	LeftMag	no
11	RightMag	no
13	TopMag	no

15	BottomMag	no
17	YMethod	no

# MNG MNGHeader Tags

Index4	Tag Name	Writable
0	ImageWidth	no
1	ImageHeight	no
2	TicksPerSecond	no
3	NominalLayerCount	no
4	NominalFrameCount	no
5	NominalPlayTime	no
6	SimplicityProfile	no

# MNG MoveObjects Tags

Index1	Tag Name	Writable
0	FirstObject	no
2	LastObject	no
4	DeltaType	no
5	DeltaXY	no

## MNG PasteImage Tags

Index1	Tag Name	Writable
0	DestinationID	no
2	TargetDeltaType	no
3	TargetXY	no
11	SourceID	no
13	CompositionMode	no
14	Orientation	no
15	OffsetOrigin	no
16	OffsetXY	no
24	BoundaryOrigin	no
25	PastClippingBoundary	no

## MNG PromoteParent Tags

Index1	Tag Name	Writable
0	NewColorType	no
1	NewBitDepth	no
2	FillMethod	no

# MNG ShowObjects Tags

Index1	Tag Name	Writable
0	FirstObject	no
2	LastObject	no
4	ShowMode	no

# MNG TerminationAction Tags

Index1	Tag Name	Writable
0	TerminationAction	no
1	IterationEndAction	no
2	Delay	no
6	IterationMax	no

## MNG ExportImage Tags

Tag Name	Writable
SnapshotID	no
SnapshotName	no
	SnapshotID

## MNG FramePriority Tags

Index1	Tag Name	Writable
0	DeltaType	no
2	Priority	no

#### FLIF Tags

Information extracted from Free Lossless Image Format files. See
<http://flif.info/> for more information.

Tag ID	Tag Name	Writable
0	ImageType	no
1	BitDepth	no
2	ImageWidth	no
3	ImageHeight	no
4	AnimationFrames	no
5	Encoding	no
'eXif'	EXIF	EXIF
'eXmp'	XMP	XMP
'iCCP'	ICC_Profile	ICC_Profile

### DjVu Tags

Information is extracted from the following chunks in DjVu images. See <a href="http://www.djvu.org/">http://www.djvu.org/</a> for the DjVu specification.

Tag ID	Tag Name	Writable
'ANTa'	ANTa	DjVu Ant
'ANTz'	CompressedAnnotation	DjVu Ant
'FORM'	FORM	DjVu Form
'INCL'	IncludedFileID	no
'INFO'	INFO	DjVu Info

### <u>DjVu</u> <u>Ant</u> <u>Tags</u>

Information extracted from annotation chunks.

Tag ID	Tag Name	Writable
'metadata'	Metadata	DjVu Meta
'xmp'	XMP	XMP

# <u>DjVu Meta Tags</u>

This table lists the standard DjVu metadata tags, but ExifTool will extract any tags that exist even if they don't appear here. The DjVu v3 documentation endorses tags borrowed from two standards: 1) BibTeX bibliography system tags (all lowercase Tag ID's in the table below), and 2) PDF DocInfo tags (capitalized Tag ID's).

Tag ID	Tag Name	Writable
'Author'	Author	no
'CreationDate'	CreateDate	no
'Creator'	Creator	no
'Keywords'	Keywords	no
'ModDate'	ModifyDate	no
'Producer'	Producer	no
'Subject'	Subject	no
'Title'	Title	no
'Trapped'	Trapped	no
'address'	Address	no
'annote'	Annotation	no
'author'	Author	no
'booktitle'	BookTitle	no
'chapter'	Chapter	no
'crossref'	CrossRef	no

'edition'	Edition	no
'eprint'	EPrint	no
'howpublished'	HowPublished	no
'institution'	Institution	no
'journal'	Journal	no
'key'	Key	no
'month'	Month	no
'note'	Note	no
'number'	Number	no
'organization'	Organization	no
'pages'	Pages	no
'publisher'	Publisher	no
'school'	School	no
'series'	Series	no
'title'	Title	no
'type'	Type	no
'url'	URL	no
'volume'	Volume	no
'year'	Year	no

# <u>DjVu Form Tags</u>

Index1	Tag Name	Writable
0	SubfileType	no

# <u>DjVu Info Tags</u>

Index1	Tag Name	Writable
0	ImageWidth	no
2	ImageHeight	no
4	DjVuVersion	no
6	SpatialResolution	no
8	Gamma	no
9	Orientation	no

# DPX Tags

Tags extracted from DPX (Digital Picture Exchange) images.

Index1	Tag Name	Writable
0	ByteOrder	no
8	HeaderVersion	no
16	DPXFileSize	no
20	DittoKey	no
36	ImageFileName	no
136	CreateDate	no
160	Creator	no
260	Project	no
460	Copyright	no
660	EncryptionKey	no
768	Orientation	no
770	ImageElements	no
772	ImageWidth	no
776	ImageHeight	no
780	DataSign	no
800	ComponentsConfiguration	no
801	TransferCharacteristic	no
802	ColorimetricSpecification	no
803	BitDepth	no
820	ImageDescription	no
892	Image2Description	no
964	Image3Description	no
1036	Image4Description	no
1108	Image5Description	no
1180	Image6Description	no
1252	Image7Description	no
1324	Image8Description	no
1432	SourceFileName	no

1532	SourceCreateDate	no
1556	InputDeviceName	no
1588	InputDeviceSerialNumber	no
1628	AspectRatio	no
1724	OriginalFrameRate	no
1728	ShutterAngle	no
1732	FrameID	no
1764	SlateInformation	no
1920	TimeCode	no
1940	FrameRate	no
1972	Reserved5?	no
2048	UserID	no

## OpenEXR Tags

Information extracted from EXR images. Use the ExtractEmbedded option to extract information from all frames of a multipart image. See <a href="http://www.openexr.com/">http://www.openexr.com/</a>> for the official specification.

Tag ID	Tag Name	Writable
'_flags'	Flags	no
'_ver'	EXRVersion	no
'adoptedNeutral'	AdoptedNeutral	no
'altitude'	GPSAltitude	no
'aperture'	Aperture	no
'capDate'	DateTimeOriginal	no
'channels'	Channels	no
'chromaticities'	Chromaticities	no
'chunkCount'	ChunkCount	no
'comments'	Comments	no
'compression'	Compression	no
'dataWindow'	DataWindow	no
'displayWindow'	DisplayWindow	no
'envmap'	EnvironmentMap	no
'exif'	EXIF	EXIF
'expTime'	ExposureTime	no
'focus'	FocusDistance	no
'framesPerSecond'	FramesPerSecond	no
'isoSpeed'	ISO	no
'keyCode'	KeyCode	no
'latitude'	GPSLatitude	no
'lineOrder'	LineOrder	no
'longitude'	GPSLongitude	no
'lookModTransform'	LookModTransform	no
'multiView'	MultiView	no
'name'	Name	no
'owner'	Owner	no
'pixelAspectRatio'	PixelAspectRatio	no
'preview'	Preview	no
'renderingTransform'	RenderingTransform	no
'screenWindowCenter'	_	no
'screenWindowWidth'	ScreenWindowWidth	no
'tiles'	Tiles	no
'timeCode'	TimeCode	no
'type'	Type	no
'utcOffset'	TimeZone	no
'version'	Version	no
'whiteLuminance'	WhiteLuminance	no
'worldToCamera'	WorldToCamera	no
'worldToNDC'	WorldToNDC	no
'wrapmodes'	WrapModes	no
'xDensity'	XResolution	no
'xmp'	XMP	XMP
vmh	771.1T	771,115

## ZISRAW Tags

As well as the header information listed below, ExifTool also extracts the top-level XML-based metadata from Zeiss Integrated Software RAW (ZISRAW) CZI files.

32	ZISRAWVersion	no
48	PrimaryFileGUID	no
64	FileGUID	no

## MRC Tags

Tags extracted from Medical Research Council (MRC) format imaging files. See <a href="https://www.ccpem.ac.uk/mrc\_format/mrc2014.php">https://www.ccpem.ac.uk/mrc\_format/mrc2014.php</a> for the specification.

Index4	Tag Name	Writable
0	ImageWidth	no
1	ImageHeight	no
2	ImageDepth	no
3	ImageMode	no
4	StartPoint	no
7	GridSize	no
10	CellWidth	no
11	CellHeight	no
12	CellDepth	no
13	CellAlpha	no
14	CellBeta	no
15	CellGamma	no
16	ImageWidthAxis	no
17	ImageHeightAxis	no
18	ImageDepthAxis	no
19	DensityMin	no
20	DensityMax	no
21	DensityMean	no
22	SpaceGroupNumber	no
23	ExtendedHeaderSize	no
26	ExtendedHeaderType	no
27	MRCVersion	no
49	Origin	no
53	MachineStamp	no
54	RMSDeviation	no
55	NumberOfLabels	no
56	Label0	no
76	Label1	no
96	Label2	no
116	Label3	no
136	Label4	no
156	Label5	no
176	Label6	no
196	Label7	no
216	Label8	no
236	Label9	no

# MRC FEI12 Tags

Tags extracted from FEI1 and FEI2 extended headers.

Tag Name	Writable
MetadataSize	no
MetadataVersion	no
Bitmask1	no
TimeStamp	no
MicroscopeType	no
MicroscopeID	no
Application	no
AppVersion	no
HighTension	no
Dose	no
AlphaTilt	no
BetaTilt	no
XStage	no
YStage	no
ZStage	no
	MetadataSize MetadataVersion Bitmaskl TimeStamp MicroscopeType MicroscopeID Application AppVersion HighTension Dose AlphaTilt BetaTilt XStage YStage

	ExifTool 13.24 Tag Names	
140	TiltAxisAngle	no
148	DualAxisRot	no
156	PixelSizeX	no
164	PixelSizeY	no
220	Defocus	no
228	STEMDefocus	no
236	AppliedDefocus	no
244	InstrumentMode	no
248	ProjectionMode	no
252	ObjectiveLens	no
268	HighMagnificationMode	no
284 288	ProbeMode EFTEMOn	no
289	Magnification	no no
209	Bitmask2	no
301	CameraLength	no
309	SpotIndex	no
313	IlluminationArea	no
321	Intensity	no
329	ConvergenceAngle	no
337	IlluminationMode	no
353	WideConvergenceAngleRange	no
354	SlitInserted	no
355	SlitWidth	no
363	AccelVoltOffset	no
371	DriftTubeVolt	no
379	EnergyShift	no
387	ShiftOffsetX	no
395	ShiftOffsetY	no
403	ShiftX	no
411	ShiftY	no
419	IntegrationTime	no
427	BinningWidth	no
431	BinningHeight	no
435	CameraName	no
451	ReadoutAreaLeft	no
455	ReadoutAreaTop	no
459	ReadoutAreaRight	no
463 467	ReadoutAreaBottom CetaNoiseReduct	no
468	CetaFramesSummed	no
472	DirectDetElectronCounting	no no
473	DirectDetAlignFrames	no
490	Bitmask3	no
518	PhasePlate	no
519	STEMDetectorName	no
535	Gain	no
543	Offset	no
571	DwellTime	no
579	FrameTime	no
587	ScanSizeLeft	no
591	ScanSizeTop	no
595	ScanSizeRight	no
599	ScanSizeBottom	no
603	FullScanFOV_X	no
611	FullScanFOV_Y	no
619	Element	no
635	EnergyIntervalLower	no
643	EnergyIntervalHigher	no
651	Method	no
655	IsDoseFraction	no
656 660	FractionNumber	no
660 664	StartFrame	no
668	EndFrame InputStackFilename	no
748	InputStackFilename Bitmask4	no
748 752	AlphaTiltMin	no
760	AlphaTiltMax	no no
768	ScanRotation	no
776	DiffractionPatternRotation	no

784	ImageRotation	no
792	ScanModeEnumeration	no
796	AcquisitionTimeStamp	no
804	DetectorCommercialName	no
820	StartTiltAngle	no
828	EndTiltAngle	no
836	TiltPerImage	no
844	TitlSpeed	no
852	BeamCenterX	no
856	BeamCenterY	no
860	CFEGFlashTimeStamp	no
868	PhasePlatePosition	no
872	ObjectiveAperture	no

## LIF Tags

Tags extracted from Leica Image Format (LIF) imaging files. As well as the tags listed below, all available information is extracted from the XML-format metadata in the LIF header.

Tag Name	Writable
TimeStampList	no

## MIFF Tags

The MIFF (Magick Image File Format) format allows aribrary tag names to be used. Only the standard tag names are listed below, however ExifTool will decode any tags found in the image.

Tag ID	Tag Name	Writable
'background-color'	BackgroundColor	no
'blue-primary'	BluePrimary	no
'border-color'	BorderColor	no
'class'	Class	no
'colors'	Colors	no
'colorspace'	ColorSpace	no
'columns'	ImageWidth	no
'compression'	Compression	no
'delay'	Delay	no
'depth'	Depth	no
'dispose'	Dispose	no
'qamma'	Gamma	no
'green-primary'	GreenPrimary	no
'id'	ID	no
'iterations'	Iterations	no
'label'	Label	no
'matt-color'	MattColor	no
'matte'	Matte	no
'montage'	Montage	no
'packets'	Packets	no
'page'	Page	no
'profile-APP1'	APP1_Profile	EXIF
		XMP
'profile-exif'	EXIF_Profile	EXIF
'profile-icc'	ICC_Profile	ICC_Profile
'profile-iptc'	IPTC_Profile	Photoshop
'profile-xmp'	XMP_Profile	XMP
'red-primary'	RedPrimary	no
'rendering-intent'	RenderingIntent	no
'resolution'	Resolution	no
'rows'	ImageHeight	no
'scene'	Scene	no
'signature'	Signature	no
'units'	Units	no
'white-point'	WhitePoint	no

# PCX Tags

Tags extracted from PC Paintbrush images.

0	Manufacturer	no
1	Software	no
2	Encoding	no
3	BitsPerPixel	no
4	LeftMargin	no
6	TopMargin	no
8	ImageWidth	no
10	ImageHeight	no
12	XResolution	no
14	YResolution	no
65	ColorPlanes	no
66	BytesPerLine	no
68	ColorMode	no
70	ScreenWidth	no
72	ScreenHeight	no

## PGF Tags

The following table lists information extracted from the header of Progressive Graphics File (PGF) images. As well, information is extracted from the embedded PNG metadata image if it exists. See <a href="http://www.libpgf.org/">http://www.libpgf.org/</a> for the PGF specification.

Index1	Tag Name	Writable
3	PGFVersion	no
8	ImageWidth	no
12	ImageHeight	no
16	PyramidLevels	no
17	Quality	no
18	BitsPerPixel	no
19	ColorComponents	no
20	ColorMode	no
21	BackgroundColor	no

## PSP Tags

Tags extracted from Paint Shop Pro images (PSP, PSPIMAGE, PSPFRAME, PSPSHAPE, PSPTUBE and TUB extensions).

Tag ID	Tag Name	Writable
'FileVersion'	FileVersion	no
$0 \times 0000$	ImageInfo	PSP Image
		PSP Image
0x0001	CreatorInfo	PSP Creator
0x000a	ExtendedInfo	PSP Ext

## PSP Image Tags

Index1	Tag Name	Writable
0	ImageWidth	no
4	ImageHeight	no
8	ImageResolution	no
16	ResolutionUnit	no
17	Compression	no
19	BitsPerSample	no
21	Planes	no
23	NumColors	no

## PSP Creator Tags

Tag Name	Writable
Title	no
CreateDate	no
ModifyDate	no
Artist	no
Copyright	no
Description	no
	Title CreateDate ModifyDate Artist Copyright

$0 \times 0006$	CreatorAppID	no
0x0007	CreatorAppVersion	no

## PSP Ext Tags

Tag ID	Tag Name	Writable
0x0003	EXIFInfo	EXIF

#### PhotoCD Tags

Tags extracted from Kodak Photo CD Image Pac (PCD) files.

Index1	Tag Name	Writable
 7	SpecificationVersion	no
9	AuthoringSoftwareRelease	no
11	ImageMagnificationDescriptor	no
13	CreateDate	no
17	ModifyDate	no
21	ImageMedium	no
22	ProductType	no
42	ScannerVendorID	no
62	ScannerProductID	no
78	ScannerFirmwareVersion	no
82	ScannerFirmwareDate	no
90	ScannerSerialNumber	no
110	ScannerPixelSize	no
112	ImageWorkstationMake	no
132	CharacterSet	no
133	CharacterEscapeSequence?	no
165	PhotoFinisherName	no
228	SceneBalanceAlgorithmRevision	no
230	SceneBalanceAlgorithmCommand	no
325	SceneBalanceAlgorithmFilmID	no
331	CopyrightStatus	no
332	CopyrightFileName	no
1538	Orientation	no
1538.1	ImageWidth	no
1538.2	ImageHeight	no
1538.3	CompressionClass	no

## Radiance Tags

Information extracted from Radiance RGBE HDR images. Tag ID's are all uppercase as stored in the file, but converted to lowercase by when extracting to avoid conflicts with internal ExifTool variables. See <a href="http://radsite.lbl.gov/radiance/refer/filefmts.pdf">http://radsite.lbl.gov/radiance/refer/filefmts.pdf</a> and <a href="http://www.graphics.cornell.edu/online/formats/rgbe/">http://www.graphics.cornell.edu/online/formats/rgbe/</a> for the specification.

Tag ID	Tag Name	Writable
'_command'	Command	no
'_comment'	Comment	no
'_orient'	Orientation	no
'colorcorr'	ColorCorrection	no
'exposure'	Exposure	no
'format'	Format	no
'gamma'	Gamma	no
'pixaspect'	PixelAspectRatio	no
'primaries'	ColorPrimaries	no
'software'	Software	no
'view'	View	no

# Other PFM Tags

Tags extracted from Portable FloatMap images. See
<http://www.pauldebevec.com/Research/HDR/PFM/> for the specification.

Tag Name	Writable

ByteOrder	no
ColorSpace	no
ImageHeight	no
ImageWidth	no

#### PDF Tags

The tags listed in the PDF tables below are those which are used by ExifTool to extract meta information, but they are only a small fraction of the total number of available PDF tags. See <a href="http://www.adobe.com/devnet/pdf/pdf\_reference.html">http://www.adobe.com/devnet/pdf/pdf\_reference.html</a> for the official PDF specification.

ExifTool supports reading and writing PDF documents up to version 2.0, including support for RC4, AES-128 and AES-256 encryption. A Password option is provided to allow processing of password-protected PDF files.

ExifTool may be used to write native PDF and XMP metadata to PDF files. It uses an incremental update technique that has the advantages of being both fast and reversible. If ExifTool was used to modify a PDF file, the original may be recovered by deleting the "PDF-update" pseudo-group (with "-PDF-update:all=" on the command line). However, there are two main disadvantages to this technique:

- 1) A linearized PDF file is no longer linearized after the update, so it must be subsequently re-linearized if this is required.
- 2) All metadata edits are reversible. While this would normally be considered an advantage, it is a potential security problem because old information is never actually deleted from the file. (However, after running ExifTool the old information may be removed permanently using the "qpdf" utility with this command: "qpdf --linearize in.pdf out.pdf".)

Tag ID	Tag Name	Writable
'Encrypt'	Encrypt	PDF Encrypt
'Info'	Info	PDF Info
'Root'	Root	PDF Root
' linearized'	Linearized	no

### PDF Encrypt Tags

Tags extracted from the document Encrypt dictionary.

Tag ID	Tag Name	Writable
'Filter'	Encryption	no
'P'	UserAccess	no

## PDF Info Tags

As well as the tags listed below, the PDF specification allows for user-defined tags to exist in the Info dictionary. These tags, which should have corresponding XMP-pdfx entries in the XMP of the PDF XML Metadata object, are also extracted by ExifTool.

Writable specifies the value format, and may be "string", "date", "integer", "real", "boolean" or "name" for PDF tags.

'AAPL:Keywords' AppleKeywords string+ 'Author' Author string 'CreationDate' CreateDate date 'Creator' Creator string 'Keywords' Keywords string+ 'ModDate' ModifyDate date 'Producer' Producer string 'SourceModified' SourceModified date	Tag ID	Tag Name	Writable
Subject Subject String	'Author' 'CreationDate' 'Creator' 'Keywords' 'ModDate' 'Producer'	Author CreateDate Creator Keywords ModifyDate Producer	string date string string+ date string

## -- ExifTool 13.24 Tag Names --

'Title'	Title	string
'Trapped'	Trapped	string!

## PDF Root Tags

This is the PDF document catalog.

Tag ID	Tag Name	Writ	able
'AF'	AF	PDF	AF
'AcroForm'	AcroForm	PDF	AcroForm
'Lang'	Language	no	
'MarkInfo'	MarkInfo	PDF	MarkInfo
'Metadata'	Metadata	PDF	Metadata
'PageLayout'	PageLayout	no	
'PageMode'	PageMode	no	
'Pages'	Pages	PDF	Pages
'Perms'	Perms	PDF	Perms
'Version'	PDFVersion	no	

## PDF AF Tags

Processed only for C2PA information if AFRelationship is  $"/C2PA\_Manifest"$ .

Tag ID	Tag Name	Writable
'EF'	EF	PDF EF

## PDF EF Tags

Tag ID	Tag Name	Writable
'F'	F_	PDF F

# PDF F Tags

C2PA JUMBF metadata extracted from "/C2PA\_Manifest" file.

Tag ID	Tag Name	Writable
'_stream'	JUMBF	Jpeg2000

## PDF AcroForm Tags

Tag ID	Tag Name	Writable
'_has_xfa'	HasXFA	no

# PDF MarkInfo Tags

Tag ID	Tag Name	Writable
'Marked'	TaggedPDF	no

## PDF Metadata Tags

Tag ID	Tag Name	Writable
'XML_stream'	XMP	XMP

#### PDF Pages Tags

Tag ID	Tag Name	Writable
'Count' 'Kids'	PageCount Kids	no PDF Kids

# PDF Kids Tags

#### -- ExifTool 13.24 Tag Names --

Tag Name Tag ID Writable \_\_\_\_\_ \_\_\_\_\_ 'Kids' Kids
'Metadata' Metadata
'PieceInfo' PieceInfo
'Resources' Resources PDF Kids PDF Metadata PDF PieceInfo PDF Resources

## PDF PieceInfo Tags

Tag ID Tag Name Writable \_\_\_\_\_

'AdobePhotoshop' AdobePhotoshop 'Illustrator' Illustrator PDF AdobePhotoshop PDF Illustrator

#### PDF AdobePhotoshop Tags

Tag ID Tag Name Writable 'Private' Private PDF Private

#### PDF Private Tags

Tag Name Tag ID Writable ----\_\_\_\_\_

'ImageResources' ImageResources PDF ImageResources

#### PDF ImageResources Tags

Tag ID Tag Name Writable '\_stream' PhotoshopStream Photoshop

### PDF Illustrator Tags

Tag ID Tag Name Writable -----'Private' Private PDF AIPrivate

#### PDF AIPrivate Tags

Tag Name Writable Tag ID

'AIMetaData' AIMetaData PDF AIMetaData
'AIPDFPrivateData' AIPDFPrivateData PostScript
'AIPrivateData' AIPrivateData PostScript
'ContainerVersion' ContainerVersion no
'CreatorVersion' CreatorVersion no
'RoundTripVersion' RoundTripVersion no

### PDF AIMetaData Tags

rag ID Tag Name Tag ID Writable '\_stream' AIStream PostScript

#### PDF Resources Tags

Tag ID Tag Name Writable -----

'ColorSpace' ColorSpace 'Properties' Properties PDF ColorSpace PDF Properties 'XObject' PDF XObject X0bject

# PDF ColorSpace Tags

Tag ID Tag Name Writable

'CS0' CS0 PDF DefaultRGB PDF DefaultRGB Cs1 'DefaultCMYK' DefaultCMYK PDF DefaultRGB

'DefaultRGB' DefaultRGB PDF DefaultRGB

## PDF DefaultRGB Tags

Tag ID	Tag Name	Writ	table
'ICCBased'	ICCBased	PDF	ICCBased

## PDF ICCBased Tags

Tag ID	Tag Name	Writable
'_stream'	ICC_Profile	ICC_Profile

## PDF Properties Tags

Tag ID	Tag Name	Writable
'MC'	MC	PDF MC

## PDF MC Tags

Tag ID	Tag Name	Writable
'Metadata'	Metadata	PDF Metadata

## PDF XObject Tags

Tag ID	Tag Name	Writable
'Im'	Im	PDF Im

## PDF Im Tags

Information extracted from embedded images with the ExtractEmbedded option. The EmbeddedImage and its metadata are extracted only for JPEG and Jpeg2000 image formats.

Tag ID	Tag Name	Writable
'ColorSpace'	EmbeddedImageColorSpace	no+
'Filter'	EmbeddedImageFilter	no+
'Height'	EmbeddedImageHeight	no
'Image_stream'	EmbeddedImage	no
'Width'	EmbeddedImageWidth	no

## PDF Perms Tags

Additional document permissions imposed by digital signatures.

Tag ID	Tag Name	Writable
'DocMDP'	DocMDP	PDF Signature
'FieldMDP'	FieldMDP	PDF Signature
'UR3'	UR3	PDF Signature

## PDF Signature Tags

Tag ID	Tag Name	Writable
'ContactInfo'	SignerContactInfo	no
'Location'	SigningLocation	no
' M '	SigningDate	no
'Name'	SigningAuthority	no
'Prop_AuthTime'	AuthenticationTime	no
'Prop_AuthType'	AuthenticationType	no
'Reason'	SigningReason	no
'Reference'	Reference	PDF Reference

# PDF Reference Tags

Tag ID Tag Name Writable

'TransformParams' TransformParams PDF TransformParams

#### PDF TransformParams Tags

Tag ID Tag Name Writable \_\_\_\_\_ 'Action' 'Annots' FieldPermissions AnnotationUsageRights no+ 'Document' DocumentUsageRights EmbeddedFileUsageRights no+ 'EF' 'Fields' FormFields 'Form' FormUsageRights no+ FormExtraUsageRights no+ 'FormEX' 'Msq' UsageRightsMessage no ModificationPermissions no 'P' 'Signature' SignatureUsageRights no+

### PostScript Tags

Tag ID	Tag Name	Writable
'AI12 BuildNumber'	AIBuildNumber	no
'AI3_ColorUsage'	AIColorUsage	no
'AI5_FileFormat'	AIFileFormat	no
'AI5_NumLayers'	AINumLayers	no
'AI5_RulerUnits'	AIRulerUnits	no
'AI5_TargetResolution'	AITargetResolution	no
'AI8_CreatorVersion'	AICreatorVersion	no
'AI9_ColorModel'	AIColorModel	no
'Author'	Author	string
'BeginDocument'	EmbeddedFile	PostScript
'BeginICCProfile'	ICC_Profile	ICC_Profile
'BeginPhotoshop'	PhotoshopData	Photoshop
'BoundingBox'	BoundingBox	no
'Copyright'	Copyright	string
'CreationDate'	CreateDate	string
'Creator'	Creator	string
'EmbeddedFileName'	EmbeddedFileName	no
'For'	For	string
'ImageData'	ImageData	no
'Keywords'	Keywords	string
'ModDate'	ModifyDate	string
'Pages'	Pages	no
'Routing'	Routing	string
'Subject'	Subject	string
'TIFFPreview'	TIFFPreview	no
'Title'	Title	string
'Version'	Version	string
'begin_xml_packet'	XMP	XMP

## ID3 Tags

ExifTool extracts ID3 and Lyrics3 information from MP3, MPEG, WAV, AIFF, OGG, FLAC, APE, MPC and RealAudio files. ID3v2 tags which support multiple languages (eg. Comment and Lyrics) are extracted by specifying the tag name, followed by a dash ('-'), then a 3-character ISO 639-2 language code (eg. "Comment-spa"). See <a href="https://id3.org/">https://id3.org/</a> for the official ID3 specification and <a href="http://www.loc.gov/standards/iso639-2/php/code\_list.php">http://www.loc.gov/standards/iso639-2/php/code\_list.php</a> for a list of ISO 639-2 language codes.

Tag Name	Writable
ID3v1	ID3 v1
ID3v1_Enh	ID3 v1_Enh
ID3v2_2	ID3 v2_2
ID3v2_3	ID3 v2_3
ID3v2_4	ID3 v2_4

## ID3 v1 Tags

Index1	Tag Name	Writable
3	Title	no
33	Artist	no
63	Album	no
93	Year	no
97	Comment	no
125	Track	no
127	Genre	no

## ID3 v1 Enh Tags

ID3 version 1 "Enhanced TAG" information (not part of the official spec).

Tag Name	Writable
Title2	no
Artist2	no
Album2	no
Speed	no
Genre	no
StartTime	no
EndTime	no
	Title2 Artist2 Album2 Speed Genre StartTime

# ID3 v2 2 Tags

ExifTool extracts mainly text-based tags from ID3v2 information. The tags in the tables below are those extracted by ExifTool, and don't represent a complete list of available ID3v2 tags.

ID3 version 2.2 tags. (These are the tags written by iTunes 5.0.)

Tag ID	Tag Name	Writable
'CNT'	PlayCounter	no
'COM'	Comment	no
'GP1'	Grouping	no
'IPL'	InvolvedPeople	no
'ITU'	iTunesU?	no
'MVI'	MovementNumber	no
' MVN '	MovementName	no
'PCS'	Podcast?	no
'PIC'	Picture	no
'PIC-1'		no
'PIC-2'	21	no
'PIC-3'	PictureDescription	no
'POP'	Popularimeter	no
'RVA'	RelativeVolumeAdjustment	no
'SLT'	SynLyrics	ID3 SynLyrics
'TAL'	Album	no
'TBP'	BeatsPerMinute	no
'TCM'	Composer	no
'TCO'	Genre	no
'TCP'	Compilation	no
'TCR'	Copyright	no
'TDA'	Date	no
'TDY'	PlaylistDelay	no
'TEN'	EncodedBy	no
'TFT'	FileType	no
'TIM'	Time	no
'TKE'	InitialKey	no
'TLA'	Language	no
'TLE'	Length	no
'TMT'	Media	no
'TOA'	OriginalArtist	no
'TOF'	OriginalFileName	no
'TOL'	OriginalLyricist	no

'TOR'	OriginalReleaseYear	no
'TOT'	OriginalAlbum	no
'TP1'	Artist	no
'TP2'	Band	no
'TP3'	Conductor	no
'TP4'	InterpretedBy	no
'TPA'	PartOfSet	no
'TPB'	Publisher	no
'TRC'	ISRC	no
'TRD'	RecordingDates	no
'TRK'	Track	no
'TS2'	AlbumArtistSortOrder	no
'TSA'	AlbumSortOrder	no
'TSC'	ComposerSortOrder	no
'TSI'	Size	no
'TSP'	PerformerSortOrder	no
'TSS'	EncoderSettings	no
'TST'	TitleSortOrder	no
'TT1'	Grouping	no
'TT2'	Title	no
'TT3'	Subtitle	no
'TXT'	Lyricist	no
'TXX'	UserDefinedText	no
'TYE'	Year	no
'ULT'	Lyrics	no
'WAF'	FileURL	no
'WAR'	ArtistURL	no
'WAS'	SourceURL	no
'WCM'	CommercialURL	no
'WCP'	CopyrightURL	no
'WPB'	PublisherURL	no
'WXX'	UserDefinedURL	no

## ID3 SynLyrics Tags

The following tags are extracted from synchronized lyrics/text frames.

Tag Name	Writable
SynchronizedLyricsDescription	no
SynchronizedLyricsText	no+
SynchronizedLyricsType	no

# ID3 v2 3 Tags

ID3 version 2.3 tags. Includes some non-standard tags written by other software.

Tag ID	Tag Name	Writable
'APIC'	Picture	no
'APIC-1'	PictureMIMEType	no
'APIC-2'	PictureType	no
'APIC-3'	PictureDescription	no
'COMM'	Comment	no
'GEOB'	GeneralEncapsulatedObject	ID3 GEOB
'GRP1'	Grouping	no
'IPLS'	InvolvedPeople	no
'ITNU'	iTunesU?	no
'MCDI'	MusicCDIdentifier	no
'MVIN'	MovementNumber	no
' MVNM '	MovementName	no
'OWNE'	Ownership	no
'PCNT'	PlayCounter	no
'PCST'	Podcast?	no
'POPM'	-1	no
'PRIV'	Private	ID3 Private
'SYLT'	SynLyrics	ID3 SynLyrics
'TALB'		no
'TBPM'	BeatsPerMinute	no

'TCAT'	PodcastCategory	no
'TCMP'	Compilation	no
'TCOM'	Composer	no
'TCON'	Genre	no
'TCOP'	Copyright	no
'TDAT'	Date	no
'TDES'	PodcastDescription	no
'TDLY'	PlaylistDelay	
	EncodedBy	no
'TENC' 'TEXT'		no
	Lyricist	no
'TFLT'	FileType	no
'TGID'	PodcastID	no
'TIME'	Time	no
'TIT1'	Grouping	no
'TIT2'	Title	no
'TIT3'	Subtitle	no
'TKEY'	InitialKey	no
'TKWD'	PodcastKeywords	no
'TLAN'	Language	no
'TLEN'	Length	no
'TMED'	Media	no
'TOAL'	OriginalAlbum	no
'TOFN'	OriginalFileName	no
'TOLY'	OriginalLyricist	no
'TOPE'	OriginalArtist	no
'TORY'	OriginalReleaseYear	no
'TOWN'	FileOwner	no
'TPE1'	Artist	no
'TPE2'	Band	no
'TPE3'	Conductor	no
'TPE4'	InterpretedBy	no
'TPOS'	PartOfSet	no
'TPUB'	Publisher	no
'TRCK'	Track	no
'TRDA'	RecordingDates	no
'TRSN'	InternetRadioStationName	no
'TRSO'	InternetRadioStationOwner	no
'TSIZ'	Size	no
'TSO2'	AlbumArtistSortOrder	
'TSOC'	ComposerSortOrder	no
'TSRC'	ISRC	no
		no
'TSSE'	EncoderSettings	no
'TXXX'	UserDefinedText	no
'TYER'	Year	no
'USER'	TermsOfUse	no
'USLT'	Lyrics	no
'WCOM'	CommercialURL	no
'WCOP'	CopyrightURL	no
'WFED'	PodcastURL	no
'WOAF'	FileURL	no
'WOAR'	ArtistURL	no
'WOAS'	SourceURL	no
'WORS'	${ t Internet Radio Station URL}$	no
'WPAY'	PaymentURL	no
'WPUB'	PublisherURL	no
'WXXX'	UserDefinedURL	no
'XDOR'	OriginalReleaseTime	no
'XOLY'	OlympusDSS	Olympus DSS
'XSOA'	AlbumSortOrder	no
'XSOP'	PerformerSortOrder	no
'XSOT'	TitleSortOrder	no
-		

# ID3 GEOB Tags

Tag ID	Tag Name	Writable
'GEOB-Data'	GEOB-Data	no
'GEOB-Desc'	GEOB-Desc	no
'GEOB-File'	GEOB-File	no
'GEOB-Mime'	GEOB-Mime	no

'application/x-c2pa-manifest-store' JUMBF Jpeg2000

# ID3 Private Tags

ID3 private (PRIV) tags. ExifTool will decode any private tags found, even if they do not appear in this table.

Tag Name	Writable
AverageLevel	no
PeakValue	no
WM_CollectionGroupID	no
WM_CollectionID	no
WM_ContentID	no
WM_MediaClassPrimaryID	no
WM_MediaClassSecondaryID	no
WM_Provider	no
XMP	XMP

## ID3 v2 4 Tags

 $\ensuremath{\text{ID3}}$  version 2.4 tags. Includes some non-standard tags written by other software.

ortware.			
Tag ID	Tag Name	Writable	€
	Diatumo		-
'APIC'		no	
	PictureMIMEType	no	
	PictureType	no	
	PictureDescription	no	
'COMM'	Comment	no	
'GEOB'	GeneralEncapsulatedObject	ID3 GEOR	3
'GRP1'	Grouping	no	
'ITNU'	iTunesU?	no	
'MCDI'	MusicCDIdentifier	no	
'MVIN'	MovementNumber	no	
' MVNM '	MovementName	no	
'OWNE'	Ownership	no	
'PCNT'	PlayCounter	no	
'PCST'	Podcast?	no	
'POPM'	Popularimeter	no	
'PRIV'	Private	ID3 Priv	<i>r</i> ate
'RVA2'	RelativeVolumeAdjustment	no	
'SYLT'	SynLyrics	ID3 SynI	Lyrics
'TALB'	Album	no	-
'TBPM'	BeatsPerMinute	no	
'TCAT'	PodcastCategory	no	
'TCMP'	Compilation	no	
'TCOM'	Composer	no	
'TCON'	Genre	no	
'TCOP'	Copyright	no	
'TDEN'	EncodingTime	no	
'TDES'	PodcastDescription	no	
'TDLY'	PlaylistDelay	no	
'TDOR'	OriginalReleaseTime		
'TDRC'	RecordingTime	no	
'TDRL'	ReleaseTime	no	
		no	
'TDTG'	TaggingTime	no	
'TENC'	EncodedBy	no	
'TEXT'	Lyricist	no	
'TFLT'	FileType	no	
'TGID'	PodcastID	no	
'TIPL'	InvolvedPeople	no	
'TIT1'	Grouping	no	
'TIT2'	Title	no	
'TIT3'	Subtitle	no	
'TKEY'	InitialKey	no	
'TKWD'	PodcastKeywords	no	
'TLAN'	Language	no	
'TLEN'	Length	no	

'TMCL'	MusicianCredits	
'TMED'	Media	no
'TMOO'	Mood	no
'TOAL'	OriginalAlbum	no
'TOFN'	_	no
_	OriginalFileName	no
'TOLY'	OriginalLyricist	no
'TOPE'	OriginalArtist	no
'TOWN'	FileOwner	no
'TPE1'	Artist	no
'TPE2'	Band	no
'TPE3'	Conductor	no
'TPE4'	InterpretedBy	no
'TPOS'	PartOfSet	no
'TPRO'	ProducedNotice	no
'TPUB'	Publisher	no
'TRCK'	Track	no
'TRSN'	InternetRadioStationName	no
'TRSO'	InternetRadioStationOwner	no
'TSO2'	AlbumArtistSortOrder	no
'TSOA'	AlbumSortOrder	no
'TSOC'	ComposerSortOrder	no
'TSOP'	PerformerSortOrder	no
'TSOT'	TitleSortOrder	no
'TSRC'	ISRC	no
'TSSE'	EncoderSettings	no
'TSST'	SetSubtitle	no
'TXXX'	UserDefinedText	no
'USER'	TermsOfUse	no
'USLT'	Lyrics	no
'WCOM'	CommercialURL	no
'WCOP'	CopyrightURL	no
'WFED'	PodcastURL	no
'WOAF'	FileURL	no
'WOAR'	ArtistURL	no
'WOAS'	SourceURL	no
'WORS'	InternetRadioStationURL	no
'WPAY'	PaymentURL	no
'WPUB'	PublisherURL	no
'WXXX'	UserDefinedURL	no
'XDOR'	OriginalReleaseTime	no
'XOLY'	OlympusDSS	Olympus DSS
'XSOA'	AlbumSortOrder	no
'XSOP'	PerformerSortOrder	no
'XSOT'	TitleSortOrder	no
22001	I I CICDOI COLUCI	110

# ID3 Lyrics3 Tags

ExifTool extracts Lyrics3 version 1.00 and 2.00 tags from any file that supports ID3. See <a href="https://id3.org/Lyrics3">https://id3.org/Lyrics3</a> for the specification.

Tag ID	Tag Name	Writable
'AUT'	Author	no
'CRC'	CRC	no
'EAL'	ExtendedAlbumName	no
'EAR'	ExtendedArtistName	no
'ETT'	ExtendedTrackTitle	no
'IMG'	AssociatedImageFile	no
'IND'	Indications	no
'INF'	AdditionalInfo	no
'LYR'	Lyrics	no

# ITC Tags

This information is found in iTunes Cover Flow data files.

Tag ID	Tag Name	Writable
'data'	ImageData	no
'itch'	Itch	ITC Header
'item'	Item	ITC Item

#### ITC Header Tags

Index1	Tag Name	Writable
16	DataType	no

#### ITC Item Tags

Index4	Tag Name	Writable
0	LibraryID	no
2	TrackID	no
4	DataLocation	no
5	ImageType	no
7	ImageWidth	no
8	ImageHeight	no

#### QuickTime Tags

The QuickTime format is used for many different types of audio, video and image files (most notably, MOV/MP4 videos and HEIC/CR3 images). ExifTool extracts standard meta information and a variety of audio, video and image parameters, as well as proprietary information written by many camera models. Tags with a question mark after their name are not extracted unless the Unknown option is set.

When writing video files, ExifTool creates both QuickTime and XMP tags by default, but the group may be specified to write one or the other separately. If no location is specified, newly created QuickTime tags are added in the ItemList location if possible, otherwise in UserData, and finally in Keys, but this order may be changed by setting the PREFERRED level of the appropriate table in the config file (see example.config in the full distribution for an example). Note that some tags with the same name but different ID's may exist in the same location, but the family 7 group names may be used to differentiate these.

ExifTool currently writes ItemList and UserData only as top-level metadata, but select Keys tags are may be written to the audio or video track. See the AudioKeys and VideoKeys tags for more information.

Alternate language tags may be accessed for ItemList and Keys tags by adding a 3-character ISO 639-2 language code and an optional ISO 3166-1 alpha 2 country code to the tag name (eg. "ItemList:Artist-deu" or "ItemList:Artist-deu-DE"). Most UserData tags support a language code, but without a country code. If no language code is specified when writing, the default language is written and alternate languages for the tag are deleted. Use the "und" language code to write the default language without deleting alternate languages. Note that when reading, "eng" is also treated as the default language if there is no country code.

According to the specification, integer-format QuickTime date/time tags should be stored as UTC. Unfortunately, digital cameras often store local time values instead (presumably because they don't know the time zone). For this reason, by default ExifTool does not assume a time zone for these values. However, if the API QuickTimeUTC option is set, then ExifTool will assume these values are properly stored as UTC, and will convert them to local time when extracting.

When writing string-based date/time tags, the system time zone is added if the PrintConv option is enabled and no time zone is specified. This is because Apple software may display crazy values if the time zone is missing for some tags.

By default ExifTool will remove null padding from some QuickTime containers in Canon CR3 files when writing, but the QuickTimePad option may be used to preserve the original size by padding with nulls if necessary.

See

<https://developer.apple.com/library/archive/documentation/QuickTime/QTFF/>
for the official QuickTime specification.

Tag ID	Tag Name	Writable
'GPS '	GPSDataList2?	no
'IDIT'	DateTimeOriginal	string
'PICT'	PreviewPICT	no
'SEAL'	SEAL	XMP SEAL
'_htc'	HTCInfo	QuickTime HTCInfo
'ardt'	ARDroneFile	no
'cust'	CustomInfo	no
'frea'	Kodak_frea	Kodak frea
'free'	KodakFree	Kodak Free
	Pittasoft ThumbnailImage Free?	QuickTime Pittasoft no no
'ftyp'	FileType	QuickTime FileType
'gdat'	GPSData	QuickTime FileType QuickTime Stream
'gps0'	GPSTrack	QuickTime Stream
'gsen'	GSensor	QuickTime Stream QuickTime Stream
'junk'	Junk?	no
'mdat'	MediaData?	no
'mdat-offset'	MediaData: MediaDataOffset	no
'mdat-size'	MediaDataSize	no
'meco'	OtherMeta	QuickTime OtherMeta
'meta'	Meta	QuickTime Meta
'moof'	MovieFragment	QuickTime Meta QuickTime MovieFragment
'moov'	Movie	QuickTime Movie  QuickTime Movie
'mpvd'	MotionPhotoVideo	yes
'nbmt'	NextbaseMeta	QuickTime Stream
'pict'	PreviewPICT	no
'pnot'	Preview	OuickTime Preview
'prrt'	ARDroneTelemetry	no
'sefd'	SamsungTrailer	Samsung Trailer
'skip'	CanonSkip	Canon Skip
Silip	PreviewImage	no
	SkipInfo	QuickTime Stream
	LigoGPSInfo	-
	Skip?	no
'thm '	ThumbnailImage	no
'thum'	ThumbnailImage	no
'udat'	GPSLog	no
'udta'	KenwoodData	QuickTime Stream
	LigoJSON	QuickTime Stream
	FLIRData	FLIR UserData
'uuid'	XMP	XMP
	UUID-PROF	QuickTime Profile
	UUID-Flip	QuickTime Flip
	UUID-Canon2	Canon uuid2
	SensorData	QuickTime Tags360Fly
	SensorData	no
	JUMBF	Jpeg2000
	CBOR	CBOR
	PreviewImage	no
	ThumbnailImage	no
	UUID-Unknown?	no
'wide'	Wide?	no

# QuickTime Stream Tags

The tags below are extracted from timed metadata in QuickTime and other formats of video files when the ExtractEmbedded option is used. Although most of these tags are combined into the single table below, ExifTool currently reads 103 different types of timed GPS metadata from video files.

Tag	Name	Writable

```
Accelerometer
                                                 no
AccelerometerData
                                                 nο
AngularVelocity
                                                 no
CTMD
                                                 Canon CTMD
CameraDateTime
                                                 no
CameraModel
                                                 no
Car
                                                 no
DJIDebug?
                                                 DJI Protobuf
DJIMetadata
                                                 DJI Protobuf
DateTimeOriginal
                                                 no
DateTimeStamp
                                                 no
Distance
                                                 no
ExposureCompensation
                                                 no
ExposureTime
                                                 no
FNumber
                                                 no
FrameNumber
                                                 no
GPSAltitude
                                                 no
GPSDOP
                                                 no
GPSDateTime
                                                 no
GPSLatitude
GPSLatitude2
GPSLongitude
                                                 no
GPSLongitude2
                                                 no
GPSSatellites
                                                 no
GPSSpeed
                                                 no
GPSSpeedRef
                                                 no
GPSTimeStamp
                                                 nο
GPSTrack
                                                 no
GPSTrackRef
                                                 no
GSensor
                                                 no
INSV
                                                 QuickTime INSV_MakerNotes
ISO
JpgFromRaw
KiloCalories
                                                 no
MagneticVariation
                                                 no
PreviewImage
                                                 no
                                                 QuickTime PreviewInfo
PreviewInfo
                                                 QuickTime RVMI_gReV
RVMI_gReV
                                                 QuickTime RVMI_sReV
RVMI_sReV
RawGSensor
                                                 no
SampleDateTime
                                                 no
SampleDuration
                                                 no
SampleTime
                                                 no
Text
                                                 no
TimeCode
                                                 nο
Unknown00?
                                                 no
Unknown01?
                                                 nο
Unknown02?
                                                 nο
Unknown03?
                                                 nο
UserLabel
                                                 no
VerticalSpeed
                                                 no
VideoTimeStamp
                                                 nο
camm0
                                                 OuickTime camm0
camm1
                                                 OuickTime camm1
                                                 OuickTime camm2
camm2
                                                 OuickTime camm3
camm3
camm4
                                                 QuickTime camm4
camm5
                                                 QuickTime camm5
camm6
                                                 QuickTime camm6
                                                 QuickTime camm7
camm7
fdsc
                                                 GoPro fdsc
gpmd_Kingslim
                                                 QuickTime Stream
                                                 QuickTime Stream
gpmd_Rove
                                                 QuickTime Stream
gpmd_FMAS
gpmd_Wolfbox
                                                 OuickTime Stream
gpmd_GoPro
                                                 GoPro GPMF
marl
                                                 GM marl
mebx
                                                 QuickTime Keys
mett
                                                 Parrot mett
```

Sony rtmd

rtmd

tx3g QuickTime tx3g

# <u>QuickTime</u> <u>INSV MakerNotes</u> <u>Tags</u>

Tag ID	Tag Name	Writable
0x000a	SerialNumber	no
$0 \times 0012$	Model	no
0x001a	Firmware	no
0x002a	Parameters	no

### QuickTime PreviewInfo Tags

Preview stored by TomTom Bandit ActionCam.

Index1	Tag Name	Writable
8	PreviewImage	no

#### QuickTime RVMI gReV Tags

GPS information extracted from the RVMI box of MOV videos.

Index1	Tag Name	Writable
4	GPSLatitude	no
8	GPSLongitude	no
16	GPSSpeed	no
18	GPSTrack	no

#### QuickTime RVMI sReV Tags

G-sensor information extracted from the RVMI box of MOV videos.

Index1	Tag Name	Writable
4	GSensor	no

## QuickTime camm0 Tags

The camm0 through camm7 tables define tags extracted from the Google Street View Camera Motion Metadata of MP4 videos. See <a href="https://developers.google.com/streetview/publish/camm-spec">https://developers.google.com/streetview/publish/camm-spec</a> for the specification.

Tag ID	Tag Name	Writable
$0 \times 0004$	AngleAxis	no

## QuickTime camm1 Tags

Tag ID	Tag Name	Writable
$0 \times 0004$	PixelExposureTime	no
0x0008	RollingShutterSkewTime	no

# QuickTime camm2 Tags

Tag ID	Tag Name	Writable
$0 \times 0004$	AngularVelocity	no

## QuickTime camm3 Tags

Tag ID	Tag Name	Writable
$0 \times 0004$	Acceleration	no

## QuickTime camm4 Tags

Tag ID	Tag Name	Writable
0x0004	Position	no

## QuickTime camm5 Tags

Tag ID	Tag Name	Writable
$0 \times 0004$	GPSLatitude	no
0x000c	GPSLongitude	no
$0 \times 0014$	GPSAltitude	no

## QuickTime camm6 Tags

Tag ID	Tag Name	Writable
$0 \times 0004$	GPSDateTime	no
0x000c	GPSMeasureMode	no
$0 \times 0010$	GPSLatitude	no
$0 \times 0018$	GPSLongitude	no
$0 \times 0020$	GPSAltitude	no
$0 \times 0024$	GPSHorizontalAccuracy	no
$0 \times 0028$	GPSVerticalAccuracy	no
0x002c	GPSVelocityEast	no
$0 \times 0030$	GPSVelocityNorth	no
$0 \times 0034$	GPSVelocityUp	no
0x0038	GPSSpeedAccuracy	no

## QuickTime camm7 Tags

Tag ID	Tag Name	Writable
$0 \times 0004$	MagneticField	no

## <u>QuickTime Keys Tags</u>

This directory contains a list of key names which are used to decode tags written by the "mdta" handler. Also in this table are a few tags found in timed metadata that are not yet writable by ExifTool. The prefix of "com.apple.quicktime." has been removed from the TagID's below. These tags support alternate languages in the same way as the ItemList tags. Note that by default, ItemList and UserData tags are preferred when writing, so to create a tag when a same-named tag exists in either of these tables, either the "Keys" location must be specified (eg. "-Keys:Author=Phil" on the command line), or the PREFERRED level must be changed via the config file.

Tag ID	Tag Name	Writable
'album'	' EncodedWith Album .variation-identifier'	yes yes
'artist' 'artwork' 'author' 'collection.u' 'com.android.' 'com.android.' 'com.android.' 'com.android.'	ApplePhotosVariationIdentifier Artist Artwork	int64s yes yes yes yes float yes yes int32s
'comment' 'compatible_b' 'content.iden 'copyright' 'creation_tim	XiaomiPreviewVideoCover Comment rands' CompatibleBrands tifier' ContentIdentifier	int32s yes yes/ yes yes yes/ yes

```
'description' Description
                                               yes
'detected-face' FaceInfo
                                               QuickTime FaceInfo
'detected-face.bounds' DetectedFaceBounds
                                               no
'detected-face.face-id' DetectedFaceID
                                               no
'detected-face.roll-angle'
              DetectedFaceRollAngle
                                               no
'detected-face.yaw-angle'
              DetectedFaceYawAngle
'direction.facing' CameraDirection
                                               yes
'direction.motion' CameraMotion
                                               yes
'director' Director
                                               yes
'displayname' DisplayName
                                               yes
'encoder' Encoder
                                               yes
'full-frame-rate-playback-intent'
             FullFrameRatePlaybackIntent
                                               yes
'genre'
             Genre
                                               yes
'information' Information
                                               yes
'keywords' Keywords
                                               yes
'live-photo-info' LivePhotoInfo
'live-photo.auto' LivePhotoAuto
                                               no
                                               int8u
'live-photo.vitality-score'
              LivePhotoVitalityScore
                                               float
'live-photo.vitality-scoring-version'
              LivePhotoVitalityScoringVersion int64s
'location.ISO6709' GPSCoordinates
'location.accuracy.horizontal'
             LocationAccuracyHorizontal
                                               yes
'location.body' LocationBody
                                               yes
'location.date' LocationDate
                                               ves
'location.name' LocationName
                                               ves
'location.note' LocationNote
                                               yes
'location.role' LocationRole
                                               yes
'major brand' MajorBrand
                                               yes/
'make'
             Make
                                               yes
'minor version' MinorVersion
                                               yes/
            Model
'model'
                                               ves
'player.movie.audio.balance' Balance
                                               yes
'player.movie.audio.bass' Bass
                                               ves
'player.movie.audio.gain' AudioGain
                                               yes
'player.movie.audio.mute' Mute
                                               int8u
'player.movie.audio.pitchshift' PitchShift
                                               yes
'player.movie.audio.treble' Treble
                                               yes
'player.movie.visual.brightness' Brightness
                                               yes
'player.movie.visual.color' Color
                                               yes
'player.movie.visual.contrast' Contrast
                                               yes
'player.movie.visual.tint' Tint
                                               yes
'player.version' PlayerVersion
                                               ves
'producer'
            Producer
                                               yes
'publisher'
             Publisher
                                               yes
'rating.user' UserRating
                                               yes
'scene-illuminance' SceneIlluminance
                                               no
'software' Software
                                               yes
'still-image-time' StillImageTime
                                               no
'title'
             Title
                                               ves
'version'
             Version
                                               ves
'video-orientation' VideoOrientation
                                               no
'xiaomi.exifInfo.videoinfo' XiaomiExifInfo
                                               yes
'year'
             Year
                                               yes
```

#### QuickTime AudioKeys Tags

Keys tags written in the audio track by some Apple devices. These tags belong to the ExifTool AudioKeys family 1 gorup.

Tag ID	Tag Name	Writable
'player.movie.audio.balance'	Balance	yes
'player.movie.audio.bass'	Bass	yes
'player.movie.audio.gain'	AudioGain	yes
'player.movie.audio.mute'	Mute	int8u

'player.movie.audio.pitchshift' PitchShift yes 'player.movie.audio.treble' Treble yes

# QuickTime VideoKeys Tags

Keys tags written in the video track. These tags belong to the ExifTool VideoKeys family 1 gorup.

Tag ID	Tag Name	Writable
'camera.focal_length.	35mm_equivalent'	
	FocalLengthIn35mmFormat	yes
'camera.framereadoutt	imeinmicroseconds'	
	FrameReadoutTime	yes
'camera.identifier'	CameraIdentifier	yes
'camera.lens_model'	LensModel	yes
'com.apple.photos.cap	tureMode' CaptureMode	yes

## QuickTime FaceInfo Tags

Tag ID	Tag Name	Writable
'crec'	FaceRec	QuickTime FaceRec

## QuickTime FaceRec Tags

Tag ID	Tag Name	Writable
'cits'	FaceItem	QuickTime Keys

## QuickTime tx3g Tags

Tags extracted from the tx3g sbtl timed metadata of Yuneec and Autel drones, and subtitle text in some other videos.

Tag ID	Tag Name	Writable
'Alt'	GPSAltitude	no
'DateTime'	DateTime	no
'EV'	ExposureCompensation	no
'F-NUM'	FNumber	no
'GPSDateTime'	GPSDateTime	no
'GimPitch'	GimbalPitch	no
'GimRoll'	GimbalRoll	no
'GimYaw'	GimbalYaw	no
'HomeLat'	GPSHomeLatitude	no
'HomeLon'	GPSHomeLongitude	no
'ISO'	ISO	no
'Lat'	GPSLatitude	no
'Lon'	GPSLongitude	no
'Pitch'	Pitch	no
'Roll'	Roll	no
'SHUTTER'	ExposureTime	no
'Text'	Text	no
'Yaw'	Yaw	no

#### QuickTime HTCInfo Tags

Tags written by some HTC camera phones.

Tag ID	Tag Name	Writable
'slmt'	Unknown_slmt?	no

## QuickTime Pittasoft Tags

Tags found in Pittasoft Blackvue dashcam "free" data.

Tag ID	Tag Name	Writable

12af 1	AccelData	QuickTime	Ctroom
'cprt.'	Copyright	no	Stream
'aps '	Copyright GPSLog OriginalFileName	no	
'ptnm'	OriginalFileName	no	
'ptrh'	Ptrh	_	Pittasoft
	StartTime	no	110000010
	PreviewImage	no	
CITAIN	110v10w1mage	110	
<u>QuickTime</u>	FileType Tags		
	Tag Name	Writable	
	MajorBrand	no	
	MinorVersion	no	
2	CompatibleBrands	no+	
2	compact 21 cD1 and	110 .	
<u>QuickTime</u>	OtherMeta Tags		
Tag ID	Tag Name	Writable	
	MetaRelation	OuickTime	MetaRelation
'meta'		QuickTime	
llicca	Meta	Quichillic	neca
<u>QuickTime</u>	MetaRelation Tags		
Index4	Tag Name	Writable	
[no tags	known]		
<u>QuickTime</u>	Meta Tags		
Tag ID	Tag Name	Writable	
'bxml'	BinaryXML?	no	
	DataInfo	QuickTime	DataInfo
'free'	Free?	no	
'grpl'	Unknown_grpl	QuickTime	grpl
	Handler	QuickTime	Handler
'idat'	MetaImageSize	no	
'iinf'	ItemInformation	QuickTime	ItemInfo
		QuickTime	ItemInfo
'iloc'	ItemLocation	no	
'ilst'	ItemList	QuickTime	ItemList
'ipmc'	IPMPControl?	no	
'ipro'	ItemProtection?	no	
'iprp'	ItemProperties	QuickTime	_
'iref'	ItemReference	QuickTime	
'keys'	AudioKeys		AudioKeys
	VideoKeys		VideoKeys
	Keys	QuickTime	Keys
'pitm'	PrimaryItemReference	no	
'uuid'	MetaVersion	no	
	UUID-Unknown?	no	
'xml '	XML	XMP XML	
<u>QuickTime</u>	DataInfo Tags		
MP4 data i	information box.		
Tag ID	Tag Name	Writable	
'dref'	DataRef	QuickTime	DataRef
<u>QuickTime</u>	<u>DataRef</u> <u>Tags</u>		
MP4 data r	reference box.		

Writable

no

Tag ID Tag Name

"url\0" URL

'url ' URL no 'urn ' URN no

## QuickTime grpl Tags

Tag ID Tag Name Writable
----[no tags known]

#### QuickTime Handler Tags

Index1	Tag Name	Writable
4	HandlerClass	no
8	HandlerType	no
12	HandlerVendorID	no
24	HandlerDescription	no

## QuickTime ItemInfo Tags

Tag ID Tag Name Writable
----- 'infe' ItemInfoEntry no

#### QuickTime ItemList Tags

This is the preferred location for creating new QuickTime tags. Tags in this table support alternate languages which are accessed by adding a 3-character ISO 639-2 language code and an optional ISO 3166-1 alpha 2 country code to the tag name (eg. "ItemList:Title-fra" or "ItemList::Title-fra-FR"). When creating a new Meta box to contain the ItemList directory, by default ExifTool adds an 'mdir' (Metadata) Handler box because Apple software may ignore ItemList tags otherwise, but the API QuickTimeHandler option may be set to 0 to avoid this.

Tag ID	Tag Name	Writable
''	iTunesInfo	QuickTime iTunesInfo
'@PST'	ParentShortTitle	string
'@ppi'	ParentProductID	string
'@pti'	ParentTitle	string
'@sti'	ShortTitle	string
'AACR'	Unknown_AACR?	string
'CDEK'	Unknown_CDEK?	string
'CDET'	Unknown_CDET?	string
'GUID'	GUID	string
'VERS'	ProductVersion	string
'aART'	AlbumArtist	string
'akID'	AppleStoreAccountType	int8s
'albm'	Album	string/
'apID'	AppleStoreAccount	string
'atID'	ArtistID	int32s
'auth'	Author	string
'catg'	Category	string
'cmID'	ComposerID	string
'cnID'	AppleStoreCatalogID	int32s
'covr'	CoverArt	string
'cpil'	Compilation	int8s
'cprt'	Copyright	string
'desc'	Description	string/
'disk'	DiskNumber	undef
'dscp'	Description	string/
'egid'	EpisodeGlobalUniqueID	string
'geID'	GenreID	int32s
'gnre'	Genre	undef/
'grup'	Grouping	string/
'gshh'	GoogleHostHeader	string
'gspm'	GooglePingMessage	string
'gspu'	GooglePingURL	string
'gssd'	GoogleSourceData	string

	ExifTool 1	3.24 Tag	Names	
'gsst'	GoogleStartTime			string
'gstd'	GoogleTrackDurat	ion		string
'hdvd'	HDVideo			int8s
'itnu'	iTunesU			int8s
'keyw'	Keyword			string
'ldes'	LongDescription			string
'ownr'	Owner			string
'pcst'	Podcast			int8s
'perf'	Performer			string
'pgap'	PlayGap			int8s
'plID'	AlbumID			int32s[2]
'prID'	ProductID			string
'purd'	PurchaseDate			string
'purl'	PodcastURL			string
'rate' 'rldt'	RatingPercent ReleaseDate			string string
'rtng'	Rating			int8s
'sdes'	StoreDescription			string
'sfID'	AppleStoreCountr	V		int32s
'shwm'	ShowMovement	2		int8s
'snal'	PreviewImage			string
'soaa'	SortAlbumArtist			string
'soal'	SortAlbum			string
'soar'	SortArtist			string
'soco'	SortComposer			string
'sonm'	SortName			string
'sosn'	SortShow			string
'stik'	MediaType			int8s
'titl'	Title			string/
'tmpo'	BeatsPerMinute			int16s
'tnal' 'trkn'	ThumbnailImage TrackNumber			string undef
'tven'	TVEpisodeID			string
'tves'	TVEpisode			int32s
'tvnn'	TVNetworkName			string
'tvsh'	TVShow			string
'tvsn'	TVSeason			int32u
'xid '	ISRC			string
'yrrc'	Year			string
"\xa9ART"	Artist			string
"\xa9alb"	Album			string
"\xa9ard"	ArtDirector			string
"\xa9arg"	Arranger			string
"\xa9aut" "\xa9cmt"	Author			string/
"\xa9cm"	Comment Composer			string string/
"\xa9con"	Conductor			string
"\xa9cpy"	Copyright			string/
"\xa9day"	ContentCreateDat	e		string
"\xa9des"	Description			string
"\xa9dir"	Director			string
"\xa9enc"	EncodedBy			string
"\xa9gen"	Genre			string
"\xa9grp"	Grouping			string
"\xa9lyr"	Lyrics			string
"\xa9mvc"	MovementCount			int16s
"\xa9mvi"	MovementNumber			int16s
"\xa9mvn" "\xa9nam"	MovementName Title			string string
"\xa9nrt"	Narrator			string
"\xa9ope"	OriginalArtist			string
"\xa9prd"	Producer			string
"\xa9pub"	Publisher			string
"\xa9sne"	SoundEngineer			string
"\xa9sol"	Soloist			string
"\xa9st3"	Subtitle			string
"\xa9too"	Encoder			string
"\xa9trk"	Track			string
"\xa9wrk" "\xa9wrt"	Work			string string
\vaywr L	Composer			p CT T11A

# QuickTime iTunesInfo Tags

ExifTool will extract any iTunesInfo tags that exist, even if they are not defined in this table. These tags belong to the family 1 "iTunes" group, and are not currently writable.

Tag ID	Tag Name	Writable
'ARTISTS'	Artists	no
'Actors'	Actors	no
'BARCODE'	Barcode	no
'CATALOGNUMBER'	CatalogNumber	no
'COSTUME_DESIGNER'	CostumeDesigner Director	no
'DIRECTOR'		no
'DIRECTOR_OF_PHOTOGRAPH		
LDICONIMPEDI	DirectorOfPhotography	
'DISCNUMBER'	DiscNumber	no
'Dynamic Range (DR)'	DynamicRange	no
'Dynamic Range (R128)'	DynamicRangeR128	no
'EDITED_BY'	EditedBy	no
'Encoding Params'	EncodingParams	QuickTime EncodingParams
'IMDB_ID'	IMDB_ID	no
'LABEL'	Label	no
'MEDIA'	Media	no
'MOOD'	Mood	no
'PRODUCER'	Producer	no
'PRODUCTION_DESIGNER'	ProductionDesigner	no
'Peak Level (R128)'	PeakLevelR128	no
'Peak Level (Sample)'	PeakLevelSample	no
'RATING'	Rating	no
'SCREENPLAY_BY'	ScreenplayBy	no
'SCRIPT'	Script	no
'TIPL'	TIPL	no
'TMDB_ID'	TMDB_ID	no
'TRACKNUMBER'	TrackNumber	no
'Volume Level (R128)'	VolumeLevelR128	no
'Volume Level (ReplayGa	in)' ReplayVolumeLevel	no
'iTunEXTC'	ContentRating	no
'iTunMOVI'	iTunMOVI	PLIST
'iTunNORM'	VolumeNormalization	no
'iTunSMPB'	iTunSMPB	no
'iTunes_CDDB_1'	CDDB1Info	no
'iTunes_CDDB_TrackNumbe	r' CDDBTrackNumber	no
'initialkey'	InitialKey	no
'originaldate'	OriginalDate	no
'originalyear'	OriginalYear	no
'popularimeter'	Popularimeter	no
'replaygain_track_gain'	-	no
'replaygain_track_peak'		no
'tool'	iTunTool	no
'~length'	Length	no
5	_	

# QuickTime EncodingParams Tags

Tag ID	Tag Name	Writable
'abrt'	AudioAvailableBitRateRange	no
'acbf'	AudioBitRateControlMode	no
'acef'	AudioExtendFrequencies	no
'brat'	AudioCurrentTargetBitRate	no
'cdcv'	AudioComponentVersion	no
'cmnc'	AudioAvailableNumberChannels	no
'init'	AudioIsInitialized	no
'lmrc'	AudioDoesSampleRateConversion	no
'mdel'	AudioMinimumDelayMode	no
'mnip'	AudioMinimumNumberInputPackets	no
'mnop'	AudioMinimumNumberOutputPackets	no

'oppr'	AudioOutputPrecedence	no
'pad0'	AudioZeroFramesPadded	no
'pakb'	AudioMaximumPacketByteSize	no
'pakd'	AudioRequiresPacketDescription	no
'pakf'	AudioPacketFrameSize	no
'prmm'	AudioCodecPrimeMethod	no
'srcq'	AudioQualitySetting	no
'tbuf'	AudioInputBufferSize	no
'ubuf'	AudioUsedInputBufferSize	no
'ursr'	AudioUseRecommendedSampleRate	no
'vbrq'	AudioVBRQuality	no
'vers'	AudioEncodingParamsVersion	no
'vpk?'	AudioHasVariablePacketByteSizes	no

# QuickTime ItemProp Tags

Tag ID	Tag Name	Writable
'ipco' 'ipma'	ItemPropertyContainer ItemPropertyAssociation	QuickTime ItemPropCont no

## QuickTime ItemPropCont Tags

Tag ID	Tag Name	Writable
'auxC'	AuxiliaryImageType	no
'av1C'	AV1Configuration	QuickTime AV1Config
'clap'	CleanAperture	no
'clli'	ContentLightLevel	QuickTime ContentLightLevel
'colr'	ICC_Profile	ICC_Profile
	ColorRepresentation	QuickTime ColorRep
'hvcC'	HEVCConfiguration	QuickTime HEVCConfig
'irot'	Rotation	int8u!
'ispe'	ImageSpatialExtent	no
'pasp'	PixelAspectRatio	int32u!
'pixi'	ImagePixelDepth	no
'rloc'	RelativeLocation	no

# QuickTime AV1Config Tags

Index1	Tag Name	Writable
0	AV1ConfigurationVersion	no
1	SeqProfile?	no
1.1	SeqLevelIdx0?	no
2	SeqTier0?	no
2.1	HighBitDepth?	no
2.2	TwelveBit?	no
2.3	ChromaFormat	no
2.4	ChromaSamplePosition	no
3	InitialDelaySamples?	no

# QuickTime ContentLightLevel Tags

Index2	Tag Name	Writable
0	MaxContentLightLevel	no
1	MaxPicAverageLightLevel	no

# QuickTime ColorRep Tags

Index1	Tag Name	Writable
0	ColorProfiles	no
4	ColorPrimaries	no
6	TransferCharacteristics	no
8	MatrixCoefficients	no
10	VideoFullRangeFlag	no

# QuickTime HEVCConfig Tags

Index1	Tag Name	Writable
0	HEVCConfigurationVersion	no
1	GeneralProfileSpace	no
1.1	GeneralTierFlag	no
1.2	GeneralProfileIDC	no
2	GenProfileCompatibilityFlags	no
6	ConstraintIndicatorFlags	no
12	GeneralLevelIDC	no
13	MinSpatialSegmentationIDC	no
15	ParallelismType	no
16	ChromaFormat	no
17	BitDepthLuma	no
18	BitDepthChroma	no
19	AverageFrameRate	no
21	ConstantFrameRate	no
21.1	NumTemporalLayers	no
21.2	TemporalIDNested	no

## QuickTime ItemRef Tags

The Item reference entries listed in the table below contain information about the associations between items in the file. This information is used by ExifTool, but these entries are not extracted as tags.

Tag ID	Tag Name	Writable
'auxl' 'cdsc' 'dimg'	AuxiliaryImageRef ContentDescribes DerivedImageRef	no no no
'thmb'	ThumbnailRef	no

# <u>QuickTime</u> <u>MovieFragment</u> <u>Tags</u>

Tag ID	Tag Name	Writable
'meta'	Meta	QuickTime Meta
'mfhd'	MovieFragmentHeader	QuickTime MovieFragHdr
'traf'	TrackFragment	QuickTime TrackFragment

## QuickTime MovieFragHdr Tags

Index4	Tag Name	Writable
1	MovieFragmentSequence	no

# QuickTime TrackFragment Tags

Tag ID	Tag Name	Writable
'meta'	Meta	QuickTime Meta

## QuickTime Movie Tags

Tag ID	Tag Name	Writable
'cmov'	CompressedMovie	QuickTime CMovie
'gps '	GPSDataList?	no
'htka'	HTCTrack	QuickTime Track
'iods'	InitialObjectDescriptor?	no
'meco'	OtherMeta	QuickTime OtherMeta
'meta'	Meta	QuickTime Meta
'mvhd'	MovieHeader	QuickTime MovieHeader
'trak'	Track	QuickTime Track
'udta'	UserData	QuickTime UserData
'uuid'	UUID-USMT	QuickTime UserMedia
	UUID-Canon	Canon uuid
	GarminGPS	QuickTime Stream

GarminGPS no UUID-Unknown? no

# QuickTime CMovie Tags

Tag ID	Tag Name	Writable
'dcom'	Compression	no

## QuickTime Track Tags

Tag ID	Tag Name	Writable
'mdia'	Media	QuickTime Media
'meco'	OtherMeta	QuickTime OtherMeta
'meta'	Meta	QuickTime Meta
'tapt'	TrackAperture	QuickTime TrackAperture
'tkhd'	TrackHeader	QuickTime TrackHeader
'tref'	TrackRef	QuickTime TrackRef
'udta'	UserData	QuickTime UserData
'uuid'	UUID-USMT	QuickTime UserMedia
	SphericalVideoXML	XMP
	UUID-Unknown?	no

# QuickTime Media Tags

## MP4 media box.

Tag ID	Tag Name	Writable
'hdlr'	Handler	QuickTime Handler
'mdhd'	MediaHeader	QuickTime MediaHeader
'minf'	MediaInfo	QuickTime MediaInfo

## QuickTime MediaHeader Tags

Index4	Tag Name	Writable
0	MediaHeaderVersion	no
1	MediaCreateDate	int32u
2	MediaModifyDate	int32u
3	MediaTimeScale	no
4	MediaDuration	no
5	MediaLanguageCode	no

## QuickTime MediaInfo Tags

# MP4 media info box.

Tag ID	Tag Name	Writable	
'dinf'	DataInfo	QuickTime	DataInfo
'gmhd'	GenMediaHeader	QuickTime	GenMediaHeader
'hdlr'	Handler	QuickTime	Handler
'hmhd'	HintHeader	QuickTime	HintHeader
'nmhd'	NullMediaHeader?	no	
'smhd'	AudioHeader	QuickTime	AudioHeader
'stbl'	SampleTable	QuickTime	SampleTable
'vmhd'	VideoHeader	QuickTime	VideoHeader

# QuickTime GenMediaHeader Tags

Tag ID	Tag Name	Writable
'gmin'	GenMediaInfo	QuickTime GenMediaInfo
'text'	Text?	no
'tmcd'	TimeCode	QuickTime TimeCode

## QuickTime GenMediaInfo Tags

Index1	Tag Name	Writable
0	GenMediaVersion	no
1	GenFlags	no
4	GenGraphicsMode	no
6	GenOpColor	no
12	GenBalance	no

# QuickTime TimeCode Tags

Tag ID	Tag Name	Writable

'tcmi' TCMediaInfo QuickTime TCMediaInfo

# <u>QuickTime</u> <u>TCMediaInfo</u> <u>Tags</u>

Index1	Tag Name	Writable
4	TextFont	no
6	TextFace	no
8	TextSize	no
12	TextColor	no
18	BackgroundColor	no
24	FontName	no

# QuickTime HintHeader Tags

MP4 hint media header.

Index2	Tag Name	Writable
2	MaxPDUSize	no
3	AvgPDUSize	no
4	MaxBitrate	no
6	AvgBitrate	no

# QuickTime AudioHeader Tags

MP4 audio media header.

Index2	Tag Name	Writable
2	Balance	no

# QuickTime SampleTable Tags

MP4 sample table box.

Taq ID	Tag Name	Writable	
'co64'	ChunkOffset64?	no	
'cslg'	CompositionToDecodeTimelineMapping?	no	
'ctts'	CompositionTimeToSample?	no	
'padb'	SamplePaddingBits?	no	
'sbgp'	SampleToGroup?	no	
'sdtp'	IdependentAndDisposableSamples?	no	
'sgpd'	SampleGroupDescription?	no	
'stco'	ChunkOffset?	no	
'stdp'	SampleDegradationPriority?	no	
'stps'	PartialSyncSamples	no	
'stsc'	SampleToChunk?	no	
'stsd'	AudioSampleDesc	QuickTime	AudioSampleDesc
	VisualSampleDesc	QuickTime	VisualSampleDesc
	HintSampleDesc	QuickTime	HintSampleDesc
	MetaSampleDesc	QuickTime	MetaSampleDesc
	OtherSampleDesc	QuickTime	OtherSampleDesc
'stsh'	ShadowSyncSampleTable?	no	
'stss'	SyncSampleTable?	no	
'stsz'	SampleSizes?	no	
'stts'	VideoFrameRate	no	

## -- ExifTool 13.24 Tag Names --

	TimeToSampleTable?	no
'stz2'	CompactSampleSizes?	no
'subs'	Sub-sampleInformation?	no

# <u>QuickTime</u> <u>AudioSampleDesc</u> <u>Tags</u>

 $\mbox{MP4}$  audio sample description. This hybrid atom contains both data and child atoms.

ID/Index	Tag Name	Writable
4	AudioFormat	no
20	AudioVendorID	no
24	AudioChannels	no
26	AudioBitsPerSample	no
32	AudioSampleRate	no
'SA3D'	SpatialAudio	QuickTime SpatialAudio
'btrt'	BitrateInfo	QuickTime Bitrate
'chan'	AudioChannelLayout	QuickTime ChannelLayout
'damr'	DecodeConfig	QuickTime DecodeConfig
'pinf'	PurchaseInfo	QuickTime ProtectionInfo
'sinf'	ProtectionInfo	QuickTime ProtectionInfo
'wave'	Wave	QuickTime Wave

# QuickTime SpatialAudio Tags

Spatial Audio tags.

Index1	Tag Name	Writable
0	SpatialAudioVersion	no
1	AmbisonicType	no
2	AmbisonicOrder	no
6	AmbisonicChannelOrdering	no
7	AmbisonicNormalization	no
8	AmbisonicChannels	no
12	AmbisonicChannelMap	no

# QuickTime Bitrate Tags

Index4	Tag Name	Writable
0	BufferSize	no
1	MaxBitrate	no
2	AverageBitrate	no

# QuickTime ChannelLayout Tags

Audio channel layout.

Index1	Tag Name	Writable
4	LayoutFlags	no
6	AudioChannels	no
8	AudioChannelTypes	no
12	NumChannelDescriptions	no
16	Channel1Label	no
20	Channel1Flags	no
24	Channel1Coordinates	no
36	Channel2Label	no
40	Channel2Flags	no
44	Channel2Coordinates	no
56	Channel3Label	no
60	Channel3Flags	no
64	Channel3Coordinates	no
76	Channel4Label	no
80	Channel4Flags	no
84	Channel4Coordinates	no
96	Channel5Label	no
100	Channel5Flags	no

## -- ExifTool 13.24 Tag Names --

104	Channel5Coordinates	no
116	Channel6Label	no
120	Channel6Flags	no
124	Channel6Coordinates	no
136	Channel7Label	no
140	Channel7Flags	no
144	Channel7Coordinates	no
156	Channel8Label	no
160	Channel8Flags	no
164	Channel8Coordinates	no

## QuickTime DecodeConfig Tags

Index1	Tag Name	Writable
0	EncoderVendor	no
4	EncoderVersion	no

## QuickTime ProtectionInfo Tags

Child atoms found in "sinf" and/or "pinf" atoms.

Tag ID	Tag Name	Writable	
'enda'	Endianness	no	
'frma'	OriginalFormat	no	
'schi'	SchemeInfo	QuickTime	SchemeInfo
'schm'	SchemeType	OuickTime	SchemeType

# QuickTime SchemeInfo Tags

Tag Name	Writable
Certificate	no
InitializationVector	no
KeyID	no
UserName	no
Rights	QuickTime Rights
UserID	no
	Certificate InitializationVector KeyID UserName Rights

# QuickTime Rights Tags

Tag ID	Tag Name	Writable
'aver'	VersionRestrictions	no
'medi'	MediaFlags	no
'mode'	ModeFlags	no
'plat'	Platform	no
'song'	ItemID	no
'tool'	ItemTool	no
'tran'	TransactionID	no
'veID'	ItemVendorID	no

# QuickTime SchemeType Tags

Index1	Tag Name	Writable
4	SchemeType	no
8	SchemeVersion	no
10	SchemeURL	no

## QuickTime Wave Tags

Tag ID	Tag Name	Writable
'enda'	Endianness	no
'frma'	PurchaseFileFormat	no

## QuickTime VisualSampleDesc Tags

ID/Index	Tag Name	Writable
2	CompressorID	no
10	VendorID	no
16	SourceImageWidth	no
17	SourceImageHeight	no
18	XResolution	no
20	YResolution	no
25	CompressorName	no
41	BitDepth	no
'CDI1'	CDI1	Canon CDI1
'CMP1'	CMP1	Canon CMP1
'JPEG'	JPEGInfo?	no
'avcC'	AVCConfiguration?	no
'btrt'	BitrateInfo	QuickTime Bitrate
'clap'	CleanAperture	QuickTime CleanAperture
'colr'	ColorRepresentation	QuickTime ColorRep
'fiel'	VideoFieldOrder	no
'gama'	Gamma	no
'pasp'	PixelAspectRatio	no
'st3d'	Stereoscopic3D	no
'sv3d'	SphericalVideo	QuickTime sv3d
uickTime	CleanAperture Tags	

# <u>QuickTime</u> <u>CleanAperture</u> <u>Tags</u>

Index8	Tag Name	Writable
0	CleanApertureWidth	no
1	CleanApertureHeight	no
2	CleanApertureOffsetX	no
3	CleanApertureOffsetY	no

# QuickTime sv3d Tags

d>

Tags defined by the Spherical Video V2 specification. See <a href="https://github.com/google/spatial-media/blob/master/docs/spherical-video-v2-rfc.m">https://github.com/google/spatial-media/blob/master/docs/spherical-video-v2-rfc.m</a>

for the specification.

Tag ID	Tag Name	Writable
'proj'	Projection	QuickTime proj
'svhd'	MetadataSource	no

# QuickTime proj Tags

Tag ID	Tag Name	Writable
'cbmp'	CubemapProj	QuickTime cbmp
'equi'	EquirectangularProj	QuickTime equi
'prhd'	ProjectionHeader	QuickTime prhd

# QuickTime cbmp Tags

Index4	Tag Name	Writable
1	Layout	no
2	Padding	no

# QuickTime equi Tags

Index4	Tag Name	Writable
1	ProjectionBoundsTop	no
2	ProjectionBoundsBottom	no
3	ProjectionBoundsLeft	no
4	ProjectionBoundsRight	no

# QuickTime prhd Tags

no
no
no

# QuickTime HintSampleDesc Tags

MP4 hint sample description.

ID/Index	Tag Name	Writable
4	HintFormat	no
16	HintTrackVersion	no
20	MaxPacketSize	no
'snro'	SequenceNumberRandomOffset	no
'tims'	RTPTimeScale	no
'tsro'	TimestampRandomOffset	no

# QuickTime MetaSampleDesc Tags

MP4 metadata sample description.

Tag ID Tag Name	Writable
0x0004 MetaFormat	no
0x0008 MetaType	no
'btrt' BitrateInfo	QuickTime Bitrate
'keys' Keys	QuickTime Keys

# <u>QuickTime</u> <u>OtherSampleDesc</u> <u>Tags</u>

Tag ID	Tag Name	Writable
$0 \times 0004$	OtherFormat	no
$0 \times 0018$	PlaybackFrameRate	no
'ftab'	FontTable	no
'mrld'	MarlinDictionary	GM mrld
'mrlh'	MarlinHeader	GM mrlh
'mrlv'	MarlinValues	GM mrlv
'name'	OtherName	no

## QuickTime VideoHeader Tags

MP4 video media header.

Index2	Tag Name	Writable
2	GraphicsMode	no
3	OpColor	no

# QuickTime TrackAperture Tags

Tag ID	Tag Name	Writable
'clef'	CleanApertureDimensions	no
'enof'	EncodedPixelsDimensions	no
'prof'	ProductionApertureDimensions	no

# QuickTime TrackHeader Tags

Index4	Tag Name	Writable
0	TrackHeaderVersion	no
1	TrackCreateDate	int32u
2	TrackModifyDate	int32u
3	TrackID	no
5	TrackDuration	no
8	TrackLayer	no
9	TrackVolume	no

10	MatrixStructure	fixed32s[9]!
19	ImageWidth	no
20	ImageHeight	no

# QuickTime TrackRef Tags

Tag ID	Tag Name	Writable
'cdsc'	ContentDescribes	no
'chap'	ChapterListTrackID	no
'mpod'	ElementaryStreamTrack	no
'tmcd'	TimeCode	no

#### QuickTime UserData Tags

Tag ID's beginning with the copyright symbol (hex 0xa9) are multilanguage text. Alternate language tags are accessed by adding a dash followed by a 3-character ISO 639-2 language code to the tag name. ExifTool will extract any multi-language user data tags found, even if they aren't in this table. Note when creating new tags, ItemList tags are preferred over these, so to create the tag when a same-named ItemList tag exists, either "UserData" must be specified (eg. "-UserData:Artist=Monet" on the command line), or the PREFERRED level must be changed via the config file.

Tag ID	Tag Name	Writable
 '@day'	ContentCreateDate	string/
'@mak'	Make	string/
'@mod'	Model	string/
'@sec'	SamsungSec	Samsung sec
'@swr'	SoftwareVersion	string/
'@xyz'	GPSCoordinates	string/
'AllF'	PlayAllFrames	int8u
'CAME'	SerialNumberHash	string
'CNCV'	CompressorVersion	string
'CNFV'	FirmwareVersion	string
'CNMN'	Model	string/
'CNOP'	CanonCNOP	Canon CNOP
'CNTH'	CanonCNTH	Canon CNTH
'DcMD'	KodakDcMD	Kodak DcMD
'FFMV'	FujiFilmFFMV	FujiFilm FFMV
'FIRM'	FirmwareVersion	string/
"FOV\0"	FieldOfView	string
'GPMF'	GoProGPMF	GoPro GPMF
'GoPr'	GoProType	string
'INFO'	SamsungINFO	Samsung INFO
'LEIC'	LeicaLEIC	Panasonic PANA
'LENS'	LensSerialNumber	string
'LOOP'	LoopStyle	int32u
'Lvlm'	LevelMeter?	rational64s
'MMAO'	MinoltaMMA0	Minolta MMA
'MMA1'	MinoltaMMA1	Minolta MMA
'MUID'	MediaUID	no
'MVTG'	FujiFilmMVTG	EXIF
'NCDT'	NikonNCDT	Nikon NCDT
'PANA'	PanasonicPANA	Panasonic PANA
'PENT'	PentaxPENT	Pentax PENT
'PXMN'	MakerNotePentax5b	Pentax
	MakerNotePentax5c	Pentax
	MakerNotePentaxUnknown	string
'PXTH'	PentaxPreview	Pentax PXTH
'QVMI'	CasioQVMI	EXIF
'RDTA'	RicohRDTA	Ricoh RDTA
'RDTB'	RicohRDTB	Ricoh RDTB
'RDTC'	RicohRDTC	Ricoh RDTC
'RDTG'	RicohRDTG	Ricoh RDTG
'RDTL'	RicohRDTL	Ricoh RDTL
'RICO'	RicohInfo	JPEG
'RMKN'	RicohRMKN	EXIF

'RTHU'	PreviewImage	no
'SDLN'	PlayMode	string
'SNum'	SerialNumber	string/
'SelO'	PlaySelection	int8u
	<del>-</del>	
'TAGS'	FujiFilmTags	FujiFilm MOV
	KodakTags	Kodak MOV
	KonicaMinoltaTags	Minolta MOV1
	MinoltaTags	Minolta MOV2
	5	
	NikonTags	Nikon MOV
	OlympusTags1	Olympus MOV1
	OlympusTags2	Olympus MOV2
	OlympusTags3	Olympus MP4
	OlympusTags4	Olympus MOV3
	PentaxTags	Pentax MOV
	SamsungTags	Samsung MP4
	SanyoMOV	Sanyo MOV
	<del>-</del>	
	SanyoMP4	Sanyo MP4
	UnknownTags?	string
'TTMD'	TomTomMetaData	QuickTime TomTom
'WLOC'	WindowLocation	int16u
'XMP '	XMP	XMP
_	<del></del>	<del></del>
'Xtra'	MicrosoftXtra	Microsoft Xtra
'_cx_'	CX?	rational64s
'_cy_'	CY?	rational64s
7_ '_yaw'	Yaw	rational64s/
<del>_</del>		
'albm'	Album	string/
'albr'	AlbumArtist	string
'angl'	CameraAngle	string
'apmd'	ApertureMode	undef
'auth'	Author	string/
'btec'	GlamourSettings	DJI Glamour
'ccid'	ContentID	string
'cdis'	ContentDistributorID	string
		5
'chpl'	ChapterList	no
'clfn'	ClipFileName	string
'clid'	ClipID	string
'clsf'	Classification	undef/
		·
'cmid'	CameraID	string
'cmnm'	Model	string/
'coll'	CollectionName	string/
'cprt'	Copyright	string/
	CodeVersion	string
'cver'		
'cvru'	CoverURI	string
'date'	DateTimeOriginal	string
'dscp'	Description	string/
'finm'	OriginalFileName	no
'fsid'	OriginalFilePath	string
'gnre'	Genre	string/
'hinf'	HintTrackInfo	QuickTime HintTrackInfo
'hinv'	HintVersion	string
'hnti'	HintInfo	QuickTime HintInfo
'htcb'	HTCBinary	QuickTime HTCBinary
'icnu'	IconURI	string
'infi'	CameraInfo	QuickTime Nextbase
'info'	FirmwareVersion	string
'infu'	InfoURL	string
'kgtt'	TrackType	string
'kywd'	Keywords	no
'loci'	LocationInformation	undef/
		·
'lrcu'	LyricsURI	string
'lvlm'	LevelMeter?	rational64s
'manu'	Make	no
'mcvr'	PreviewImage	string
		2
'meta'	Meta	QuickTime Meta
'modl'	Model	no
'name'	Name	string
'perf'	Performer	string/
_		
'pmcc'	GarminSettings	string
'pose'	pose	Kodak pose
'ptch'	Pitch	rational64s/

	EXILTOOL 13.24	Iay	машев	
'ptv '	PrintToVideo			QuickTime Video
	Rads?			rational64s
'rads'				
'reel'	ReelName			string
'roll'	Roll			rational64s/
'rtng'	Rating			undef/
'scen'	Scene			string
'scrn'	OlympusPreview			Olympus scrn
'shot'	ShotName			string
'slno'	SerialNumber			string
'smta'	SamsungSmta			Samsung smta
'tags'	Audible_tags			Audible tags
'thmb'	MakerNotePentax5a			Pentax
CIIIID				
	OlympusThumbnail			Olympus thmb
	ThumbnailImage			string
	ThumbnailPNG			string
	UnknownThumbnail			string
'time'	TimeStamp			no
'titl'	Title			string/
'urat'	UserRating			undef/
'uuid'	GarminSoftware			string
	GarminModel			no
	UUID-Unknown?			no
'vndr'	Vendor			
				string
'vrot'	AccelerometerData			no
'yrrc'	Year			undef/
"\xa9ART"	Artist			string
"\xa9TIM"	StartTimecode			string
"\xa9TSC"	StartTimeScale			string
"\xa9TSZ"	StartTimeSampleSize			string
"\xa9alb"	Album			string
"\xa9arg"	Arranger			string
"\xa9ark"	ArrangerKeywords			string
"\xa9cmt"	Comment			string
"\xa9cok"	ComposerKeywords			string
"\xa9com"	Composer			string
"\ха9сру"	Copyright			string
"\xa9day"	ContentCreateDate			string
"\xa9dir"	Director			string
"\xa9ed1"	Edit1			string
"\xa9ed2"	Edit2			string
"\xa9ed3"	Edit3			string
"\xa9ed4"	Edit4			string
"\xa9ed5"	Edit5			string
"\xa9ed6"	Edit6			string
"\xa9ed7"	Edit7			string
"\xa9ed8"	Edit8			
				string
"\xa9ed9"	Edit9			string
"\xa9enc"	EncoderID			string
"\xa9fmt"	Format			string
"\xa9fpt"	Pitch			string
"\xa9frl"	Roll			string
"\xa9fyw"	Yaw			string
"\xa9gen"				_
	Genre			string
"\xa9gpt"	CameraPitch			string
"\xa9grl"	CameraRoll			string
"\xa9grp"	Grouping			string
"\xa9gyw"	CameraYaw			string
"\xa9inf"	Information			string
				<del>-</del>
"\xa9isr"	ISRCCode			string
"\xa9lab"	RecordLabelName			string
"\xa9lal"	RecordLabelURL			string
"\xa9lyr"	Lyrics			string
"\xa9mak"	Make			string
"\xa9mal"	MakerURL			string
				<del>-</del>
"\xa9mdl"	Model			string/
"\xa9mod"	Model			string
"\xa9nam"	Title			string
"\xa9pdk"	ProducerKeywords			string
"\xa9phg"	RecordingCopyright			string
"\xa9prd"	Producer			string
/~>P+ W				~ ~5

"\xa9prf"	Performers	string
"\xa9prk"	PerformerKeywords	string
"\xa9prl"	PerformerURL	string
"\xa9req"	Requirements	string
"\xa9snk"	SubtitleKeywords	string
"\xa9snm"	Subtitle	string
"\xa9src"	SourceCredits	string
"\xa9swf"	SongWriter	string
"\xa9swk"	SongWriterKeywords	string
"\xa9swr"	SoftwareVersion	string
"\xa9too"	Encoder	string
"\xa9trk"	Track	string
"\xa9wrt"	Composer	string/
"\xa9xsp"	SpeedX	string
"\xa9xyz"	GPSCoordinates	string
"\xa9ysp"	SpeedY	string
"\xa9zsp"	SpeedZ	string

## QuickTime TomTom Tags

Tags found in TomTom Bandit Action Cam MP4 videos.

Tag Name	Writable
TomTomAD	QuickTime Stream
TomTomHL?	no
TomTomID	no
TomTomVD	no+
TomTomVI?	no
	TomTomAD TomTomHL? TomTomID TomTomVD

# QuickTime HintTrackInfo Tags

Tag ID	Tag Name	Writable
'dimm'	ImmediateDataBytes	no
'dmax'	LargestPacketDuration	no
'dmed'	MediaTrackBytes	no
'drep'	RepeatedDataBytes	no
'maxr'	MaxDataRate	no
'npck'	NumPackets	no
'nump'	NumPackets	no
'payt'	PayloadType	no
'pmax'	LargestPacketSize	no
'tmax'	MaxTransmissionTime	no
'tmin'	MinTransmissionTime	no
'totl'	TotalBytes	no
'tpaY'	TotalBytesNoRTPHeaders	no
'tpay'	TotalBytesNoRTPHeaders	no
'tpyl'	TotalBytesNoRTPHeaders	no
'trpY'	TotalBytes	no
'trpy'	TotalBytes	no

# QuickTime HintInfo Tags

Tag ID	Tag Name	Writable
'rtp '	RealtimeStreamingProtocol	no
'sdp '	StreamingDataProtocol	no

# QuickTime HTCBinary Tags

Index4	Tag Name	Writable
[no tags	known]	

# QuickTime Nextbase Tags

Tags found in 'infi' atom from some Nextbase videos. As well as these tags, other existing tags are also extracted. These tags are not currently writable but they may all be removed by deleting the Nextbase

group.

Tag ID	Tag Name	Writable
'2nd Cam'	SecondCam	no
'Alerts'	Alerts	no
'Alexa' 'Alexa - Paired D	Alexa	no
Alexa - Paired D	evice Name Alexa-PairedDeviceName	20
'Alexa - Pairing'		no no
	Mode' Alexa-PrivacyMode	no
'Alexa - Wake Wor		110
Alexa - Wake Word	Alexa-WakeWordLanguage	no
'Audio'	Audio	no no
'Auto Power Off'		no
'Battery Status'		no
	dress' BluetoothMACAddress	no
'Bluetooth Name'		no
'Country'	Country	no
'Default Settings	-	no
'Device Sounds'		
'Dual Files'	DualFiles	no no
		no
'Emergency SOS' 'Exposure'	Exposure	no
<del>-</del>	Mode' ExtremeWeatherMode	no
'FCC-ID'	FCC-ID	no
'Firmware'		no
'Firmware Version		no
'Format SD Card'		no
'G Sensor'	GSensor	-
'GPS Stamp'	GPSStamp	no no
'Image Stabilicat	ion' ImageStabilisation	no
	gs' KeepUserSettings	no
'Language'	Language	no
'Linux'	Linux	no
'Model'	Model	no
'Model Stamp'		no
'MyNextbase - Pai:		110
ny wentebase far	MyNextbase-PairedDeviceName	no
'MvNextbase - Pai:	ring' MyNextbase-Pairing	no
'NBCD'	NBCD	no
'Number / License	Plate' NumberLicensePlate	no
'Parking Mode'		no
'RTOS'	RTOS	no
'Recording Histor	y' RecordingHistory	no
'Resolution'	Resolution	no
'Reversing Camera	' ReversingCamera	no
'SD Card Class'		no
'SD Card Format'	SDCardFormat	no
'SD Card Manf Dat	e' SDCardManfDate	no
'SD Card Manf ID'	SDCardManfID	no
'SD Card Model No	' SDCardModelNo	no
'SD Card OEM ID'	SDCardOEMID	no
'SD Card Serial N	o' SDCardSerialNo	no
'SD Card Size'	SDCardSize	no
'SD Card Type'	SDCardType	no
	ce' SDCardUsedSpace	no
'Screen Dimming'	ScreenDimming	no
'Screen Saver'	ScreenSaver	no
'Serial No'	SerialNumber	no
'Speed Stamp'	SpeedStamp	no
'Speed Units'	SpeedUnits	no
'System Info'	SystemInfo	no
'Time & Date'	TimeAndDate	no
'Time Lapse'	TimeLapse	no
'Time Stamp'	VideoTimeStamp	no
'Time Zone / DST'		no
'Video Length'		no
	s' Wi-FiMACAddress	no
'Wi-Fi Password'	Wi-FiPassword	no

# -- ExifTool 13.24 Tag Names --

'Wi-Fi SSID'	Wi-FiSSID	no
'what3words'	What3Words	no

# QuickTime Video Tags

Index1	Tag Name	Writable
0	DisplaySize	no
6	SlideShow	no

# QuickTime UserMedia Tags

Tag ID	Tag Name	Writable

'MTDT' MetaData QuickTime MetaData

# QuickTime MetaData Tags

Tag ID	Tag Name	Writable
0x0001	Title	no
$0 \times 0003$	ProductionDate	no
$0 \times 0004$	Software	no
$0 \times 0005$	Product	no
0x000a	TrackProperty	no
0x000b	TimeZone	no
0x000c	ModifyDate	no

# QuickTime MovieHeader Tags

Index4	Tag Name	Writable
0	MovieHeaderVersion	no
1	CreateDate	int32u
2	ModifyDate	int32u
3	TimeScale	no
4	Duration	no
5	PreferredRate	no
6	PreferredVolume	no
9	MatrixStructure	no
18	PreviewTime	no
19	PreviewDuration	no
20	PosterTime	no
21	SelectionTime	no
22	SelectionDuration	no
23	CurrentTime	no
24	NextTrackID	no

# QuickTime Preview Tags

Index2	Tag Name	Writable
0	PreviewDate	int32u
2	PreviewVersion	no
3	PreviewAtomType	no
5	PreviewAtomIndex	no

## QuickTime SkipInfo Tags

Tag ID	Tag Name	Writable
'thma'	ThumbnailImage	no
'ver '	Version	no

# QuickTime Profile Tags

Tag ID	Tag Name	Writable	
'APRF'	AudioProfile	QuickTime	AudioProf
'FPRF'	FileGlobalProfile	QuickTime	FileProf

'OLYM'	OlympusOLYM	Olympus	OLYM
ОПІП	Отушравошти	Office	ОПТИ

'VPRF' VideoProfile QuickTime VideoProf

# QuickTime AudioProf Tags

Index4	Tag Name	Writable
0	AudioProfileVersion?	no
1	AudioTrackID	no
2	AudioCodec	no
3	AudioCodecInfo?	no
4	AudioAttributes	no
5	AudioAvgBitrate	no
6	AudioMaxBitrate	no
7	AudioSampleRate	no
8	AudioChannels	no

# QuickTime FileProf Tags

Index4	Tag Name	Writable
0	FileProfileVersion?	no
1	FileFunctionFlags	no

# QuickTime VideoProf Tags

Tag Name	Writable
VideoProfileVersion?	no
VideoTrackID	no
VideoCodec	no
VideoCodecInfo?	no
VideoAttributes	no
VideoAvgBitrate	no
VideoMaxBitrate	no
VideoAvgFrameRate	no
VideoMaxFrameRate	no
VideoSize	no
PixelAspectRatio	no
	VideoProfileVersion? VideoTrackID VideoCodec VideoCodecInfo? VideoAttributes VideoAvgBitrate VideoMaxBitrate VideoAvgFrameRate VideoMaxFrameRate VideoSize

# QuickTime Flip Tags

Found in MP4 files from Flip Video cameras.

Tag Name	Writable
PreviewImageWidth	no
PreviewImageHeight	no
PreviewImageLength	no
SerialNumber	no
PreviewImage	no
	PreviewImageWidth PreviewImageHeight PreviewImageLength SerialNumber

# QuickTime Tags360Fly Tags

Timed metadata found in MP4 videos from the 360Fly.

Tag ID	Tag Name	Writable
$0 \times 0001$	Accel360Fly	QuickTime Accel360Fly
$0 \times 0002$	Gyro360Fly	QuickTime Gyro360Fly
0x0003	Mag360Fly	QuickTime Mag360Fly
$0 \times 0005$	GPS360Fly	QuickTime GPS360Fly
$0 \times 0006$	Rot360Fly	QuickTime Rot360Fly
0x00fa	Fusion360Fly	QuickTime Fusion360Fly

# QuickTime Accel360Fly Tags

Index1	Tag Name	Writable
1	AccelMode?	no

2	SampleTime	no
10	AccelYPR	no

## QuickTime Gyro360Fly Tags

Index1	Tag Name	Writable
1	GyroMode?	no
2	SampleTime	no
10	GyroYPR	no

### QuickTime Mag360Fly Tags

Index1	Tag Name	Writable
1	MagMode?	no
2	SampleTime	no
10	MagnetometerXYZ	no

#### QuickTime GPS360Fly Tags

Index1	Tag Name	Writable
1	GPSMode?	no
2	SampleTime	no
10	GPSLatitude	no
14	GPSLongitude	no
18	GPSAltitude	no
22	GPSSpeed	no
24	GPSTrack	no
26	Acceleration	no

#### QuickTime Rot360Fly Tags

Index1	Tag Name	Writable
1	RotMode?	no
2	SampleTime	no
10	RotationXYZ	no

# QuickTime Fusion360Fly Tags

Index1	Tag Name	Writable
1	FusionMode?	no
2	SampleTime	no
10	FusionYPR	no

## QuickTime ImageFile Tags

Tags used in QTIF QuickTime Image Files.

Tag ID	Tag Name	Writable
'idat'	ImageData	no
'idsc'	ImageDescription	QuickTime VisualSampleDesc
'iicc'	ICC Profile	ICC Profile

#### RIFF Tags

The RIFF container format is used various types of fines including AVI, WAV, WEBP, LA, OFR, PAC and WV. According to the EXIF specification, Meta information is embedded in two types of RIFF "LIST" chunks: "INFO" and "exif", and information about the audio content is stored in the "fmt" chunk. As well as this information, some video information and proprietary manufacturer-specific information is also extracted.

Large AVI videos may be a concatenation of two or more RIFF chunks. For these files, information is extracted from subsequent RIFF chunks as sub-documents, but the Duration is calculated for the full video.

ExifTool currently has the ability to write EXIF, XMP and ICC\_Profile metadata to WEBP images, but can't yet write to other RIFF-based formats.

Tag ID	Tag Name	Writable
'ALPH'	ALPH	RIFF ALPH
'ANIM'	ANIM	RIFF ANIM
'ANMF'	ANMF	RIFF ANMF
'C2PA'	JUMBF	Jpeg2000
'CSET'	CharacterSet	RIFF CSET
'EXIF'	EXIF	EXIF
BXII	UnknownEXIF	no
'ICCP'	ICC_Profile	ICC Profile
'IDIT'	DateTimeOriginal	no
'JUNK'	OlympusJunk	Olympus AVI
OONK	CasioJunk	EXIF
	RicohJunk	Ricoh AVI
	PentaxJunk	Pentax Junk
	PentaxJunk2	Pentax Junk2
	LucasJunk	QuickTime Stream
LITINO	TextJunk	no
'JUNQ'	OldXMP	no
'LIST_INF0'	Info	RIFF Info
'LIST_INFO'	Info	RIFF Info
'LIST_Tdat'	Tdat	RIFF Tdat
'LIST_adtl'	AssociatedDataList	RIFF
'LIST_exif'	Exif	RIFF Exif
'LIST_hdrl'	Hdrl	RIFF Hdrl
'LIST_hydt'	PentaxData	Pentax AVI
'LIST_ncdt'	NikonData	Nikon AVI
'LIST_pntx'	PentaxData2	Pentax AVI
'SEAL'	SEAL	XMP SEAL
'SGLT'	BikeBroAccel	QuickTime Stream
'SLLT'	BikeBroGPS	QuickTime Stream
'VP8 '	VP8Bitstream	RIFF VP8
'VP8L'	VP8L	RIFF VP8L
'VP8X'	VP8X	RIFF VP8X
"XMP\0"	XMP	XMP
'XMP '	XMP	XMP
'_PMX '	XMP	XMP
'aXML'	AXML	XMP XML
'acid'	Acidizer	RIFF Acidizer
'afsp'	Afsp	no
'bext'	BroadcastExtension	RIFF BroadcastExt
'cue '	CuePoints	no
'ds64'	DataSize64	RIFF DS64
'fact'	NumberOfSamples	no
'fmt '	AudioFormat	RIFF AudioFormat
'gps0'	GPSTrack	QuickTime Stream
'gsen'	GSensor	QuickTime Stream
'guan'	Guano	no
'iXML'	IXML	XMP XML
'id3 '	ID3	ID3
'inst'	Instrument	RIFF Instrument
'labl'	CuePointLabel	no
'list'	ListType	no
'ltxt'	LabeledText	no
'note'	CuePointNote	no
'olym'	Olym	Olympus WAV
'plst'	Playlist	no
'smpl'	Sampler	RIFF Sampler
'tx_USER'	UserText	RIFF UserText
'tx_Unknown'	Text	no

# RIFF ALPH Tags

WebP alpha chunk.

0	AlphaPreprocessing	no
0.1	AlphaFiltering	no
0.2	AlphaCompression	no

## RIFF ANIM Tags

WebP animation chunk.

Index1	Tag Name	Writable
0	BackgroundColor	no
4	AnimationLoopCount	no

# RIFF ANMF Tags

WebP animation frame chunk.

Index1	Tag Name	Writable
12	Duration	no

# RIFF CSET Tags

Index2	Tag Name	Writable
0	CodePage	no
1	CountryCode	no
2	LanguageCode	no
3	Dialect	no

# RIFF Info Tags

RIFF INFO tags found in AVI video and WAV audio files. Tags which are part of the EXIF 2.3 specification have an underlined Tag Name in the HTML version of this documentation. Other tags are found in AVI files generated by some software.

Tag ID	Tag Name	Writable
'AGES'	Rated	no
'CMNT'	Comment	no
'CODE'	EncodedBy	no
'COMM'	Comments	no
'DIRC'	Directory	no
'DISP'	SoundSchemeTitle	no
'DTIM'	DateTimeOriginal	no
'GENR'	Genre	no
'IARL'	ArchivalLocation	no
'IART'	Artist	no
'IAS1'	FirstLanguage	no
'IAS2'	SecondLanguage	no
'IAS3'	ThirdLanguage	no
'IAS4'	FourthLanguage	no
'IAS5'	FifthLanguage	no
'IAS6'	SixthLanguage	no
'IAS7'	SeventhLanguage	no
'IAS8'	EighthLanguage	no
'IAS9'	NinthLanguage	no
'IBSU'	BaseURL	no
'ICAS'	DefaultAudioStream	no
'ICDS'	CostumeDesigner	no
'ICMS'	Commissioned	no
'ICMT'	Comment	no
'ICNM'	Cinematographer	no
'ICNT'	Country	no
'ICOP'	Copyright	no
'ICRD'	DateCreated	no
'ICRP'	Cropped	no
'IDIM'	Dimensions	no

'IDIT'	DateTimeOriginal	no
'IDPI'	DotsPerInch	no
'IDST'	DistributedBy	no
'IEDT'	EditedBy	no
'IENC'	EncodedBy	no
'IENG'	Engineer	no
'IGNR'	Genre	no
'IKEY'	Keywords	no
'ILGT'	Lightness	no
'ILGU'	LogoURL	no
'ILIU'	LogoIconURL	no
'ILNG'	Language	no
'IMBI'	MoreInfoBannerImage	
'IMBU'	MoreInfoBannerURL	no
	Medium	no
'IMED'		no
'IMIT'	MoreInfoText	no
'IMIU'	MoreInfoURL	no
'IMUS'	MusicBy	no
'INAM'	Title	no
'IPDS'	ProductionDesigner	no
'IPLT'	NumColors	no
'IPRD'	Product	no
'IPRO'	ProducedBy	no
'IRIP'	RippedBy	no
'IRTD'	Rating	no
'ISBJ'	Subject	no
'ISFT'	Software	no
'ISGN'	SecondaryGenre	no
'ISHP'	Sharpness	no
'ISMP'	TimeCode	no
'ISRC'	Source	no
'ISRF'	SourceForm	no
'ISTD'	ProductionStudio	no
'ISTR'	Starring	no
'ITCH'	Technician	no
'ITRK'	TrackNumber	no
'IWMU'	WatermarkURL	no
'IWRI'	WrittenBy	no
'LANG'	Language	no
'LOCA'	Location	
'PRT1'		no
	Part	no
'PRT2'	NumberOfParts	no
'RATE'	Rate	no
'STAR'	Starring	no
'STAT'	Statistics	no
'TAPE'	TapeName	no
'TCDO'	EndTimecode	no
'TCOD'	StartTimecode	no
'TITL'	Title	no
'TLEN'	Length	no
'TORG'	Organization	no
'TRCK'	TrackNumber	no
'TURL'	URL	no
'TVER'	Version	no
'VMAJ'	VegasVersionMajor	no
'VMIN'	VegasVersionMinor	no
'YEAR'	Year	no

# RIFF Tdat Tags

Tag ID Tag Name Writable
----[no tags known]

# RIFF Exif Tags

These tags are part of the EXIF 2.3 specification for WAV audio files.

Tag ID Tag Name Writable

## -- ExifTool 13.24 Tag Names --

'ecor'	Make	no
'emdl'	Model	no
'emnt'	MakerNotes	no
'erel'	RelatedImageFile	no
'etim'	TimeCreated	no
'eucm'	UserComment	no
'ever'	ExifVersion	no

## RIFF Hdrl Tags

Tag ID	Tag Name	Writable
'IDIT'	DateTimeOriginal	no
'ISMP'	TimeCode	no
'ITST odml'	OnenDMI.	RIFF OpenDM

'LIST\_odml' OpenDML RIFF OpenDML 'LIST\_strl' Stream RIFF Stream 'avih' AVIHeader RIFF AVIHeader

# RIFF OpenDML Tags

Tag ID	Tag Name	Writable
'dmlh'	ExtendedAVIHeader	RIFF ExtAVIHdr

## RIFF ExtAVIHdr Tags

Index4	Tag Name	Writable
0	TotalFrameCount	no

## RIFF Stream Tags

Tag ID	Tag Name	Writa	able
'strd'	StreamData	RIFF	StreamData
'strf'	AudioFormat	RIFF	AudioFormat
	VideoFormat	BMP	
'strh'	StreamHeader	RIFF	StreamHeader
'strn'	StreamName	no	

# RIFF StreamData Tags

This chunk is used to store proprietary information in AVI videos from some cameras. The first 4 characters of the data are used as the Tag ID below.

Tag ID	Tag Name	Writable
'AVIF'	AVIF	EXIF
'CASI'	CasioData	Casio AVI
'Zora'	VendorName	no
'unknown'	UnknownData	no

# RIFF AudioFormat Tags

Index2	Tag Name	Writable
0	Encoding	no
1	NumChannels	no
2	SampleRate	no
4	AvgBytesPerSec	no
7	BitsPerSample	no

# RIFF StreamHeader Tags

Index4	Tag Name	Writable
0	StreamType	no
1	AudioCodec	no
	VideoCodec	no

	Codec	no
5	AudioSampleRate	no
	VideoFrameRate	no
	StreamSampleRate	no
8	AudioSampleCount	no
	VideoFrameCount	no
	StreamSampleCount	no
10	Quality	no
11	SampleSize	no

# RIFF AVIHeader Tags

Index4	Tag Name	Writable
0	FrameRate	no
1	MaxDataRate	no
4	FrameCount	no
6	StreamCount	no
8	ImageWidth	no
9	ImageHeight	no

#### RIFF VP8 Tags

This chunk is found in simple-format (lossy) WebP files. See <a href="https://developers.google.com/speed/webp/docs/riff\_container">https://developers.google.com/speed/webp/docs/riff\_container</a> for the WebP container specification.

Index1	Tag Name	Writable
0	VP8Version	no
6	ImageWidth	no
6.1	HorizontalScale	no
8	ImageHeight	no
8.1	VerticalScale	no

## RIFF VP8L Tags

This chunk is found in lossless WebP files.

Index1	Tag Name	Writable
1	ImageWidth	no
2	ImageHeight	no
4	AlphaIsUsed	no

## RIFF VP8X Tags

This chunk is found in extended WebP files.

Index1	Tag Name	Writable
0	WebP_Flags	no
4	ImageWidth	no
6	ImageHeight	no

## RIFF Acidizer Tags

Index1	Tag Name	Writable
0	AcidizerFlags	no
4	RootNote	no
12	Beats	no
16	Meter	no
20	Tempo	no

# RIFF BroadcastExt Tags

Information found in the Broadcast Audio Extension chunk (see
<http://tech.ebu.ch/docs/tech/tech3285.pdf>).

## -- ExifTool 13.24 Tag Names --

Index1	Tag Name	Writable
0	Description	no
256	Originator	no
288	OriginatorReference	no
320	DateTimeOriginal	no
338	TimeReference	no
346	BWFVersion	no
348	BWF_UMID	no
602	CodingHistory	no

## RIFF DS64 Tags

64-bit data sizes for MBWF/RF64 files. See <a href="https://tech.ebu.ch/docs/tech/tech3306-2009.pdf">https://tech.ebu.ch/docs/tech/tech3306-2009.pdf</a>> for the specification.

Index8	Tag Name	Writable
0	RIFFSize64	no
1	DataSize64	no
2	NumberOfSamples64	no

## RIFF Instrument Tags

Index1	Tag Name	Writable
0	UnshiftedNote	no
1	FineTune	no
2	Gain	no
3	LowNote	no
4	HighNote	no
5	LowVelocity	no
6	HighVelocity	no

## RIFF Sampler Tags

Index4	Tag Name	Writable
0	Manufacturer	no
1	Product	no
2	SamplePeriod	no
3	MIDIUnityNote	no
4	MIDIPitchFraction	no
5	SMPTEFormat	no
6	SMPTEOffset	no
7	NumSampleLoops	no
8	SamplerDataLen	no
9	SamplerData	no

# RIFF UserText Tags

Tags decoded from the USER-format txts stream written by Momento M6 dashcam. Extracted only if the ExtractEmbedded option is used.

Index1	Tag Name	Writable
28	GPSAltitude	no
40	Accelerometer	no
56	GPSSpeed	no
60	GPSLatitude	no
64	GPSLongitude	no
68	GPSDateTime	no

# FLAC Tags

Free Lossless Audio Codec (FLAC) meta information. ExifTool also extracts ID3 information from these files.

Tag ID	Tag Name	Writable

0x0000	StreamInfo	FLAC StreamInfo
$0 \times 0001$	Padding?	no
$0 \times 0002$	Application_riff	RIFF
	ApplicationUnknown?	no
0x0003	SeekTable?	no
0x0004	VorbisComment	Vorbis Comments
0x0005	CueSheet?	no
0x0006	Picture	FLAC Picture

#### FLAC StreamInfo Tags

FLAC is big-endian, so bit 0 is the high-order bit in this table.

Tag ID	Tag Name	Writable
'Bit000-015'	BlockSizeMin	no
'Bit016-031'	BlockSizeMax	no
'Bit032-055'	FrameSizeMin	no
'Bit056-079'	FrameSizeMax	no
'Bit080-099'	SampleRate	no
'Bit100-102'	Channels	no
'Bit103-107'	BitsPerSample	no
'Bit108-143'	TotalSamples	no
'Bit144-271'	MD5Signature	no

## FLAC Picture Tags

Index4	Tag Name	Writable
0	PictureType	no
1	PictureMIMEType	no
2	PictureDescription	no
3	PictureWidth	no
4	PictureHeight	no
5	PictureBitsPerPixel	no
6	PictureIndexedColors	no
7	PictureLength	no
8	Picture	no

#### GM Tags

These tags are extracted from  ${\rm GM/Cosworth}$  PDR (Performance Data Recorder) information found in videos from General Motors cars such as Corvette and Camero.

Use the API PrintCSV option to output all timed PDR data in CSV format at greatly increased speed and with much lower memory usage. This option prints the numerical values for each channel in CSV format, suitable for import into RaceRender. In this output, the gear numbers for Neutral and Reverse are changed to -1 and -100 respectively for compatibility with RaceRender.

## GM marl Tags

Tags extracted from the 'ctbx' 'marl' (Marlin) box of timed PDR metadata from GM cars. Use the -ee (API ExtractEmbedded) option to extract this information, or the API PrintCSV option to output in CSV format.

Tag Name	Writable
ABSActive	no
AccelPos	no
BatteryVoltage	no
Beacon	no
BoostPressureInd	no
BrakePos	no
CPUFree	no
CPUIO	no
CPUIRQ	no
CPUSystem	no

CPUUser	no
ClutchPos	no
CoolantTemp	no
CornerExitSetting	no
DiskReadOperations	no
DiskReadRate	no
DiskReadTime	no
DiskWriteOperations	no
DiskWriteRate	no
DiskWriteTime	no
Distance	no
DriverPerformanceMode	no
EngineSpeedRequest	no
EngineTorqureReq	no
FuelCapacity	no
FuelLevel	no
GPSAltitude	no
GPSDateTime	no
GPSFix	no
GPSLatitude	no
GPSLongitude	no
GPSTrack	no
Gear	no
InfotainOpMode	no
IntakeAirTemperature	no
IntakeBoostPressure	no
LFTyrePressure	no
LFTyreTemp	no
LRTyrePressure	no
LRTyreTemp	no
LateralAcceleration	no
LongitudinalAcceleration	no
OilPressure	no
OilTemp	no
OutsideAirTemperature	no
RFTyrePressure	no
RFTyreTemp	no
RPM	no
RRTyrePressure	no
RRTyreTemp	no
RecordingEventOdometer	no
_	
Speed	no
SpeedControlResponse SpeedResponse thtorugation	no
SpeedRequestIntervention	no
Steering1Switch	no
Steering2Switch	no
SteeringAngle	no
SuspensionDisplacementLeftFront	no
SuspensionDisplacementLeftRear	no
SuspensionDisplacementRightFront	no
SuspensionDisplacementRightRear	no
SystemBackupPowerEnabled	no
SystemBackupPowerMode	no
SystemPowerMode	no
TimeStamp	no
TractionControlActive	no
TransOilTemp	no
TransportStorageMode	no
ValetMode	no
VehicleStabilityActive	no
VerticalAcceleration	no
WheelspeedLeftDriven	no
WheelspeedLeftNon-Driven	no
WheelspeedRightDriven	no
WheelspeedRightNon-Driven	no
YawRate	no

# <u>GM</u> <u>mrld</u> <u>Tags</u>

The Marlin dictionary. Only one channel is listed but all available

channels are extracted. Use the  $\mbox{-struct}$  (API Struct) option to extract the channel information as structures.

Tag Name	Writable
Channel01	GM Channel Struct
Channel01Description	no_
Channel01DispMax	no_
Channel01DispMin	no_
Channel01Flags	no_
Channel01ID	no_
Channel01Interval	no_
Channel01Max	no_
Channel01Min	no_
Channel01Multiplier	no_
Channel01Name	no_
Channel01Num	no_
Channel010ffset	no_
Channel01Type	no_
Channel01Units	no_

## **GM** Channel Struct

Information stored for each channel in the Marlin dictionary.

Field Name	Writable
ID	no
Type	no
Num	no
Units	no
Flags	no
Interval	no
Min	no
Max	no
DispMin	no
DispMax	no
Multiplier	no
Offset	no
Name	no
Description	no

## GM mrlh Tags

The Marlin PDR header.

Index1	Tag Name	Writable
0	MarlinDataVersion	no

# <u>GM</u> <u>mrlv</u> <u>Tags</u>

Tags found in the 'mrlv' (Marlin values) box.

Tag ID	Tag Name	Writable
'date'	Date1	no
'lang'	Language	no
'ldat'	Date2	no
'ltim'	Time2	no
'swvs'	SoftwareVersion	no
'time'	Time1	no
'tstm'	StartTime	no
'unit'	Units	no
'zone'	TimeZone	no

# Parrot Tags

Parrot mett Tags

Streaming metadata found in Parrot drone videos. See

<https://developer.parrot.com/docs/pdraw/metadata.html> for the specification.

Tag ID	Tag Name	Writable
'P1'	ParrotV1	Parrot V1
'P2'	ParrotV2	Parrot V2
'P3'	ParrotV3	Parrot V3
'E1'	ParrotTimeStamp	Parrot TimeStamp
'E2'	ParrotFollowMe	Parrot FollowMe
'E3'	ParrotAutomation	Parrot Automation
'application/arcore-accel'	ARCoreAccel	Parrot ARCoreAccel
'application/arcore-custom-event'		
	ARCoreCustom	Parrot ARCoreCustom
'application/arcore-gyro'	ARCoreGyro	Parrot ARCoreGyro
'application/arcore-video-0'	ARCoreVideo	Parrot ARCoreVideo

# Parrot V1 Tags

Parrot version 1 streaming metadata.

Index1	Tag Name	Writable
4	DroneYaw	no
6	DronePitch	no
8	DroneRoll	no
10	CameraPan	no
12	CameraTilt	no
14	FrameView	no
22	ExposureTime	no
24	ISO	no
26	WifiRSSI	no
27	Battery	no
28	GPSLatitude	no
32	GPSLongitude	no
36	GPSAltitude	no
36.1	GPSSatellites	no
40	AltitudeFromTakeOff	no
44	DistanceFromHome	no
48	SpeedX	no
50	SpeedY	no
52	SpeedZ	no
54	Binning	no
54.1	FlyingState	no
55	Animation	no
55.1	PilotingMode	no

# Parrot V2 Tags

Parrot version 2 basic streaming metadata.

Index1	Tag Name	Writable
4	Elevation	no
8	GPSLatitude	no
12	GPSLongitude	no
16	GPSAltitude	no
16.1	GPSSatellites	no
20	GPSVelocityNorth	no
22	GPSVelocityEast	no
24	GPSVelocityDown	no
26	AirSpeed	no
28	DroneQuaternion	no
36	FrameView	no
44	CameraPan	no
46	CameraTilt	no
48	ExposureTime	no
50	ISO	no
52	Binning	no
52.1	FlyingState	no

53	Animation	no
53.1	PilotingMode	no
54	WifiRSSI	no
55	Battery	no
'Groups'	Groups	no

# Parrot V3 Tags

Parrot version 3 basic streaming metadata.

Index1	Tag Name	Writable
4	Elevation	no
8	GPSLatitude	no
12	GPSLongitude	no
16	GPSAltitude	no
16.1	GPSSatellites	no
20	GPSVelocityNorth	no
22	GPSVelocityEast	no
24	GPSVelocityDown	no
26	AirSpeed	no
28	DroneQuaternion	no
36	FrameBaseView	no
44	FrameView	no
52	ExposureTime	no
54	ISO	no
56	RedBalance	no
58	BlueBalance	no
60	FOV	no
64	LinkGoodput	no
64.1	LinkQuality	no
68	WifiRSSI	no
69	Battery	no
70	Binning	no
70.1	FlyingState	no
71	Animation	no
71.1	PilotingMode	no

# Parrot TimeStamp Tags

Parrot streaming metadata timestamp extension.

Index1	Tag Name	Writable
4	TimeStamp	no

# Parrot FollowMe Tags

Parrot streaming metadata follow-me extension.

Index1	Tag Name	Writable
4	GPSTargetLatitude	no
8	GPSTargetLongitude	no
12	GPSTargetAltitude	no
16	Follow-meMode	no
17	Follow-meAnimation	no

## Parrot Automation Tags

Parrot streaming metadata automation extension.

Index1	Tag Name	Writable
4	GPSFramingLatitude	no
8	GPSFramingLongitude	no
12	GPSFramingAltitude	no
16	GPSDestLatitude	no
20	GPSDestLongitude	no
24	GPSDestAltitude	no

28	AutomationAnimation	no
29	AutomationFlags	no

#### Parrot ARCoreAccel Tags

ARCore accelerometer data.

Index1	Tag Name	Writable
4	AccelerometerUnknown?	no
5	Accelerometer	no

#### Parrot ARCoreCustom Tags

Index1	Tag Name	Writable
[no tags	known]	

#### Parrot ARCoreGyro Tags

ARCore accelerometer data.

Index1	Tag Name	Writable
4	GyroscopeUnknown?	no
5	Gyroscope	no

#### Parrot ARCoreVideo Tags

Index1	Tag Name	Writable
Ino tags	known]	

#### AAC Tags

Tags extracted from Advanced Audio Coding (AAC) files.

Tag ID	Tag Name	Writable
'Bit016-017'	ProfileType	no
'Bit018-021'	SampleRate	no
'Bit023-025'	Channels	no
'Encoder'	Encoder	no

## Ogg Tags

ExifTool extracts the following types of information from Ogg files. See <a href="http://www.xiph.org/vorbis/doc/">http://www.xiph.org/vorbis/doc/</a>> for the Ogg specification.

Tag ID	Tag Name	Writable
'FLAC'	FLAC	FLAC
'ID3'	ID3	ID3
'Opus'	Opus	Opus
'theora'	Theora	Theora
'vorbis'	Vorbis	Vorbis

# Vorbis Tags

Information extracted from Ogg Vorbis files. See
<http://www.xiph.org/vorbis/doc/> for the Vorbis specification.

Tag ID	Tag Name	Writable
	Identification Comments	Vorbis Identification Vorbis Comments

# <u>Vorbis</u> <u>Comments</u> <u>Tags</u>

The tags below are only some common tags found in the Vorbis comments of Ogg Vorbis and Ogg FLAC audio files, however ExifTool will extract values from any tag found, even if not listed here.

Tag ID	Tag Name	Writable
'ACTOR'	Actor	no
'ALBUM'	Album	no
'ARTIST'	Artist	no+
'COMMENT'	Comment	no
'COMPOSER'	Composer	no
'CONTACT'	Contact	no+
'COPYRIGHT'	Copyright	no
'COVERART'	CoverArt	no
'COVERARTMIME'	CoverArtMIMEType	no
'DATE'	Date	no
'DESCRIPTION'	Description	no
'DIRECTOR'	Director	no
'ENCODED_BY'	EncodedBy	no
'ENCODED_USING'	EncodedUsing	no
'ENCODER'	Encoder	no
'ENCODER_OPTIONS'	EncoderOptions	no
'GENRE'	Genre	no
'ISRC'	ISRCNumber	no
'LICENSE'	License	no
'LOCATION'	Location	no
'METADATA_BLOCK_PICTURE'	Picture	FLAC Picture
'ORGANIZATION'	Organization	no
'PERFORMER'	Performer	no+
'PRODUCER'	Producer	no
'REPLAYGAIN_ALBUM_GAIN'	ReplayGainAlbumGain	no
'REPLAYGAIN_ALBUM_PEAK'	ReplayGainAlbumPeak	no
'REPLAYGAIN_TRACK_GAIN'	ReplayGainTrackGain	no
'REPLAYGAIN_TRACK_PEAK'	ReplayGainTrackPeak	no
'TITLE'	Title	no
'TRACKNUMBER'	TrackNumber	no
'VERSION'	Version	no
'vendor'	Vendor	no

# Vorbis Identification Tags

Index1	Tag Name	Writable
0	VorbisVersion	no
4	AudioChannels	no
5	SampleRate	no
9	MaximumBitrate	no
13	NominalBitrate	no
17	MinimumBitrate	no

# Opus Tags

Information extracted from Ogg Opus files. See
<https://www.opus-codec.org/docs/> for the specification.

Tag ID	Tag Name	Writable
'OpusHead'	Header	Opus Header
'OpusTags'	Comments	Vorbis Comments

# Opus Header Tags

Index1	Tag Name	Writable
0	OpusVersion	no
1	AudioChannels	no
4	SampleRate	no
8	OutputGain	no

# Theora Tags

Information extracted from Ogg Theora video files. See
<http://www.theora.org/doc/Theora.pdf> for the Theora specification.

Tag ID	Tag Name	Writable

 $0 \times 0080$  Identification Theora Identification  $0 \times 0081$  Comments Vorbis Comments

## Theora Identification Tags

Tags extracted from the Theora identification header.

Index1	Tag Name	Writable
0	TheoraVersion	no
7	ImageWidth	no
10	ImageHeight	no
13	XOffset	no
14	YOffset	no
15	FrameRate	no
23	PixelAspectRatio	no
29	ColorSpace	no
30	NominalVideoBitrate	no
33	Quality	no
34	PixelFormat	no

#### APE Tags

Tags found in Monkey's Audio (APE) information. Only a few common tags are listed below, but ExifTool will extract any tag found. ExifTool supports APEv1 and APEv2 tags, as well as ID3 information in APE files, and will also read APE metadata from MP3 and MPC files.

Tag ID	Tag Name	Writable
'Album'	Album	no
'Artist'	Artist	no
'DURATION'	Duration	no
'Genre'	Genre	no
'Title'	Title	no
'Tool Name'	ToolName	no
'Tool Version'	ToolVersion	no
'Track'	Track	no
'Year'	Year	no

## APE NewHeader Tags

APE MAC audio header for version 3.98 or later.

Tag Name	Writable
CompressionLevel	no
BlocksPerFrame	no
FinalFrameBlocks	no
TotalFrames	no
BitsPerSample	no
Channels	no
SampleRate	no
	CompressionLevel BlocksPerFrame FinalFrameBlocks TotalFrames BitsPerSample Channels

## APE OldHeader Tags

APE MAC audio header for version 3.97 or earlier.

Index2	Tag Name	Writable
0	APEVersion	no
1	CompressionLevel	no
3	Channels	no
4	SampleRate	no
10	TotalFrames	no
12	FinalFrameBlocks	no

## Audible Tags

ExifTool will extract any information found in the metadata dictionary of Audible .AA files, even if not listed in the table below.

Tag ID	Tag Name	Writable
'_chapter_count'	ChapterCount	no
'_cover_art'	CoverArt	no
'author'	Author	no
'copyright'	Copyright	no
'pub_date_start'	PublishDateStart	no
'pubdate'	PublishDate	no

## Audible tags Tags

Information found in "tags" atom of Audible M4B audio books.

Tag ID	Tag Name	Writable
'cvrx' 'meta' 'tseg'	Audible_cvrx Audible_meta Audible_tseg	Audible cvrx Audible meta Audible tseg

## Audible cvrx Tags

Audible cover art information in M4B audio books.

Tag Name	Writable
CoverArt	no
CoverArtType	no

# Audible meta Tags

Information found in Audible M4B "meta" atom.

Tag ID	Tag Name	Writable
'ALBUMARTIST'	AlbumArtist	no
'Album'	Album	no
'Artist'	Artist	no
'Comment'	Comment	no
'Genre'	Genre	no
'SUBTITLE'	Subtitle	no
'TOOL'	CreatorTool	no
'Title'	Title	no
'Year'	Year	no
'itunesmediatype'	iTunesMediaType	no
'track'	ChapterName	no

# Audible tseg Tags

Tag ID	Tag Name	Writable
'meta'	Audible_meta2	Audible meta
'tshd'	ChapterNumber	no

# MPC Tags

Tags used in Musepack (MPC) audio files. ExifTool also extracts ID3 and APE information from these files.

Tag ID	Tag Name	Writable
'Bit032-063'	TotalFrames	no
'Bit080-081'	SampleRate	no
'Bit084-087'	Quality	no
'Bit088-093'	MaxBand	no
'Bit096-111'	ReplayGainTrackPeak	no
'Bit112-127'	ReplayGainTrackGain	no
'Bit128-143'	ReplayGainAlbumPeak	no
'Bit144-159'	ReplayGainAlbumGain	no
'Bit179'	FastSeek	no
'Bit191'	Gapless	no
'Bit216-223'	EncoderVersion	no

# MPEG Tags

The MPEG format doesn't specify any file-level meta information. In lieu of this, information is extracted from the first audio and video frame headers in the file.

## MPEG Audio Tags

Tag ID	Tag Name	Writable
'Bit11-12'	MPEGAudioVersion	no
'Bit13-14'	AudioLayer	no
'Bit16-19'	AudioBitrate	no
'Bit20-21'	SampleRate	no
'Bit24-25'	ChannelMode	no
'Bit26'	MSStereo	no
'Bit26-27'	ModeExtension	no
'Bit27'	IntensityStereo	no
'Bit28'	CopyrightFlag	no
'Bit29'	OriginalMedia	no
'Bit30-31'	Emphasis	no

## MPEG Video Tags

Tag ID	Tag Name	Writable
'Bit00-11'	ImageWidth	no
'Bit12-23'	ImageHeight	no
'Bit24-27'	AspectRatio	no
'Bit28-31'	FrameRate	no
'Bit32-49'	VideoBitrate	no

## MPEG Xing Tags

These tags are extracted from the Xing/Info frame.

Tag Name	Writable
Encoder	no
LameHeader	MPEG Lame
LameQuality	no
LameVBRQuality	no
VBRBytes	no
VBRFrames	no
VBRScale	no

## MPEG Lame Tags

Tags extracted from Lame 3.90 or later header.

Index1	Tag Name	Writable
9	LameMethod	no
10	LameLowPassFilter	no
20	LameBitrate	no
24	LameStereoMode	no

## M2TS Tags

The MPEG-2 transport stream is used as a container for many different audio/video formats (including AVCHD). This table lists information extracted from M2TS files.

Tag Name	Writable
AudioStreamType	no
Duration	no
VideoStreamType	no
_AC3	M2TS AC3
_H264	H264
_MISB	MISB

# M2TS AC3 Tags

Tags extracted from AC-3 audio streams.

Tag Name	Writable
AudioBitrate	no
AudioChannels	no
AudioSampleRate	no
SurroundMode	no

#### H264 Tags

Tags extracted from  ${\tt H.264}$  video streams. The metadata for AVCHD videos is stored in this stream.

Tag Name	Writable
ImageHeight	no
ImageWidth	no
MDPM	H264 MDPM

#### H264 MDPM Tags

The following tags are decoded from the Modified Digital Video Pack Metadata (MDPM) of the unregistered user data with UUID 17ee8c60f84d11d98cd60800200c9a66 in the H.264 Supplemental Enhancement Information (SEI). [Yes, this description is confusing, but nothing compared to the challenge of actually decoding the data!] This information may exist at regular intervals through the entire video, but only the first occurrence is extracted unless the ExtractEmbedded (-ee) option is used (in which case subsequent occurrences are extracted as sub-documents).

Tag ID	Tag Name	Writable
0x0013	TimeCode	no
0x0018	DateTimeOriginal	no
$0 \times 0070$	Camera1	H264 Cameral
$0 \times 0071$	Camera2	H264 Camera2
0x007f	Shutter	H264 Shutter
0x00a0	ExposureTime	no
0x00a1	FNumber	no
0x00a2	ExposureProgram	no
0x00a3	BrightnessValue	no
0x00a4	ExposureCompensation	no
0x00a5	MaxApertureValue	no
0x00a6	Flash	no
0x00a7	CustomRendered	no
0x00a8	WhiteBalance	no
0x00a9	FocalLengthIn35mmFormat	no
0x00aa	SceneCaptureType	no
0x00b0	GPSVersionID	no
0x00b1	GPSLatitudeRef	no
$0 \times 00 b2$	GPSLatitude	no
$0 \times 00 b5$	GPSLongitudeRef	no
$0 \times 00 $	GPSLongitude	no
$0 \times 00 $ b9	GPSAltitudeRef	no
0x00ba	GPSAltitude	no
0x00bb	GPSTimeStamp	no
0x00be	GPSStatus	no
0x00bf	GPSMeasureMode	no
0x00c0	GPSDOP	no
0x00c1	GPSSpeedRef	no
0x00c2	GPSSpeed	no
0x00c3	GPSTrackRef	no
0x00c4	GPSTrack	no
0x00c5	GPSImgDirectionRef	no
0x00c6	GPSImgDirection	no
0x00c7	GPSMapDatum	no

0x00ca	GPSDateStamp	no	
0x00e0	MakeModel	H264	MakeModel
0x00e1	RecInfo	H264	RecInfo
0x00e4	Model	no	
0x00ee	FrameInfo	H264	FrameInfo

## <u>H264</u> <u>Cameral</u> <u>Tags</u>

Index1	Tag Name	Writable
0	ApertureSetting	no
1	Gain	no
1.1	ExposureProgram	no
2.1	WhiteBalance	no
3	Focus	no

# <u>H264 Camera2 Tags</u>

Index1	Tag Name	Writable
1	ImageStabilization	no

## H264 Shutter Tags

Index2	Tag Name	Writable
1.1	ExposureTime	no

# <u>H264 MakeModel Tags</u>

Index2	Tag Name	Writable
0	Make	no

# <u>H264</u> <u>RecInfo</u> <u>Tags</u>

Recording information stored by some Canon video cameras.

Index1	Tag Name	Writable
0	RecordingMode	no

## <u>H264</u> FrameInfo Tags

Frame rate information stored by some Canon video cameras.

Index1	Tag Name	Writable
0	CaptureFrameRate	no
1	VideoFrameRate	no

## MISB Tags

These tags are extracted from STANAG-4609 MISB (Motion Industry Standards Board) KLV-format metadata in M2TS videos.

Tag ID	Tag Name	Writa	able
'060E2B34030101010E01030302000000	_	MISB	Security
'060e2b3402030101434e415644494147	7 '		
	ChurchillNav	MISB	ChurchillNav
'060e2b34020b01010e01030101000000	) '		
	UASDataLink	MISB	UASDatalink
' <other>'</other>	Unknown	MISB	Unknown

## MISB Security Tags

Tags extracted from the MISB ST 0102.11 Security Metadata local set.

Tag ID	Tag Name	Writable

$0 \times 0001$	SecurityClassification	no
$0 \times 0002$	ClassifyingCountryCodeMethod	no
0x0003	ClassifyingCountry	no
$0 \times 0004$	SecuritySCI-SHIInformation	no
$0 \times 0005$	Caveats	no
$0 \times 0006$	ReleasingInstructions	no
$0 \times 0007$	ClassifiedBy	no
0x0008	DerivedFrom	no
0x0009	ClassificationReason	no
0x000a	DeclassificationDate	no
0x000b	${\tt ClassificationAndMarkingSystem}$	no
0x000c	ObjectCountryCodingMethod	no
0x000d	ObjectCountryCodes	no
0x000e	ClassificationComments	no
0x000f	UMID	no
$0 \times 0010$	StreamID	no
$0 \times 0011$	TransportStreamID	no
$0 \times 0015$	ItemDesignatorID	no
$0 \times 0016$	SecurityVersion	no
$0 \times 0017$	${\tt ClassifyingCountryCodingMethodDate}$	no
$0 \times 0018$	ObjectCountryCodingMethodDate	no

# MISB ChurchillNav Tags

Proprietary tags used by Churchill Navigation units. These tags are all currently unknown, but extracted with the Unknown option.

Tag ID	Tag Name	Writable
[no tags	known]	

# MISB UASDatalink Tags

Tags extracted from the MISB ST 0601.11 UAS Datalink local set.

Tag ID	Tag Name	Writable
0x0001	Checksum	no
$0 \times 0002$	GPSDateTime	no
0x0003	MissionID	no
$0 \times 0004$	TailNumber	no
0x0005	GPSTrack	no
$0 \times 0006$	PitchAngle	no
$0 \times 0007$	RollAngle	no
0x0008	TrueAirspeed	no
$0 \times 0009$	IndicatedAirspeed	no
0x000a	ProjectIDCode	no
0x000b	SensorName	no
0x000c	ImageCoordinateSystem	no
0x000d	GPSLatitude	no
0x000e	GPSLongitude	no
0x000f	GPSAltitude	no
$0 \times 0010$	HorizontalFieldOfView	no
$0 \times 0011$	VerticalFieldOfView	no
$0 \times 0012$	SensorRelativeAzimuthAngle	no
$0 \times 0013$	SensorRelativeElevationAngle	no
$0 \times 0014$	SensorRelativeRollAngle	no
$0 \times 0015$	SlantRange	no
$0 \times 0016$	TargetWidth	no
$0 \times 0017$	FrameCenterLatitude	no
$0 \times 0018$	FrameCenterLongitude	no
$0 \times 0019$	FrameCenterElevation	no
0x001a	OffsetCornerLatitude1	no
$0 \times 001 b$	OffsetCornerLongitude1	no
0x001c	OffsetCornerLatitude2	no
0x001d	OffsetCornerLongitude2	no
0x001e	OffsetCornerLatitude3	no
0x001f	OffsetCornerLongitude3	no
$0 \times 0020$	OffsetCornerLatitude4	no
0x0021	OffsetCornerLongitude4	no

	ExifTool 13.24 Tag Names	
0x0022	IcingDetected	no
0x0023	WindDirection	no
$0 \times 0024$	WindSpeed	no
0x0025	StaticPressure	no
0x0026	DensityAltitude	no
$0 \times 0027$	AirTemperature	no
0x0028	TargetLocationLatitude	no
0x0029	TargetLocationLongitude	no
0x002a	TargetLocationElevation	no
0x002b	TargetTrackGateWidth	no
0x002c 0x002d	TargetTrackGateHeight TargetErrorEstimateCE90	no no
0x002a	TargetErrorEstimateLE90	no
0x0026	GenericFlagData01	no
0x0030	SecurityLocalMetadataSet	MISB Security
0x0031	DifferentialPressure	no
0x0032	AngleOfAttack	no
0x0033	VerticalSpeed	no
0x0034	SideslipAngle	no
0x0035	AirfieldBarometricPressure	no
0x0036	AirfieldElevation	no
0x0037	RelativeHumidity	no
0x0038	GPSSpeed	no
0x0039	GroundRange	no
0x003a	FuelRemaining	no
0x003b	CallSign	no
0x003c	WeaponLoad	no
0x003d 0x003e	WeaponFired LaserPRFCode	no
0x003e 0x003f	SensorFieldOfViewName	no no
0x0031 0x0040	MagneticHeading	no
0x0041	UAS_LSVersionNumber	no
$0 \times 0042$	TargetLocationCovarianceMatrix	no
0x0043	AlternateLatitude	no
$0 \times 0044$	AlternateLongitude	no
$0 \times 0045$	AlternateAltitude	no
$0 \times 0046$	AlternateName	no
$0 \times 0047$	AlternateHeading	no
$0 \times 0048$	EventStartTime	no
0x0049	RVTLocalSet	MISB Unknown
0x004a	VMTIDataSet	MISB Unknown
0x004b	SensorEllipsoidHeight	no
0x004c 0x004d	AlternateEllipsoidHeight OperationalMode	no
0x004a 0x004e	FrameCenterHeightAboveEllipsoid	no no
0x004e	SensorVelocityNorth	no
0x0011	SensorVelocityEast	no
0x0051	ImageHorizonPixelPack	no
$0 \times 0052$	CornerLatitude1	no
0x0053	CornerLongitudel	no
$0 \times 0054$	CornerLatitude2	no
$0 \times 0055$	CornerLongitude2	no
$0 \times 0056$	CornerLatitude3	no
$0 \times 0057$	CornerLongitude3	no
$0 \times 0058$	CornerLatitude4	no
0x0059	CornerLongitude4	no
0x005a	FullPitchAngle	no
0x005b	FullAngle	no
0x005c 0x005d	FullAngleOfAttack FullSideslipAngle	no
0x005a	MIISCoreIdentifier	no no
0x005e	SARMotionImageryData	MISB Unknown
0x0051	TargetWidthExtended	no
0x0000	RangeImageLocalSet	MISB Unknown
0x0062	GeoregistrationLocalSet	MISB Unknown
0x0063	CompositeImagingLocalSet	MISB Unknown
0x0064	SegmentLocalSet	MISB Unknown
0x0065	AmendLocalSet	MISB Unknown
0x0066	SDCC-FLP	no
0x0067	DensityAltitudeExtended	no

0x0068SensorEllipsoidHeightExtendedno0x0069AlternateEllipsoidHeightExtendedno

## MISB Unknown Tags

Other tags are extracted with the Unknown option.

Tag Name

Tag ID Tag Name Writable
----[no tags known]

## Matroska Tags

Tag ID

The following tags are extracted from Matroska multimedia container files. This container format is used by file types such as MKA, MKV, MKS and WEBM. For speed, by default ExifTool extracts tags only up to the first Cluster unless a Seek element specifies the position of a Tags element after this. However, the Verbose (-v) and Unknown = 2 (-U) options force processing of Cluster data, and the ExtractEmbedded (-ee) option skips over Clusters to read subsequent tags. See <a href="http://www.matroska.org/technical/specs/index.html">http://www.matroska.org/technical/specs/index.html</a> for the official Matroska specification.

Writable

Tag ID	rag Name	WIICADIE
0x0000	ChapterDisplay	Matroska
0x0003	TrackType	no
0x0005	ChapterString	no
0x0006	VideoCodecID	no
0210000	AudioCodecID	no
	CodecID	no
0x0008	TrackDefault	no
0x0009	ChapterTrackNumber?	no
0x000e	Slices	Matroska
0x000f	ChapterTrack	Matroska
0x0011	ChapterTimeStart	no
0x0012	ChapterTimeEnd	no
0x0016	CueRefTime?	no
$0 \times 0017$	CueRefCluster?	no
0x0017	ChapterFlagHidden?	no
0x0010 0x001a		
	VideoScanType	no
0x001b	BlockDuration?	no
0x001c	TrackLacing?	no
0x001f	AudioChannels	no
0x0020	BlockGroup	Matroska
0x0021	Block?	no
0x0022	BlockVirtual?	no
0x0023	SimpleBlock?	no
0x0024	CodecState?	no
0x0025	BlockAdditional?	no
0x0026	BlockMore	Matroska
$0 \times 0027$	Position	no
0x0027	CodecDecodeAll	no
	PrevSize	
0x002b		no
0x002e	TrackEntry	Matroska
0x002f	EncryptedBlock?	no
$0 \times 0030$	ImageWidth	no
0x0033	CueTime?	no
$0 \times 0035$	AudioSampleRate	no
0x0036	ChapterAtom	Matroska
$0 \times 0037$	CueTrackPositions	Matroska
0x0039	TrackUsed	no
0x003a	ImageHeight	no
0x003b	CuePoint	Matroska
0x003E 0x003f	CRC-32?	
		no
0x004b	BlockAdditionalID?	no
0x004c	LaceNumber?	no
0x004d	FrameNumber?	no
0x004e	Delay?	no
0x004f	ClusterDuration?	no
$0 \times 0057$	TrackNumber	no

	EXILIOOI IJ.24 lag Names -	_
0x005b	CueReference	Matroska
$0 \times 0060$	Video	Matroska
$0 \times 0061$	Audio	Matroska
$0 \times 0067$	TimeCode?	no
0x0068	TimeSlice	Matroska
0x006a	CueCodecState?	no
0x006b	CueRefCodecState?	no
0x006c	Void?	no
0x006e	BlockAddID?	no
$0 \times 0071$	CueClusterPosition?	no
$0 \times 0.077$	CueTrack?	no
0x007a	ReferencePriority? ReferenceBlock?	no
0x007b 0x007d	ReferenceVirtual?	no no
$0 \times 0074$	ContentCompressionAlgorithm	no
0x0251 $0x0255$	ContentCompressionSettings?	no
0x0282	DocType	no
0x0285	DocTypeReadVersion	no
0x0286	EBMLVersion	no
$0 \times 0287$	DocTypeVersion	no
0x02f2	EBMLMaxIDLength?	no
0x02f3	EBMLMaxSizeLength?	no
0x02f7	EBMLReadVersion	no
0x037c	ChapterLanguage	no
0x037e	ChapterCountry	no
$0 \times 0444$	SegmentFamily?	no
$0 \times 0461$	DateTimeOriginal	no
0x047a	TagLanguageBCP47	no
0x0484	TagDefault	no
$0 \times 0485$ $0 \times 0487$	TagBinary TagString	no
0x0489	Duration	no no
0x050d	ChapterProcessPrivate?	no
0x0598	ChapterFlagEnabled?	no
0x05a3	TagName	no
0x05b9	EditionEntry	Matroska
0x05bc	EditionUID?	no
0x05bd	EditionFlagHidden?	no
0x05db	EditionFlagDefault?	no
0x05dd	EditionFlagOrdered?	no
0x065c	AttachedFileData	no
0x0660	AttachedFileMIMEType AttachedFileName	no
0x066e 0x0675	AttachedFileReferral?	no no
0x067e	AttachedFileDescription	no
0x06ae	AttachedFileUID	no
0x07e1	ContentEncryptionAlgorithm	no
0x07e2	ContentEncryptionKeyID?	no
0x07e3	ContentSignature?	no
0x07e4	ContentSignatureKeyID?	no
0x07e5	ContentSignatureAlgorithm	no
0x07e6	ContentSignatureHashAlgorithm	no
0x0d80	MuxingApp	no
0x0dbb	Seek	Matroska
0x1031 0x1032	ContentEncodingOrder?	no
0x1032	ContentEncodingScope? ContentEncodingType	no no
0x1033	ContentCompression	Matroska
0x1035	ContentEncryption	Matroska
0x135f	CueRefNumber?	no
0x136e	TrackName	no
0x1378	CueBlockNumber?	no
0x137f	TrackOffset?	no
0x13ab	SeekID?	no
0x13ac	SeekPosition?	no
0x13b8	Stereo3DMode	no
0x14aa		
	CropBottom	no
0x14b0	DisplayWidth	no
	-	

	Exillool 13.24 Tag Names -	
0x14ba	DisplayHeight	no
0x14bb	CropTop	no
0x14cc	CropLeft	no
0x14dd	CropRight	no
0x15aa	TrackForced	no
0x15ee	MaxBlockAdditionID?	no
0x1741	WritingApp	no
0x1854	SilentTracks	Matroska
0x18d7	SilentTrackNumber	no
0x21a7	AttachedFile	Matroska
0x2240	ContentEncoding	Matroska
0x2264	AudioBitsPerSample	no
0x23a2	CodecPrivate?	no
0x23c0	Targets	Matroska
0x23c3	ChapterPhysicalEquivalent	no
0x23c4	TagChapterUID	no
0x23c5	TagTrackUID	no
0x23c6	TagAttachmentUID	no
0x23c9	TagEditionUID	no
0x23ca	TargetType	no
0x2532	SignedElement?	
	_	no
0x2624	TrackTranslate	Matroska
0x26a5	TrackTranslateTrackID?	no
0x26bf	TrackTranslateCodec	no
0x26fc	TrackTranslateEditionUID?	no
0x27c8	SimpleTag	Matroska
0x28ca	TargetTypeValue	no
0x2911	ChapterProcessCommand	Matroska
0x2922	ChapterProcessTime?	no
		-
0x2924	ChapterTranslate	Matroska
0x2933	ChapterProcessData?	no
0x2944	ChapterProcess	Matroska
0x2955	ChapterProcessCodecID?	no
0x29a5	ChapterTranslateID?	no
0x29bf	ChapterTranslateCodec	no
0x29fc	ChapterTranslateEditionUID?	no
0x2d80	ContentEncodings	Matroska
0x2de7	MinCache?	no
0x2df8	MaxCache?	no
0x2e67	ChapterSegmentUID?	no
0x2ebc	ChapterSegmentEditionUID?	no
0x2fab	TrackOverlay?	no
0x3373	Tag	Matroska
0x3384	SegmentFileName	no
0x33a4	SegmentUID?	no
0x33c4	ChapterUID?	no
0x33c5	TrackUID	no
0x3446	TrackAttachmentUID	no
0x35a1	BlockAdditions	Matroska
0x38b5		
	OutputAudioSampleRate	no
0x3ba9	Title	no
0x3d7b	ChannelPositions?	no
0x3e5b	SignatureElements	Matroska
0x3e7b	SignatureElementList	Matroska
0x3e8a	SignatureAlgo	no
0x3e9a	SignatureHash	no
0x3ea5	SignaturePublicKey?	no
0x3eb5	Signature?	no
0x7670	Projection	Matroska Projection
		•
0x2b59c	TrackLanguage	no
0x2b59d	TrackLanguageIETF	no
0x3314f	TrackTimecodeScale	no
0x383e3	FrameRate	no
0x3e383	VideoFrameRate	no
	DefaultDuration	no
0x58688	VideoCodecName	no
	AudioCodecName	no
	CodecName	no
0x6b240	CodecDownloadURL	no
0xad7b1	TimecodeScale	
UNAU/DI	TIMECOMEDUATE	no

0xfb523         Gamma         no           0x1a9697         CodecSettings         no           0x1b4040         CodecInfoURL         no           0x1c83ab         PrevFileName         no           0x1cb923         PrevUID?         no           0x1eb923         NextUID?         no           0x43a770         Chapters         Matroska           0x14d9b74         SeekHead         Matroska           0x254c367         Tags         Matroska           0x549a966         Info         Matroska           0x654ae6b         Tracks         Matroska           0x8538067         SegmentHeader         Matroska           0xa45dfa3         EBMLHeader         Matroska           0xc53b6b         Cues         Matroska           0xf43b675         Cluster         Matroska           0x5345414c         SEAL         XMP SEAL	0xeb524	ColorSpace?	no
0x1b4040         CodecInfoURL         no           0x1c83ab         PrevFileName         no           0x1cb923         PrevUID?         no           0x1eb923         NextFileName         no           0x1eb923         NextUID?         no           0x43a770         Chapters         Matroska           0x14d9b74         SeekHead         Matroska           0x254c367         Tags         Matroska           0x549a966         Info         Matroska           0x654ae6b         Tracks         Matroska           0x8538067         SegmentHeader         Matroska           0xa45dfa3         EBMLHeader         Matroska           0xb538667         SignatureSlot         Matroska           0xc53bb6b         Cues         Matroska           0xf43b675         Cluster         Matroska	0xfb523	Gamma	no
0x1c83ab         PrevFileName         no           0x1cb923         PrevUID?         no           0x1e83bb         NextFileName         no           0x1eb923         NextUID?         no           0x43a770         Chapters         Matroska           0x14d9b74         SeekHead         Matroska           0x254c367         Tags         Matroska           0x549a966         Info         Matroska           0x654ae6b         Tracks         Matroska           0x8538067         SegmentHeader         Matroska           0xa45dfa3         EBMLHeader         Matroska           0xb538667         SignatureSlot         Matroska           0xc53bb6b         Cues         Matroska           0xf43b675         Cluster         Matroska	0x1a9697	CodecSettings	no
0x1cb923         PrevUID?         no           0x1e83bb         NextFileName         no           0x1eb923         NextUID?         no           0x43a770         Chapters         Matroska           0x14d9b74         SeekHead         Matroska           0x254c367         Tags         Matroska           0x549a966         Info         Matroska           0x654ae6b         Tracks         Matroska           0x8538067         SegmentHeader         Matroska           0x941a469         Attachments         Matroska           0xa45dfa3         EBMLHeader         Matroska           0xb538667         SignatureSlot         Matroska           0xc53bb6b         Cues         Matroska           0xf43b675         Cluster         Matroska	0x1b4040	CodecInfoURL	no
0x1e83bb         NextFileName         no           0x1eb923         NextUID?         no           0x43a770         Chapters         Matroska           0x14d9b74         SeekHead         Matroska           0x254c367         Tags         Matroska           0x549a966         Info         Matroska           0x654ae6b         Tracks         Matroska           0x8538067         SegmentHeader         Matroska           0x941a469         Attachments         Matroska           0x4538667         SignatureSlot         Matroska           0xc53bb6b         Cues         Matroska           0xf43b675         Cluster         Matroska	0x1c83ab	PrevFileName	no
0x1eb923         NextUID?         no           0x43a770         Chapters         Matroska           0x14d9b74         SeekHead         Matroska           0x254c367         Tags         Matroska           0x549a966         Info         Matroska           0x654ae6b         Tracks         Matroska           0x8538067         SegmentHeader         Matroska           0x941a469         Attachments         Matroska           0xa45dfa3         EBMLHeader         Matroska           0xb538667         SignatureSlot         Matroska           0xc53bb6b         Cues         Matroska           0xf43b675         Cluster         Matroska	0x1cb923	PrevUID?	no
0x43a770         Chapters         Matroska           0x14d9b74         SeekHead         Matroska           0x254c367         Tags         Matroska           0x549a966         Info         Matroska           0x654ae6b         Tracks         Matroska           0x8538067         SegmentHeader         Matroska           0x941a469         Attachments         Matroska           0xa45dfa3         EBMLHeader         Matroska           0xb538667         SignatureSlot         Matroska           0xc53bb6b         Cues         Matroska           0xf43b675         Cluster         Matroska	0x1e83bb	NextFileName	no
0x14d9b74         SeekHead         Matroska           0x254c367         Tags         Matroska           0x549a966         Info         Matroska           0x654ae6b         Tracks         Matroska           0x8538067         SegmentHeader         Matroska           0x941a469         Attachments         Matroska           0xa45dfa3         EBMLHeader         Matroska           0xb538667         SignatureSlot         Matroska           0xc53bb6b         Cues         Matroska           0xf43b675         Cluster         Matroska	0x1eb923	NextUID?	no
0x254c367         Tags         Matroska           0x549a966         Info         Matroska           0x654ae6b         Tracks         Matroska           0x8538067         SegmentHeader         Matroska           0x941a469         Attachments         Matroska           0xa45dfa3         EBMLHeader         Matroska           0xb538667         SignatureSlot         Matroska           0xc53bb6b         Cues         Matroska           0xf43b675         Cluster         Matroska	0x43a770	Chapters	Matroska
0x549a966         Info         Matroska           0x654ae6b         Tracks         Matroska           0x8538067         SegmentHeader         Matroska           0x941a469         Attachments         Matroska           0xa45dfa3         EBMLHeader         Matroska           0xb538667         SignatureSlot         Matroska           0xc53bb6b         Cues         Matroska           0xf43b675         Cluster         Matroska	0x14d9b74	SeekHead	Matroska
0x654ae6bTracksMatroska0x8538067SegmentHeaderMatroska0x941a469AttachmentsMatroska0xa45dfa3EBMLHeaderMatroska0xb538667SignatureSlotMatroska0xc53bb6bCuesMatroska0xf43b675ClusterMatroska	0x254c367	Tags	Matroska
0x8538067SegmentHeaderMatroska0x941a469AttachmentsMatroska0xa45dfa3EBMLHeaderMatroska0xb538667SignatureSlotMatroska0xc53bb6bCuesMatroska0xf43b675ClusterMatroska	0x549a966	Info	Matroska
0x941a469AttachmentsMatroska0xa45dfa3EBMLHeaderMatroska0xb538667SignatureSlotMatroska0xc53bb6bCuesMatroska0xf43b675ClusterMatroska	0x654ae6b	Tracks	Matroska
0xa45dfa3EBMLHeaderMatroska0xb538667SignatureSlotMatroska0xc53bb6bCuesMatroska0xf43b675ClusterMatroska	0x8538067	SegmentHeader	Matroska
0xb538667SignatureSlotMatroska0xc53bb6bCuesMatroska0xf43b675ClusterMatroska	0x941a469	Attachments	Matroska
0xc53bb6bCuesMatroska0xf43b675ClusterMatroska	0xa45dfa3	EBMLHeader	Matroska
0xf43b675 Cluster Matroska	0xb538667	SignatureSlot	Matroska
	0xc53bb6b	Cues	Matroska
0x5345414c SEAL XMP SEAL	0xf43b675	Cluster	Matroska
	0x5345414c	SEAL	XMP SEAL

## Matroska Projection Tags

Projection tags defined by the Spherical Video V2 specification. See <a href="https://github.com/google/spatial-media/blob/master/docs/spherical-video-v2-rfc.m">https://github.com/google/spatial-media/blob/master/docs/spherical-video-v2-rfc.m</a>

for the specification.

d>

Tag ID	Tag Name	Writable	
0x7671	ProjectionType	no	
$0 \times 7672$	EquirectangularProj	QuickTime	equi
	CubemapProj	QuickTime	cbmp
	ProjectionPrivate	no	
0x7673	ProjectionPoseYaw	no	
0x7674	ProjectionPosePitch	no	
0x7675	ProjectionPoseRoll	no	

# Matroska StdTag Tags

Standardized Matroska tags, stored in a SimpleTag structure (see <a href="https://www.matroska.org/technical/tagging.html">https://www.matroska.org/technical/tagging.html</a>).

Tag ID	Tag Name	Writable
'ACCOMPANIMENT'	Accompaniment	no
'ACTOR'	Actor	no
'ADDRESS'	Address	no
'ARRANGER'	Arranger	no
'ARTIST'	Artist	no
'ART_DIRECTOR'	ArtDirector	no
'ASSISTANT_DIRECTOR'	AssistantDirector	no
'BARCODE'	Barcode	no
'BPM'	BPM	no
'BPS'	BPS	no
'CATALOG_NUMBER'	CatalogNumber	no
'CHARACTER'	Character	no
'CHOREGRAPHER'	Choregrapher	no
'COMMENT'	Comment	no
'COMPOSER'	Composer	no
'COMPOSER_NATIONALITY'	ComposerNationality	no
'COMPOSITION_LOCATION'	CompositionLocation	no
'CONDUCTOR'	Conductor	no
'CONTENT_TYPE'	ContentType	no
'COPRODUCER'	Coproducer	no
'COPYRIGHT'	Copyright	no
'COSTUME_DESIGNER'	CostumeDesigner	no
'COUNTRY'	Country	no
'DATE_DIGITIZED'	CreateDate	no
'DATE_ENCODED'	DateEncoded	no

'DATE_PURCHASED'	DatePurchased	no
'DATE RECORDED'	DateTimeOriginal	no
'DATE_RELEASED'	DateReleased	no
'DATE_TAGGED'	DateTagged	no
'DATE_WRITTEN'	DateWritten	no
'DESCRIPTION'	Description	no
'DIRECTOR'	Director	no
'DIRECTOR_OF_PHOTOGRAPH	Y '	
2	DirectorOfPhotography	no
LD T CMD T DIIM DD DIII		
'DISTRIBUTED_BY'	DistributedBy	no
'EDITED_BY'	EditedBy	no
'EMAIL'	Email	no
'ENCODED_BY'	EncodedBy	no
'ENCODER'	Encoder	no
'ENCODER_SETTINGS'	EncoderSettings	no
'EXECUTIVE_PRODUCER'	ExecutiveProducer	no
'FAX'	FAX	no
'FPS'	FPS	no
'GENRE'	Genre	no
'IMDB'	IMDB	no
'INITIAL_KEY'	InitialKey	no
'INSTRUMENTS'	Instruments	no+
'ISBN'	ISBN	no
'ISRC'	ISRC	no
'KEYWORDS'	Keywords	no+
'LABEL'	Label	no
'LABEL_CODE'	LabelCode	no
'LAW RATING'	LawRating	no
'LCCN'	Lccn	no
	LeadPerformer	
'LEAD_PERFORMER'		no
'LICENSE'	License	no
'LYRICIST'	Lyricist	no
'LYRICS'	Lyrics	no
'MASTERED BY'	MasteredBy	no
'MCDI'	MCDI	
		no
'MEASURE'	Measure	no
'MIXED_BY'	MixedBy	no
'MOOD'	Mood	no
'ORIGINAL'	Original	no
'ORIGINAL_MEDIA_TYPE'	OriginalMediaType	no
'PART_NUMBER'	PartNumber	no
'PART_OFFSET'	PartOffset	no
'PERIOD'	Period	no
'PHONE'	Phone	no
'PLAY_COUNTER'	PlayCounter	no
	_	
'PRODUCER'	Producer	no
'PRODUCTION_COPYRIGHT'	ProductionCopyright	no
'PRODUCTION_DESIGNER'	ProductionDesigner	no
'PRODUCTION_STUDIO'	ProductionStudio	no
'PUBLISHER'	Publisher	no
'PURCHASE CURRENCY'	PurchaseCurrency	no
<del>_</del>		
'PURCHASE_INFO'	PurchaseInfo	no
'PURCHASE_ITEM'	PurchaseItem	no
'PURCHASE_OWNER'	PurchaseOwner	no
'PURCHASE PRICE'	PurchasePrice	no
'RATING'	Rating	no
	_	
'RECORDING_LOCATION'	RecordingLocation	no
'REMIXED_BY'	RemixedBy	no
'REPLAYGAIN_GAIN'	ReplaygainGain	no
'REPLAYGAIN PEAK'	ReplaygainPeak	no
'SAMPLE'	Sample	no
'SCREENPLAY_BY'	ScreenplayBy	no
'SORT_WITH'	SortWith	no
'SOUND_ENGINEER'	SoundEngineer	no
'SPHERICAL-VIDEO'	SphericalVideoXML	XMP
'SUBJECT'	Subject	no
	Subtitle	
'SUBTITLE'		no
'SUMMARY'	Summary	no
'SYNOPSIS'	Synopsis	no
'TERMS_OF_USE'	TermsOfUse	no
<u>—</u>		

'THANKS_TO'	ThanksTo	no
'TITLE'	Title	no
'TMDB'	TMDB	no
'TOTAL_PARTS'	TotalParts	no
'TUNING'	Tuning	no
'TVDB'	TVDB	no
'URL'	URL	no
'WRITTEN_BY'	WrittenBy	no
'spherical-video'	SphericalVideoXML	XMP

## MOI Tags

MOI files store information about associated MOD or TOD files, and are written by some JVC, Canon and Panasonic camcorders.

Index1	Tag Name	Writable
0	MOIVersion	no
6	DateTimeOriginal	no
14	Duration	no
128	AspectRatio	no
132	AudioCodec	no
134	AudioBitrate	no
218	VideoBitrate	no

## MXF Tags

Tags extracted from Material Exchange Format files. Tag ID's are not listed because they are bulky 16-byte binary values.

Tag Name	Writable
AAFManufacturerID?	no
AES3PCMDescriptor	MXF
AFDAndBarData?	no
AGICOAID?	no
AICI?	no
AIFCSummary?	no
ANCPacketCount	no
ANCPayloadByteArray	no
ANCPayloadSampleCoding	no
ANCPayloadSampleCount	no
ANCWrappingType	no
Abstract	no
Abstract	no
AccountingReferenceNumber	no
ActiveFormatDescriptor	no
ActiveLinesperFrame	no
ActiveSamplesperLine	no
ActiveState	no
Ad-ID?	no
Address	MXF
AddressLine	no
AddressLine	no
AddressNameValueSets?	no
AddressSets?	no
AdvertisingMaterialReference	no
AestheticValue	no
AlphaMaximumRef	no
AlphaMinimumRef	no
AlphaSampleDepth	no
AlphaTransparency	no
AlternateName	no
AlternateName	no
Alternates?	no
AnalogDataCodingKind	no
AnalogMetadataCarrier	no
AnalogMonitoringAndControlCodingKind	no
AnalogSystem	no
AnalogVideoSystemName	no
AnalogVideoSystemName?	no
AnamorphicLensCharacteristic	no

AnchorOffset	no
AncillaryResourceID?	no
AngleToNorth	no
5	_
AngularUnitKind	no
Annotation?	no
Annotation	MXF
AnnotationCueWordsSet?	no
AnnotationDescription	no
AnnotationDescription	no
AnnotationKind	_
	no
AnnotationKind	no
AnnotationParticipantSets?	no
AnnotationSets?	no
AnnotationSynopsis	no
AnnotationSynopsis	no
	_
ApplicationEnvironmentID	no
ApplicationInformationArray?	no
ApplicationName	no
ApplicationName	no
ApplicationPlatform	no
ApplicationPlatform	no
ApplicationPlug-InBatch?	no
ApplicationPlug-InInstanceID?	no
ApplicationProductID?	no
ApplicationScheme?	no
ApplicationSchemeBatch?	no
ApplicationSupplierName	_
	no
ApplicationSupplierName	no
ApplicationVersionNumber	no
ApplicationVersionString	no
ApplicationVersionString	no
ApproximateImageContainerSize	no
ArchiveID	no
	-
AssetValue	no
AssignedCategoryName	no
AssignedCategoryName	no
AssignedCategoryValue	no
AssignedCategoryValue	no
AssociatedMetadataDefinition?	no
AstronomicalBodyName	no
AstronomicalBodyName	no
AudienceAppreciation	no
AudienceRating	no
AudienceReach	no
AudienceShare	no
AudioAverageBitrate	no
AudioCodingSchemeCode	no
AudioCodingSchemeID?	no
AudioCodingSchemeName	no
AudioCompressionAlgorithm	no
AudioDeviceKind	no
AudioDeviceParameter	
	no
AudioDeviceParameterSetting	no
AudioEnhancementOrModificationDescription	no
AudioFirstMix-DownProcess	no
AudioFixedBitrateFlag	no
AudioMonoChannelCount	no
AudioNoiseReductionAlgorithm	no
	_
AudioReferenceLevel	no
AudioReferenceLevel	no
AudioSampleRate	no
AudioSampleRate	no
AudioStereoChannelCount	no
AudioWatermarkKind	no
	_
AuthenticationFlag	no
AuxiliaryBitsMode	no
AvailableRepresentations?	no
AverageBytesPerSecond	no
Award	MXF
AwardCategory	no

	EXILIOOI	13.21	ıag	Names	
AwardCategory					no
AwardName					no
AwardName					no
AwardParticipantSet	s?				no
AwardSets?					no
BICI?	_				no
BackgroundMusicFlag BankDetailsSet?	3				no no
BeginAnchor					no
BeginAnchor					no
BextCodingHistory					no
BextCodingHistory					no
Bitrate					no
BitsPerAudioSample					no
BitsPerPixel					no
BitsPerPixel					no
BitsPerSample					no
BlackReferenceLevel	L				no
BlockAlign					no
BlockContinuityCour	ıt				no
BlockStartOffset					no
BoundingRectangle? BrandMainTitle					no
BrandMainTitle BrandMainTitle					no no
BrandOriginalTitle					no
BrandOriginalTitle BrandOriginalTitle					no
Branding					MXF
BrandingSets?					no
BroadcastChannel					no
BroadcastDate					no
BroadcastMediumCode	9				no
BroadcastMediumKind	i.				no
BroadcastOrganizati					no
BroadcastOrganizati	onName				no
BroadcastRegion					no
BroadcastRegion					no
BroadcastServiceNam BroadcastTime	ne				no
Broadcastiime BroadcasterRightsTo	Conv				no
BufferDelay?	осору				no no
BuildingName					no
BuildingName					no
Bypass					no
BypassOverride					no
ByteOffset					no
ByteOrder					no
CBEStartOffset					no
CDCIEssenceDescript					MXF
CISACLegalEntityID?					no
CaptionDescription					MXF
CaptionDescriptionS	sets?				no
CaptionKind CaptionKind					no no
CaptionTitles					no
CaptionsDescription	Particina	ntSets	: 2		no
CaptionsViaTeletext			•		no
CaptureAspectRatio					no
CaptureFilmFrameRat	te				no
CaptureGammaEquation					no
CaptureGammaEquation	on				no
CaptureGammaEquatio	n?				no
CatalogDataStatus					no
CatalogDataStatus					no
CatalogPrefixNumber					no
CatalogingSystemNan					no
Channel Aggignment?	wer				no
ChannelAssignment? ChannelCount					no
Channel Handle					no no
ChannelID					no
					110

ChannelIDs	no
ChannelStatusMode	no
CipherAlgorithm?	no
CipherAlgorithmAES128CBC? Citizenship	no
Citizenship	no no
CityName	no
CityName	no
ClassDefinitions?	no
Classification	MXF
ClassificationAndMarkingSystem	no
ClassificationComment	no
ClassificationComment	no
ClassificationNameValueSets?	no
ClassificationReason	no
ClassificationSets?	no
ClassifiedBy	no
ClassifyingCountryCode	no
ClipCreationDateTime	no
ClipFramework	MXF
ClipID	no
ClipIDArray?	no
ClipKind	no
ClipNumber	no
ClipNumber ClipShotSets?	no
CloneCount	no no
ClosedBodyPartition?	no
ClosedCaptionSubtitlesFlag	no
ClosedCompleteBodyPartition?	no
ClosedCompleteHeader	MXF Header
ClosedGOPIndicator	no
ClosedHeader	MXF Header
CodecDefinition?	no
CodecDefinition?	no
*******	
CodecDefinitions?	no
CodecDefinitions? CodecEssenceDescriptor?	no no
CodecDefinitions? CodecEssenceDescriptor? CodecEssenceKinds?	
CodecDefinitions? CodecEssenceDescriptor? CodecEssenceKinds? CodedContentScanningKind	no
CodecDefinitions? CodecEssenceDescriptor? CodecEssenceKinds? CodedContentScanningKind CodingLawKind	no no
CodecDefinitions? CodecEssenceDescriptor? CodecEssenceKinds? CodedContentScanningKind CodingLawKind CodingLawName	no no no no no
CodecDefinitions? CodecEssenceDescriptor? CodecEssenceKinds? CodedContentScanningKind CodingLawKind CodingLawName CodingStyleDefault?	no no no no no no
CodecDefinitions? CodecEssenceDescriptor? CodecEssenceKinds? CodedContentScanningKind CodingLawKind CodingLawName CodingStyleDefault? CollectionName	no no no no no no no no no
CodecDefinitions? CodecEssenceDescriptor? CodecEssenceKinds? CodedContentScanningKind CodingLawKind CodingLawName CodingStyleDefault? CollectionName CollectionName	no
CodecDefinitions? CodecEssenceDescriptor? CodecEssenceKinds? CodedContentScanningKind CodingLawKind CodingLawName CodingStyleDefault? CollectionName CollectionName ColorDescriptor	no
CodecDefinitions? CodecEssenceDescriptor? CodecEssenceKinds? CodedContentScanningKind CodingLawKind CodingLawName CodingStyleDefault? CollectionName CollectionName ColorDescriptor ColorDescriptor	no n
CodecDefinitions? CodecEssenceDescriptor? CodecEssenceKinds? CodedContentScanningKind CodingLawKind CodingLawName CodingStyleDefault? CollectionName CollectionName ColorDescriptor ColorDescriptor ColorFieldCode	no n
CodecDefinitions? CodecEssenceDescriptor? CodecEssenceKinds? CodedContentScanningKind CodingLawKind CodingLawName CodingStyleDefault? CollectionName CollectionName ColorDescriptor ColorDescriptor ColorFieldCode ColorPrimaries	no n
CodecDefinitions? CodecEssenceDescriptor? CodecEssenceKinds? CodedContentScanningKind CodingLawKind CodingLawName CodingStyleDefault? CollectionName CollectionName ColorDescriptor ColorDescriptor ColorFieldCode ColorPrimaries ColorPrimaries?	no n
CodecDefinitions? CodecEssenceDescriptor? CodecEssenceKinds? CodedContentScanningKind CodingLawKind CodingLawName CodingStyleDefault? CollectionName CollectionName ColorDescriptor ColorDescriptor ColorFieldCode ColorPrimaries ColorPrimaries? ColorRangeLevels	no n
CodecDefinitions? CodecEssenceDescriptor? CodecEssenceKinds? CodedContentScanningKind CodingLawKind CodingLawName CodingStyleDefault? CollectionName CollectionName ColorDescriptor ColorDescriptor ColorFieldCode ColorPrimaries ColorPrimaries? ColorRangeLevels ColorSiting	no n
CodecDefinitions? CodecEssenceDescriptor? CodecEssenceKinds? CodedContentScanningKind CodingLawKind CodingLawName CodingStyleDefault? CollectionName CollectionName ColorDescriptor ColorDescriptor ColorFieldCode ColorPrimaries ColorPrimaries? ColorRangeLevels	no n
CodecDefinitions? CodecEssenceDescriptor? CodecEssenceKinds? CodedContentScanningKind CodingLawKind CodingLawName CodingStyleDefault? CollectionName CollectionName ColorDescriptor ColorDescriptor ColorFieldCode ColorPrimaries ColorPrimaries? ColorRangeLevels ColorSiting ColorimetryCode	no n
CodecEssenceDescriptor? CodecEssenceKinds? CodedContentScanningKind CodingLawKind CodingLawName CodingStyleDefault? CollectionName CollectionName ColorDescriptor ColorDescriptor ColorFieldCode ColorPrimaries ColorPrimaries? ColorRangeLevels ColorSiting ColorimetryCode ColorimetryCode?	no n
CodecEssenceDescriptor? CodecEssenceKinds? CodedContentScanningKind CodingLawKind CodingLawName CodingStyleDefault? CollectionName CollectionName ColorDescriptor ColorDescriptor ColorFieldCode ColorPrimaries ColorPrimaries? ColorRangeLevels ColorSiting ColorimetryCode ColorimetryCode? CommunicationSets?	no n
CodecEssenceDescriptor? CodecEssenceKinds? CodedContentScanningKind CodingLawKind CodingLawName CodingStyleDefault? CollectionName CollectionName ColorDescriptor ColorDescriptor ColorFieldCode ColorPrimaries ColorPrimaries? ColorRangeLevels ColorSiting ColorimetryCode ColorimetryCode? CommunicationSets? ComponentAttributes?	no n
CodecEssenceDescriptor? CodecEssenceKinds? CodedContentScanningKind CodingLawKind CodingLawName CodingStyleDefault? CollectionName CollectionName ColorDescriptor ColorDescriptor ColorFieldCode ColorPrimaries ColorPrimaries? ColorRangeLevels ColorSiting ColorimetryCode ColorimetryCode? Communications CompleteFooter?	no n
CodecEssenceDescriptor? CodecEssenceKinds? CodedContentScanningKind CodingLawKind CodingLawName CodingStyleDefault? CollectionName CollectionName ColorDescriptor ColorDescriptor ColorFieldCode ColorPrimaries ColorPrimaries ColorPrimaries? ColorRangeLevels ColorSiting ColorimetryCode ColorimetryCode? CommunicationSets? Communications CompleteFooter? ComponentDataDefinition ComponentDepth	no n
CodecEssenceDescriptor? CodecEssenceKinds? CodedContentScanningKind CodingLawKind CodingLawName CodingStyleDefault? CollectionName CollectionName ColorDescriptor ColorDescriptor ColorFieldCode ColorPrimaries ColorPrimaries ColorPrimaries? ColorRangeLevels ColorSiting ColorimetryCode ColorimetryCode? CommunicationSets? Communications CompleteFooter? ComponentAttributes? ComponentDepth ComponentKLVData?	no n
CodecEssenceDescriptor? CodecEssenceKinds? CodedContentScanningKind CodingLawKind CodingLawName CodingStyleDefault? CollectionName CollectionName ColorDescriptor ColorDescriptor ColorFieldCode ColorPrimaries ColorPrimaries? ColorRangeLevels ColorSiting ColorimetryCode ColorimetryCode? Communications CompleteFooter? ComponentAttributes? ComponentDepth ComponentMaximumRef	no n
CodecEssenceDescriptor? CodecEssenceKinds? CodedContentScanningKind CodingLawKind CodingLawName CodingStyleDefault? CollectionName CollectionName ColorDescriptor ColorDescriptor ColorFieldCode ColorPrimaries ColorPrimaries? ColorRangeLevels ColorSiting ColorimetryCode ColorimetryCode? CommunicationSets? Communications CompleteFooter? ComponentAttributes? ComponentDataDefinition ComponentMaximumRef ComponentMinimumRef	no n
CodecEssenceDescriptor? CodecEssenceKinds? CodedContentScanningKind CodingLawKind CodingLawName CodingStyleDefault? CollectionName CollectionName ColorDescriptor ColorDescriptor ColorFieldCode ColorPrimaries ColorPrimaries? ColorRangeLevels ColorSiting ColorimetryCode ColorimetryCode? CommunicationSets? Communications CompleteFooter? ComponentAttributes? ComponentDataDefinition ComponentDepth ComponentMaximumRef ComponentUserComments?	no n
CodecEssenceDescriptor? CodecEssenceKinds? CodedContentScanningKind CodingLawKind CodingLawName CodingStyleDefault? CollectionName CollectionName ColorDescriptor ColorDescriptor ColorFieldCode ColorPrimaries ColorPrimaries? ColorRangeLevels ColorSiting ColorimetryCode ColorimetryCode? CommunicationSets? Communications CompleteFooter? ComponentAttributes? ComponentDataDefinition ComponentDepth ComponentMaximumRef ComponentUserComments? ComponentSinSequence?	no n
CodecEssenceDescriptor? CodecEssenceKinds? CodedContentScanningKind CodingLawKind CodingLawName CodingStyleDefault? CollectionName CollectionName ColorDescriptor ColorDescriptor ColorFieldCode ColorPrimaries? ColorRangeLevels ColorSiting ColorimetryCode ColorimetryCode? CommunicationSets? Communications ComponentAttributes? ComponentDataDefinition ComponentMaximumRef ComponentSinSequence? ComponentSinSequence? CompositionRendering?	no n
CodecEssenceDescriptor? CodecEssenceKinds? CodedContentScanningKind CodingLawKind CodingLawName CodingStyleDefault? CollectionName CollectionName ColorDescriptor ColorDescriptor ColorFieldCode ColorPrimaries ColorPrimaries? ColorRangeLevels ColorSiting ColorimetryCode ColorimetryCode? CommunicationSets? Communications CompleteFooter? ComponentDataDefinition ComponentDataDefinition ComponentMaximumRef ComponentUserComments? ComponentsInSequence? CompositionRendering? ComputedKeyData	no n
CodecEssenceDescriptor? CodecEssenceKinds? CodedContentScanningKind CodingLawKind CodingLawName CodingStyleDefault? CollectionName CollectionName ColorDescriptor ColorDescriptor ColorFieldCode ColorPrimaries ColorPrimaries ColorPrimaries? ColorSiting ColorimetryCode ColorimetryCode ColorimetryCode? CommunicationSets? Communications CompleteFooter? ComponentAttributes? ComponentDepth ComponentDepth ComponentMaximumRef ComponentMinimumRef ComponentUserComments? ComponentSinSequence? CompositionRendering? ComputedKeyData ComputedKeyData ComputedKeyFrames	no n
CodecEssenceDescriptor? CodecEssenceKinds? CodedContentScanningKind CodingLawKind CodingLawName CodingStyleDefault? CollectionName CollectionName ColorDescriptor ColorDescriptor ColorFieldCode ColorPrimaries? ColorRangeLevels ColorSiting ColorimetryCode ColorimetryCode? CommunicationSets? Communications CompleteFooter? ComponentAttributes? ComponentDataDefinition ComponentMaximumRef ComponentMinimumRef ComponentUserComments? ComponentSInSequence? ComputedKeyData ComputedKeyFrames ComputedKeyFrames ComputedKeySounds	no n
CodecEssenceDescriptor? CodecEssenceKinds? CodedContentScanningKind CodingLawKind CodingLawName CodingStyleDefault? CollectionName CollectionName ColorDescriptor ColorDescriptor ColorFieldCode ColorPrimaries ColorPrimaries ColorPrimaries? ColorSiting ColorimetryCode ColorimetryCode ColorimetryCode? CommunicationSets? Communications CompleteFooter? ComponentAttributes? ComponentDepth ComponentDepth ComponentMaximumRef ComponentMinimumRef ComponentUserComments? ComponentSinSequence? CompositionRendering? ComputedKeyData ComputedKeyData ComputedKeyFrames	no n

	ExifTool	13.24	Tag	Names	
ComputedObjectKind					no
ComputedObjectKind					no
ComputedStratumKind	i				no
ConstantBPictureFla	ag				no
ConsumerRightsToCop	ру				no
ContactDepartmentNa	ame				no
ContactDepartmentNa	ame				no
ContactID?					no
ContactKind					no
ContactKind					no
ContactNameValueSet	cs?				no
ContactsList					MXF
ContactsListSet?					no
ContainerDefinition					no
ContainerLastModify	Date				no
ContainerVersion	•				no
ContentClassificati	-				no
ContentClassificat					no
ContentCodingSyster ContentMaturityDesc					no
ContentMaturityGrap					no
ContentMaturityRat:					no no
ContentPackageIndex					no
ContentPackageMetac					no
ContentStorage?	acallin				no
ContentStorageSet					MXF
ContentValue					no
ContextDescription					no
ContiquousDataFlag					no
Contract					MXF
ContractClauseDesci	ription				no
ContractClauseDesci	ciption				no
ContractDateTime					no
ContractEntity					no
ContractInstallment	Percentag	ge			no
ContractLineCode					no
ContractLineName					no
ContractLineName	G 1 0				no
ContractParticipant	Sets?				no
ContractSets? ContractTermsOfBusi	negg				no no
ContractTermsOfBusi					no
ContractType	LIICSS				no
ContractType					no
ContractTypeCode					no
ContractTypeLink					no
ContributionStatus					no
ContributionStatus					no
ControlPointList?					no
ControlPointTime					no
CopyCount					no
CopyrightLicenseCou					no
CopyrightLicenseReg					no
CopyrightLicenseReg	gionName				no
CopyrightOwnerName					no
CopyrightOwnerName					no
CopyrightStatus					no
CopyrightStatus	- 1				no
CornerLatitudePoint CornerLatitudePoint					no
CornerLatitudePoint					no no
CornerLatitudePoint					
CornerLatitudePoint					no no
CornerLatitudePoint					no
CornerLatitudePoint					no
CornerLatitudePoint					no
CornerLongitudePoir					no
CornerLongitudePoir					no
CornerLongitudePoir					no
CornerLongitudePoir	nt2				no

ExilTool 13.24 Tag Names	
CornerLongitudePoint3	no
CornerLongitudePoint3	no
CornerLongitudePoint4	no
CornerLongitudePoint4	no
CountryCodeMethod	no
CountryCodeMethod	no
CountryName	no
CreateDate	no
CryptographicContext	MXF
CryptographicContextID?	no
CryptographicContextLink?	no
CryptographicContextObject?	no
CryptographicFramework	MXF
CryptographicFrameworkLabel?	no
CryptographicKeyID?	no
Csiz	no
Cue-InWords	no
Cue-InWords	no
Cue-OutWords	no
Cue-OutWords	no
CueWords	MXF
CulturalValue	no
CurrencyCode	no
CurrencyName	no
CurrentNumberInSequence	no
CurrentNumberInSequence	no
CurrentRepeatNumber	no
CutPoint	no
DMFramework	MXF
DMSegment	MXF
DMSet	MXF
DMSourceClip	MXF
DOI?	no
DVBParentalRating	no
DataDefinition?	no
DataDefinitions?	no
DataDeviceKind	no
DataDeviceParameterName	no
DataDeviceParameterSetting	no
DataEnhancementOrModificationDescription	no
DataEssenceCoding	no
DataEssenceCodingID?	no
DateTimeDropFrameFlag	no
DateTimeEmbeddedFlag	no
DateTimeKind?	no
DateTimeRate	no
DeclassificationDate	no
DefaultDataValue?	no
DefaultFadeDuration	no
DefaultFadeEditRate	no
DefaultFadeType?	no
DefaultNamespaceURI	no
DefaultNamespaceURI	no
DefaultObject?	no
DefinedName	no
DefinedName	no
DefinitionObjectID?	no
DefinitionObjectName	no
DefinitionObjectName	no
DegradedEffects?	no
DeltaEntryArray?	no
DerivedFrom	no
Description	no
Description	no
DescriptionKind	no
DescriptionKind	no
DescriptiveComment	no

	ExifTool	13.24	Tag	Names	
DescriptiveComment					no
DescriptiveMetadata	aApplicat:	ionEnvi	roni	mentID	no
DescriptiveMetadata					no
DescriptiveMetadata		);			no
DescriptiveMetadata					no
DescriptiveMetadata DescriptiveMetadata		on a o a o			no
DescriptiveMetadata DescriptiveMetadata		ences:			no no
DescriptiveMetadata					no
DeviceAbsoluteHead:					no
DeviceAbsolutePosi	tionalAccu	ıracy			no
DeviceAbsoluteSpeed	f				no
DeviceAltitude					no
DeviceAltitude					no
DeviceAssetNumber DeviceDesignation					no no
DeviceIDKind					no
DeviceKind					no
DeviceKind					no
DeviceKindCode					no
DeviceLatitude					no
DeviceLatitude					no
DeviceLatitude					no
DeviceLongitude DeviceLongitude					no
DeviceLongitude					no no
DeviceManufacturer	Name				no
DeviceManufacturer					no
DeviceModel					no
DeviceParameterName	eValueSets	3?			no
DeviceParameters	_				MXF
DeviceParametersSet					no
DeviceRelativeHead: DeviceRelativePosit	_				no no
DeviceRelativePosit					no
DeviceRelativePosit	tionZ				no
DeviceRelativePosit	cionalAccu	ıracy			no
DeviceRelativeSpeed	f				no
DeviceSerialNumber					no
DeviceUsageDescript					no
DeviceUsageDescript DeviceXDimension	cion				no
DeviceYDimension					no no
DialNorm					no
Dictionary?					no
DictionaryDescript					no
DictionaryDescript					no
DictionaryIdentific					no
DigitalEncodingBit					no
DigitalMetadataCari DigitalOrAnalogOrig					no
DigitalVideoFileFor	-				no no
DirectorName					no
DiscPartitionCapac	ity				no
DisplayF2Offset					no
DisplayHeight					no
DisplayUnits					no
DisplayUnits					no
DisplayWidth DisplayXOffset					no no
DisplayYOffset					no
Dither					no
DropFrame					no
Duration					no
DynamicSourcePackag					no
DynamicSourceTrack:	LDs				no
E-mailAddress E-mailAddress					no
E-mailAddress EPGProgramSynopsis					no no
EdgeCode					no
-5					

EXIITOOI 13.24 Tag Name	s	•
EdgeCodeFilmGauge?		no
EdgeCodeFormat?		no
EdgeCodeHeader?		no
EdgeCodeStart		no
EditHint?		no
EditRate		no
EditUnitFlags		no
EditUnitLength		no
EditingEventComment		no
EditingEventComment		no
EffectRendering?		no
ElectrospatialFormulation		no
ElementCount		no
ElementDelta		
ElementLength		no
5		no
ElementNameList		no
Emphasis		no
EncryptedContainerLabel?		no
EncryptedSourceValue?		no
EncryptedTrackFileID?		no
EndAnchor		no
EndAnchor		no
EnhancementOrModificationDescription		no
EnumerationUnderlyingIntegerType?		no
EpisodeEndNumber		no
EpisodeNumber		no
EpisodeNumber		no
EpisodeStartNumber		no
<pre>EpisodicItemSets?</pre>		no
EssenceContainerArray?		no
EssenceContainerDataSet		${\tt MXF}$
EssenceContainerFormat?		no
EssenceContainerFormat?		no
EssenceContainers?		no
EssenceData?		no
EssenceDescription?		no
EssenceIsIdentified		no
EssenceLength		no
EssenceLocators?		no
EssenceStreamID		no
Event		${\tt MXF}$
EventAbsoluteDuration		no
EventAbsoluteDuration?		no
EventAbsoluteDurationFrameCount		no
EventAnnotationSets?		no
EventElapsedTimeToEnd		no
EventElapsedTimeToStart		no
EventEndTimeOffset		no
EventEndTimecodeOffset?		no
EventIndication		no
EventIndication		no
EventOrigin		no
EventSets?		no
EventStart		no
EventStartTimeOffset		no
EventStartTimecodeOffset?		no
EventTrack		MXF
EventTrackEditRate		no
ExCCIData?		no
ExposedAspectRatio ExtendedCaptionsLanguageCode		no no
		_
ExtendedClipIDArray2		no
ExtendedClipIDArray?		no
ExtendedTextLanguageCode  ExtendibleElementNemeLigt		no
ExtendibleElementNameList		no
FNumber		no
Fade-InDuration		no
Fade-InType?		no
Fade-OutDuration		no
Fade-OutType?		no

	:	ExifTool	13.24	Tag	Names		
FamilyName						no	o
FamilyName						no	o
FaxNumber						no	2
FaxNumber						no	o
FemaleLeadActres	sNa	me				no	0
FestivalName						no	2
FestivalName						no	0
FieldDominance						no	Э
FieldFrameTypeCo	de					no	Э
FieldOfViewHoriz	ont	al				no	O
FieldOfViewHoriz	ont	al				no	O
FieldOfViewVerti	cal					no	O
FieldOfViewVerti	cal	FP				no	O
FieldRate						no	O
FileDescriptor						M	ΧF
FileDescriptors?						no	C
FileSecurityRepo	rt					no	O
FileSecurityWave	:					no	O
FillerData?						no	O
FilmBatchNumber						no	O
FilmBatchNumber						no	O
FilmCaptureApert						no	O
FilmColorProcess						no	O
FilmFormatName						no	O
FilmFormatName						no	O
FilmFormatName?						no	O
FilmGauge?						no	O
FilmStockKind						no	O
FilmStockKind						no	O
FilmStockManufac						no	O
FilmStockManufac		erName				no	
FilmTestParamete	r					no	
FilmTestResult						no	
FilmTestResult?	٠.					no	
FilmToVideoTrans			n?			no	
FilmToVideoTrans						no	
FilmToVideoTrans		Pnase?				no	
FilteringApplied						no	
FilteringCode						no	
FirstBroadcastFl FirstGivenName	ag					no	
FirstGivenName						no	
	nion	<b>a</b> o				no	
FirstNumberInSeq FirstNumberInSeq						no	
FirstTransmissio						no no	
FixedArrayElemen						no	
FixedChannelStat						no	
FixedUserData?	usb	aca:				no	
FocalLength						no	
FocalLength						no	
Footer?						no	
FormatDescriptor						no	
FormatDescriptor						no	
FormerFamilyName						no	
FormerFamilyName						no	
FrameCenterEleva		n				no	
FrameCenterLatit		_				no	
FrameCenterLatit						no	
FrameCenterLatit						no	
FrameCenterLatit		Longitud	e			no	
FrameCenterLongi						no	o
FrameCenterLongi						no	o
FrameCenterLongi						no	o
FrameCode						no	O
FrameCount						no	O
FrameCountOffset						no	O
FrameLayout						no	Э
FramePositionalA	.ccu	racy				no	O
FrameRate						no	O
FrameworkExtende	dTe:	xtLangua	geCode			no	O

Ех	111001	13.24	Tag	Names	
FrameworkTextLanguage	Code				no
FrameworkThesaurusNam					no
FrameworkThesaurusNam					
	Е				no
FrameworkTitle					no
FrameworkTitle					no
GenerationCloneNumber					no
GenerationCopyNumber					no
GenerationID?					no
GenericDataEssenceDes	criptor	<u>-</u>			MXF
GenericPackage					MXF
GenericPayloads?					no
GenericPictureEssence	Descrir	otor			MXF
GenericSoundEssenceDe					MXF
GenericTrack	scripto	JI			
					MXF
Genre					no
Genre					no
GeographicAreaNorthwe	st?				no
GeographicAreaSourceD	atum				no
GeographicAreaSouthea	st?				no
GeographicLocation?					no
GeographicPolygonCoor	dinates	3?			no
GeographicPolygonSour					no
GeographicalCoordinat					no
GlobalNumber	CD:				_
					no
GraphicKind					no
GraphicUsageKind					no
GraphicUsageKind					no
GroupRelationship					MXF
GroupSet?					no
GroupSets?					no
GroupSynopsis					no
GroupSynopsis					no
HMACAlgorithmSHA1128?					no
HTMLDOCTYPE					no
HTMLDOCTYPE					no
HTMLMetaDescription					no
HTMLMetaDescription					
HardwareAcceleratorFl	. ~				no
	ag				no
HasAudioWatermark					no
HasVideoWatermark					no
HeaderByteCount					no
HistoricalValue					no
HonorsAndQualificatio					no
HonorsAndQualificatio	ns				no
HorizontalActionSafeP	ercenta	age			no
HorizontalDatum					no
HorizontalGraphicsSaf	ePercer	ntage			no
HorizontalSubsampling		5			no
IBTN?					no
IEEEDeviceID					no
IEEEManufacturerID					
					no
ISAN?					no
ISBD?					no
ISBN?					no
ISCI?					no
ISMN?					no
ISO3166CountryCode					no
ISO639-1LanguageCode					no
ISO639-1LanguageCode					no
ISO639CaptionsLanguag	eCode				no
ISO639TextLanguageCod					no
ISRC?					no
ISRN?					no
ISSN?					no
ISTC?					
					no
ISWC?					no
IdenticalGOPIndicator					no
Identification					MXF
Identification					MXF
IdentificationList?					no

EXIITOOI 13.24 Tag Names	
IdentificationSets?	no
IdentificationUL?	no
IdentifierIssuingAuthority	no
IdentifierIssuingAuthority	no
IdentifierKind	no
IdentifierValue	no
ImageAlignmentOffset	no
ImageCategory	no
ImageCoordinateSystem	no
ImageEndOffset	no
ImageFormatSet?	no
ImageHeight	no
ImageSourceDeviceKind	no
ImageSourceDeviceKind	no
ImageStartOffset	no
ImageWidth	no
IncludeSync	no
IndexByteCount	no
IndexDuration	no
IndexEditRate	no
IndexEntryArray?	no
IndexStreamID	no
IndexTableSegment?	no
IndexingStartPosition	no
IndividualAwardName	no
InkNumber	no
InputSegment?	no
InputSegmentCount	no
InputSegments?	no
InsertMusicFlag	no
InstallmentNumber	no
InstanceUID?	no
IntegrationIndication	no
IntegrationIndication	no
IntellectualPropertyDescription	no
IntellectualPropertyDescription	no
IntellectualPropertyLicenseCountryCode	no
IntellectualPropertyLicenseRegionCode	no
IntellectualPropertyLicenseRegionName	no
IntellectualPropertyRights	no
IntellectualPropertyRights	no
IntendedAFD	no
IntentDescriptor	no
IntentDescriptor	no
InterestedPartyName	no
Interpolation?	no
InterpolationDefinitions?	no
IsConcrete	no
IsDubbed	no
IsLiveProduction	no
IsLiveTransmission	no
IsOptional	no
IsRecording	no
IsRepeat	no
IsSearchable	no
IsSigned	no
IsUniqueIdentifier	no
IsVoiceover	no
ItemDesignatorID? ItemID	no
ItemName	no no
ItemName	
ItemValue	no
ItemValue	no no
JFIFMarkerDescription	no
JFIFMarkerDescription	no
JPEG2000PictureSubDescriptor	MXF
JPEGTableID?	no
JobFunctionCode	no
JobFunctionName	no

	EXILIOOT	13.24	Tag	Names	
JobFunctionName					no
JobTitle					no
JobTitle					no
Jurisdiction					no
Jurisdiction					no
KAGSize					no
KLVDataDefinitions'	?				no
KLVDataParentPrope	cties?				no
KLVDataType?					no
KLVDataValue?					no
KLVMetadataSequence	≘?				no
KeyCode?					no
KeyData					no
KeyDataOrProgram					no
KeyFrame					no
KeyFrameSampleCount	-				no
KeyFrames					no
KeyPoint					MXF
KeyPointSets?					no
KeySound					no
KeySounds					no
KeyText					no
KeyTimePoint					no
KeypointKind					no
KeypointKind					no
KeypointValue					no
KeypointValue					no
Keywords					no
Keywords					no
LUID					no
LanguageName					no
LanguageName					no
LastNumberInSequen					no
LastNumberInSequen	ce				no
LayerNumber					no
LeadingLines					no
LengthSystemName					no
LengthUnitKind					no
LicenseOptionsDesc	ription				no
LineNumber					no
LinkedApplicationP					no
LinkedDescriptiveF			ID?		no
LinkedDescriptiveOl		-InID?			no
LinkedGenerationID	?				no
LinkedPackageID?	TD0				no
LinkedTimecodeTracl	STD.				no
LinkedTrackID					no
LinkingName					no
LinkingName					no
LocalCreationDateT			_		no
LocalDatumAbsolute		_			no
LocalDatumRelativel LocalEndDateTime	POSICIONA	ccuracy	<i>!</i>		no
LocalEventEndDateT	lma				no
LocalEventEndDateT					no
LocalEventStartDate					no
LocalEventStartDate					no
LocalFestivalDateT:					no no
LocalFilePath	Lille				no
LocalFilePath					no
LocalID					no
LocalLastModifyDate	3				_
LocalModifyDate	_				no no
LocalStartDateTime					no
LocalTagEntries?					no
LocalTagUniqueID?					no
LocalTagValue					no
LocalTapeNumber					no
LocalTargetID					no
LocalTargetID					no
<u> </u>					-

Exillool 13.24 Tag Names	
LocalUserDateTime	no
Location	MXF
LocationDescription	no
LocationDescription	no
LocationKind	_
LocationKind	no
	no
LocationSets?	no
LockedIndicator	no
LogoFlag	no
LowDelayIndicator	no
LumaEquation	no
LuminanceSampleRate	no
MIC?	no
MICAlgorithm?	no
MIMECharSet	no
MIMECharSet	no
MIMEEncoding	no
MIMEEncoding	no
MIMEMediaType	no
MIMEMediaType	no
MPEG2VideoDescriptor	MXF
MPEG7BiMAccessUnitFrame1?	no
MPEG7BiMAccessUnitFrame2?	no
MPEG7BiMAccessUnitFrame3?	_
MPEG7BiMAccessUnitFrame4?	no
	no
MPEG7BiMAccessUnitFrame5?	no
MPEG7BiMAccessUnitFrame6?	no
MPEG7BiMAccessUnitFrame7?	no
MPEG7BiMAccessUnitFrame8?	no
MPEG7BiMDecoderInitFrame1?	no
MPEG7BiMDecoderInitFrame2?	no
MPEG7BiMDecoderInitFrame3?	no
MPEG7BiMDecoderInitFrame4?	no
MPEG7BiMDecoderInitFrame5?	no
MPEG7BiMDecoderInitFrame6?	no
MPEG7BiMDecoderInitFrame7?	no
MPEG7BiMDecoderInitFrame8?	no
MPEGAudioBitrate	no
MPEGAudioRecodingDataset?	no
MPEGVideoRecodingDataset?	no
MagneticDiskNumber	no
MagneticTrack	no
MainCatalogNumber	no
MainName	no
MainName	no
MainSponsorName	no
MainTitle	no
MainTitle	_
	no
MajorVersion	no
MaleLeadActorName	no
ManufacturerID?	no
ManufacturerInformationObject?	no
MapDatumUsed	no
MarkIn	no
MarkOut	no
MaterialAbsoluteDuration	no
MaterialAbsoluteDuration?	no
MaterialEndTimeOffset	no
MaterialEndTimecodeOffset?	no
MaterialPackage	MXF
MaximumAPIVersion	no
MaximumBPictureCount	no
MaximumGOPSize	no
MaximumSupportedEngineVersion	no
MaximumSupportedPlatformVersion	no
MaximumUseCount	no
MediaLocation	no
MemberNameList	no
MemberTypes?	no
MetadataEncodingSchemeCode	no
THE CAGACABITE COATTIST CITEMIC COAC	110

Exiliodi 13.24 lag Names -	_
MetadataItemName	no
MetadataItemName	no
MetadataServerLocators?	no
MicrophonePlacementTechniques	no
MinimumAPIVersion	no
MinimumSupportedEngineVersion	no
MinimumSupportedPlatformVersion	no
MinorVersion	no
MissionID	no
MissionID	
	no
MobileTelephoneNumber	no
ModifyDate	no
MonoSourceTrackIDs	no
MultipleDescriptor	MXF
NITFLayerTargetID	no
NITFLayerTargetID	no
NMEADocumentText	no
NOLACode	no
NameSuffix	no
NameSuffix	no
NameValue	MXF
NamespacePrefix	no
NamespacePrefix	no
NamespacePrefixes	no
NamespacePrefixes	no
NamespaceURI	no
<del>-</del>	_
NamespaceURI	no
NamespaceURIs	no
NamespaceURIs	no
Nationality	no
Nationality	no
NatureOfPersonality	no
NatureOfPersonality	no
NetworkLocator	MXF
NextNumberInSequence	no
NextNumberInSequence	no
NielsenStreamIdentifier	no
NominationCategory	no
NominationCategory	no
Non-USClassifyingCountryCode	no
ObjectAreaDimension	no
ObjectClass?	no
ObjectClassDefinition?	no
ObjectCountryCode	no
ObjectCountryCode	no
ObjectCountryCodeMethod	no
ObjectDescription	_
	no
ObjectDescription	no
ObjectDescriptionCode	
01-iiiii	no
ObjectHorizontalAverageDimension	no
ObjectIdentificationConfidence	
ObjectIdentificationConfidence ObjectKind	no no no
ObjectIdentificationConfidence ObjectKind ObjectKind	no no
ObjectIdentificationConfidence ObjectKind ObjectKind ObjectModelVersion	no no no
ObjectIdentificationConfidence ObjectKind ObjectKind	no no no no
ObjectIdentificationConfidence ObjectKind ObjectKind ObjectModelVersion	no no no no
ObjectIdentificationConfidence ObjectKind ObjectKind ObjectModelVersion ObjectName	no no no no no no
ObjectIdentificationConfidence ObjectKind ObjectKind ObjectModelVersion ObjectName ObjectRegionCode	no no no no no no no no
ObjectIdentificationConfidence ObjectKind ObjectKind ObjectModelVersion ObjectName ObjectRegionCode ObjectRegionName	no
ObjectIdentificationConfidence ObjectKind ObjectKind ObjectModelVersion ObjectName ObjectRegionCode ObjectRegionName ObjectVerticalAverageDimension	no
ObjectIdentificationConfidence ObjectKind ObjectKind ObjectModelVersion ObjectName ObjectRegionCode ObjectRegionName ObjectVerticalAverageDimension ObliquityAngle	no n
ObjectIdentificationConfidence ObjectKind ObjectKind ObjectModelVersion ObjectName ObjectRegionCode ObjectRegionName ObjectVerticalAverageDimension ObliquityAngle OffsetToIndexTable	no n
ObjectIdentificationConfidence ObjectKind ObjectKind ObjectModelVersion ObjectName ObjectRegionCode ObjectRegionName ObjectVerticalAverageDimension ObliquityAngle OffsetToIndexTable OffsetToIndexTable	no n
ObjectIdentificationConfidence ObjectKind ObjectKind ObjectModelVersion ObjectName ObjectRegionCode ObjectRegionName ObjectVerticalAverageDimension ObliquityAngle OffsetToIndexTable OffsetToIndexTable OffsetToMetadata OffsetTOMetadata	no n
ObjectIdentificationConfidence ObjectKind ObjectKind ObjectModelVersion ObjectName ObjectRegionCode ObjectRegionName ObjectVerticalAverageDimension ObliquityAngle OffsetToIndexTable OffsetToIndexTable OffsetToMetadata OffsetToMetadata OpenBodyPartition?	no n
ObjectIdentificationConfidence ObjectKind ObjectKind ObjectModelVersion ObjectName ObjectRegionCode ObjectRegionName ObjectVerticalAverageDimension ObliquityAngle OffsetToIndexTable OffsetToIndexTable OffsetToMetadata OffsetToMetadata OpenBodyPartition? OpenCompleteBodyPartition?	no n
ObjectIdentificationConfidence ObjectKind ObjectModelVersion ObjectName ObjectRegionCode ObjectRegionName ObjectVerticalAverageDimension ObliquityAngle OffsetToIndexTable OffsetToIndexTable OffsetToMetadata OffsetToMetadata OpenBodyPartition? OpenCompleteBodyPartition?	no n
ObjectKind ObjectKind ObjectKind ObjectModelVersion ObjectName ObjectRegionCode ObjectRegionName ObjectVerticalAverageDimension ObliquityAngle OffsetToIndexTable OffsetToIndexTable OffsetToMetadata OffsetToMetadata OpenBodyPartition? OpenCompleteBodyPartition? OpenCompleteHeader OpenHeader	no n
ObjectKind ObjectKind ObjectModelVersion ObjectName ObjectRegionCode ObjectRegionName ObjectVerticalAverageDimension ObliquityAngle OffsetToIndexTable OffsetToIndexTable OffsetToMetadata OffsetToMetadata OpenBodyPartition? OpenCompleteBodyPartition? OpenCompleteHeader OpenHeader OperatingSystemInterpretations	no n
ObjectKind ObjectKind ObjectKind ObjectModelVersion ObjectName ObjectRegionCode ObjectRegionName ObjectVerticalAverageDimension ObliquityAngle OffsetToIndexTable OffsetToIndexTable OffsetToMetadata OffsetToMetadata OpenBodyPartition? OpenCompleteBodyPartition? OpenCompleteHeader OpenHeader	no n

	FXILLOOT	13.24	Tag	Names	
OperationDefinition	nID?				no
OperationDefinition	ns?				no
OperationParameter:					no
OperationalPattern					no
OpticalDiscNumber					no
OpticalTestParamet	erName				no
OpticalTestResult					no
OpticalTestResult					no
OpticalTrack					no
Organisation					MXF
OrganizationCode					no
OrganizationCode					no
OrganizationID					no
OrganizationID					no
OrganizationIDKind					no
OrganizationIDKind OrganizationIDKind					
OrganizationKind					no
					no
OrganizationKind OrganizationMainNa					no
_					no
OrganizationMainNa	ue				no
OrganizationSets?					no
OrganizationalProg					no
OrganizationalProg	ramnumber				no
Origin					no
OriginCode		_			no
OriginalExtendedSp		ryLangı	iage(	Code	no
OriginalProducerNa					no
OriginalProducerNa	ne				no
OriginalTitle					no
OriginalTitle					no
OtherGivenNames					no
OtherGivenNames					no
OtherValues					no
PII?					no
POSIXMicroseconds					no
PURL					no
PackLength					no
PackageAttributes?					no
PackageID?					no
PackageKLVData?					no
PackageLastModifyDa					no
PackageMarkInPosit					no
PackageMarkOutPosi	tion				no
PackageMarker?					no
PackageName					no
PackageName					no
PackageTimelineMar	kerRef?				no
PackageTracks?					no
PackageUsageKind?					no
PackageUserComment	s?				no
Packages?					no
PaddingBits					no
Palette?					no
PaletteLayout?					no
PanScanInformation	?				no
ParameterDataType?					no
ParameterDefinition	n?				no
ParameterDefinition	ns?				no
Parameters?					no
ParentClass?					no
Participant					MXF
ParticipantID?					no
ParticipantOrganiza	ationSets:	?			no
PartitionMetadata?					no
Password					no
Password					no
PayeeAccountName					no
PayeeAccountNumber					no
PayeeAccountSortCo	de				no
PayerAccountName					no

	ExifTool	13.24	Tag	Names	
PayerAccountNumb	er				no
PayerAccountSort					no
PaymentDueDateTi					no
PaymentsSets?					no
PeakChannelCount					no
PeakEnvelope					no
PeakEnvelopeBloc	kSize				no
PeakEnvelopeData					no
PeakEnvelopeData					no
PeakEnvelopeForm					no
PeakEnvelopeTime					no
PeakEnvelopeVers	ion				no
PeakFrameCount PeakOfPeaksPosit					no
PerceivedDisplay					no no
PerceivedDisplay					no
PerforationsPerF					no
PerforationsPerF					no
Person					MXF
PersonDescriptio	n				no
PersonDescriptio	n				no
PersonOrganizati	onSets?				no
PersonSets?					no
PhysicalInstance					no
PhysicalMediaLen					no
PhysicalMediaLoc					no
PictureComponent					no
PictureDisplayRa	te				no
PictureFormat PixelLayout?					MXF
PlaceKeyword					no no
PlaceKeyword					no
PlaceName					no
PlaceName					no
PlaintextOffset					no
PlatformDesignat	ion				no
PlatformDesignat	ion				no
PlatformHeadingA	ngle				no
PlatformModel					no
PlatformPitchAng					no
PlatformRollAngl					no
PlatformSerialNu	mber				no
Plug-InAPIID?	D.O.				no
Plug-InCategoryI Plug-InDefinitio					no
Plug-InEngineID?	115:				no no
Plug-InLocatorSe	† ?				no
Plug-InPlatformI					no
PointsPerPeakVal					no
PolarCharacteris	tic				no
PosTableArray?					no
PositionInSequen	ce				no
PositionTable?					no
PositionTableCou					no
PositionTableInd	_				no
PositionWithinVi					no
PositionWithinVi		YCoord:	inate	9	no
PostCodeForPostb	OX				no
PostalCode PostalCode					no
PostalCode PostalTown					no no
PostalTown					no
PostboxNumber					no
Preface					MXF
PresentationAspe	ctRatio				no
PresentationGamm					no
PresentationGamm					no
PresenterName					no
PreviousNumberIn					no
PreviousNumberIn	Sequence				no

_	
PreviousRepeatNumber	no
PrimaryExtendedSpokenLanguageCode	
	no
PrimaryOriginalLanguageCode	no
PrimaryPackage?	no
PrimarySpokenLanguageCode	no
Primer	MXF
Processing	MXF
ProcessingSet?	no
ProducerName	no
ProductFormat	no
	_
ProductFormat	no
ProductionFramework	MXF
ProductionOrganizationRole	no
ProductionOrganizationRole	no
	_
ProductionScriptReference	no
ProductionScriptReference	no
ProductionSettingPeriodSets?	no
ProfileAndLevel	no
	_
ProgramAwardName	no
ProgramCommercialMaterialReference	no
ProgramIdentifier	no
ProgramIdentifierString	no
	_
ProgramKind	no
ProgramMaterialClassificationCode	no
ProgramNumber	no
ProgramSupportMaterialReference	no
	_
ProgrammingGroupKind	no
ProgrammingGroupKind	no
ProgrammingGroupTitle	no
ProgrammingGroupTitle	no
	_
ProjectName	no
ProjectName	no
ProjectNumber	no
ProjectSet?	no
Projects	MXF
	IAIVL
Properties?	no
Properties?	no no
Properties? PropertyType?	no
Properties? PropertyType? Publication	no MXF
Properties? PropertyType? Publication PublicationSets?	no MXF no
Properties? PropertyType? Publication	no MXF
Properties? PropertyType? Publication PublicationSets?	no MXF no
Properties? PropertyType? Publication PublicationSets? PublishingMediumName PublishingMediumName	no MXF no no
Properties? PropertyType? Publication PublicationSets? PublishingMediumName PublishingMediumName PublishingOrganizationName	no MXF no no no
Properties? PropertyType? Publication PublicationSets? PublishingMediumName PublishingMediumName PublishingOrganizationName PublishingOrganizationName	no MXF no no no no
Properties? PropertyType? Publication PublicationSets? PublishingMediumName PublishingMediumName PublishingOrganizationName PublishingOrganizationName PublishingRegionName	no MXF no no no
Properties? PropertyType? Publication PublicationSets? PublishingMediumName PublishingMediumName PublishingOrganizationName PublishingOrganizationName	no MXF no no no no
Properties? PropertyType? Publication PublicationSets? PublishingMediumName PublishingMediumName PublishingOrganizationName PublishingOrganizationName PublishingRegionName PublishingRegionName	no MXF no no no no no no
Properties? PropertyType? Publication PublicationSets? PublishingMediumName PublishingMediumName PublishingOrganizationName PublishingOrganizationName PublishingRegionName PublishingRegionName PublishingRegionName PublishingServiceName	no MXF no no no no no no no no
Properties? PropertyType? Publication PublicationSets? PublishingMediumName PublishingMediumName PublishingOrganizationName PublishingOrganizationName PublishingRegionName PublishingRegionName PublishingServiceName PublishingServiceName	no MXF no
Properties? PropertyType? Publication PublicationSets? PublishingMediumName PublishingMediumName PublishingOrganizationName PublishingOrganizationName PublishingRegionName PublishingRegionName PublishingRegionName PublishingServiceName PublishingServiceName PublishingServiceName PublishingServiceName	no MXF no no no no no no no no
Properties? PropertyType? Publication PublicationSets? PublishingMediumName PublishingMediumName PublishingOrganizationName PublishingOrganizationName PublishingOrganizationName PublishingRegionName PublishingRegionName PublishingServiceName PublishingServiceName PublishingServiceName PulldownFieldDominance PulldownSequence?	no MXF no
Properties? PropertyType? Publication PublicationSets? PublishingMediumName PublishingMediumName PublishingOrganizationName PublishingOrganizationName PublishingRegionName PublishingRegionName PublishingRegionName PublishingServiceName PublishingServiceName PublishingServiceName PublishingServiceName	no MXF no
Properties? PropertyType? Publication PublicationSets? PublishingMediumName PublishingMediumName PublishingOrganizationName PublishingOrganizationName PublishingRegionName PublishingRegionName PublishingServiceName PublishingServiceName PublishingServiceName PublishingServiceName PublishingServiceName PulldownFieldDominance PulldownSequence? PurchaserAccountName	no MXF no
Properties? PropertyType? Publication PublicationSets? PublishingMediumName PublishingMediumName PublishingOrganizationName PublishingOrganizationName PublishingRegionName PublishingRegionName PublishingServiceName PublishingServiceName PublishingServiceName PulldownFieldDominance PulldownSequence? PurchaserAccountName	no MXF no
Properties? PropertyType? Publication PublicationSets? PublishingMediumName PublishingMediumName PublishingOrganizationName PublishingOrganizationName PublishingRegionName PublishingRegionName PublishingServiceName PublishingServiceName PublishingServiceName PulldownFieldDominance PulldownSequence? PurchaserAccountName PurchaserAccountName PurchaserAccountNumber	no MXF no
Properties? PropertyType? Publication PublicationSets? PublishingMediumName PublishingMediumName PublishingOrganizationName PublishingOrganizationName PublishingRegionName PublishingRegionName PublishingServiceName PublishingServiceName PublishingServiceName PublishingServiceName PurldownFieldDominance PulldownSequence? PurchaserAccountName PurchaserAccountName PurchaserAccountNumber PurchaserIdentificationKind	no MXF no
Properties? PropertyType? Publication PublicationSets? PublishingMediumName PublishingMediumName PublishingOrganizationName PublishingOrganizationName PublishingRegionName PublishingRegionName PublishingServiceName PublishingServiceName PublishingServiceName PulldownFieldDominance PulldownSequence? PurchaserAccountName PurchaserAccountName PurchaserAccountNumber	no MXF no
Properties? PropertyType? Publication PublicationSets? PublishingMediumName PublishingMediumName PublishingOrganizationName PublishingOrganizationName PublishingRegionName PublishingRegionName PublishingServiceName PublishingServiceName PublishingServiceName PublishingServiceName PulldownFieldDominance PulldownSequence? PurchaserAccountName PurchaserAccountName PurchaserAccountNumber PurchaserIdentificationKind PurchaserIdentificationValue	no MXF no
Properties? PropertyType? Publication PublicationSets? PublishingMediumName PublishingMediumName PublishingOrganizationName PublishingOrganizationName PublishingRegionName PublishingRegionName PublishingServiceName PublishingServiceName PublishingServiceName PublishingServiceName PulldownFieldDominance PulldownFieldDominance PurchaserAccountName PurchaserAccountName PurchaserAccountNumber PurchaserIdentificationKind PurchasingDepartment	no MXF no
Properties? PropertyType? Publication PublicationSets? PublishingMediumName PublishingMediumName PublishingOrganizationName PublishingOrganizationName PublishingRegionName PublishingRegionName PublishingServiceName PublishingServiceName PublishingServiceName PulldownFieldDominance PulldownFieldDominance PurchaserAccountName PurchaserAccountName PurchaserAccountNumber PurchaserIdentificationKind PurchasingDepartment PurchasingOrganizationName	no MXF no
Properties? PropertyType? Publication PublicationSets? PublishingMediumName PublishingMediumName PublishingOrganizationName PublishingOrganizationName PublishingRegionName PublishingRegionName PublishingServiceName PublishingServiceName PublishingServiceName PulldownFieldDominance PulldownFieldDominance PurchaserAccountName PurchaserAccountName PurchaserAccountNumber PurchaserIdentificationKind PurchasingDepartment PurchasingOrganizationName Purpose	no MXF no
Properties? PropertyType? Publication PublicationSets? PublishingMediumName PublishingMediumName PublishingOrganizationName PublishingOrganizationName PublishingRegionName PublishingRegionName PublishingServiceName PublishingServiceName PublishingServiceName PulldownFieldDominance PulldownFieldDominance PurchaserAccountName PurchaserAccountName PurchaserAccountNumber PurchaserIdentificationKind PurchasingDepartment PurchasingOrganizationName	no MXF no
Properties? PropertyType? Publication PublicationSets? PublishingMediumName PublishingMediumName PublishingOrganizationName PublishingOrganizationName PublishingRegionName PublishingRegionName PublishingServiceName PublishingServiceName PublishingServiceName PulldownFieldDominance PulldownFieldDominance PurchaserAccountName PurchaserAccountName PurchaserIdentificationKind PurchasingOrganizationName Purpose Purpose	no MXF no
Properties? PropertyType? Publication PublicationSets? PublishingMediumName PublishingMediumName PublishingOrganizationName PublishingOrganizationName PublishingRegionName PublishingRegionName PublishingServiceName PublishingServiceName PublishingServiceName PublishingServiceName PulldownFieldDominance PulldownFieldDominance PurchaserAccountName PurchaserAccountNumber PurchaserIdentificationKind PurchaserIdentificationValue PurchasingDepartment PurchasingOrganizationName Purpose Purpose QltyBasicData	no MXF no
Properties? PropertyType? Publication PublicationSets? PublishingMediumName PublishingMediumName PublishingOrganizationName PublishingOrganizationName PublishingRegionName PublishingRegionName PublishingServiceName PublishingServiceName PublishingServiceName PublishingServiceName PulldownFieldDominance PulldownFieldDominance PurchaserAccountName PurchaserAccountName PurchaserIdentificationKind PurchaserIdentificationValue PurchasingDepartment PurchasingOrganizationName Purpose Purpose QltyBasicData QltyBasicData	no MXF no
Properties? PropertyType? Publication PublicationSets? PublishingMediumName PublishingMediumName PublishingOrganizationName PublishingOrganizationName PublishingRegionName PublishingRegionName PublishingServiceName PublishingServiceName PublishingServiceName PublishingServiceName PulldownFieldDominance PulldownFieldDominance PurchaserAccountName PurchaserAccountName PurchaserAccountNumber PurchaserIdentificationKind PurchasingDepartment PurchasingOrganizationName Purpose Purpose QltyBasicData QltyBasicData QltyCueSheet	no MXF no
Properties? PropertyType? Publication PublicationSets? PublishingMediumName PublishingOrganizationName PublishingOrganizationName PublishingRegionName PublishingRegionName PublishingServiceName PublishingServiceName PublishingServiceName PublishingServiceName PulldownFieldDominance PulldownFieldDominance PurchaserAccountName PurchaserAccountName PurchaserIdentificationKind PurchaserIdentificationValue PurchasingDepartment PurchasingOrganizationName Purpose Purpose QltyBasicData QltyCueSheet QltyCueSheet	no MXF no
Properties? PropertyType? Publication PublicationSets? PublishingMediumName PublishingMediumName PublishingOrganizationName PublishingOrganizationName PublishingRegionName PublishingRegionName PublishingServiceName PublishingServiceName PublishingServiceName PublishingServiceName PulldownFieldDominance PulldownFieldDominance PurchaserAccountName PurchaserAccountName PurchaserAccountNumber PurchaserIdentificationKind PurchasingDepartment PurchasingOrganizationName Purpose Purpose QltyBasicData QltyBasicData QltyCueSheet	no MXF no
Properties? PropertyType? Publication PublicationSets? PublishingMediumName PublishingOrganizationName PublishingOrganizationName PublishingRegionName PublishingRegionName PublishingServiceName PublishingServiceName PublishingServiceName PublishingServiceName PulldownFieldDominance PulldownFieldDominance PurchaserAccountName PurchaserAccountName PurchaserIdentificationKind PurchaserIdentificationValue PurchasingDepartment PurchasingOrganizationName Purpose Purpose QltyBasicData QltyCueSheet QltyCueSheet QltyEndOfModulation	no MXF no
Properties? PropertyType? Publication PublicationSets? PublishingMediumName PublishingOrganizationName PublishingOrganizationName PublishingRegionName PublishingRegionName PublishingServiceName PublishingServiceName PublishingServiceName PublishingServiceName PulldownFieldDominance PulldownFieldDominance PurchaserAccountName PurchaserAccountName PurchaserIdentificationKind PurchasingDepartment PurchasingOrganizationName Purpose Purpose QltyBasicData QltyBasicData QltyCueSheet QltyEndOfModulation QltyEndOfModulation	no MXF no
PropertyType? Publication PublicationSets? PublishingMediumName PublishingOrganizationName PublishingOrganizationName PublishingRegionName PublishingRegionName PublishingServiceName PublishingServiceName PublishingServiceName PublishingServiceName PublishingServiceName PublishingServiceName PulldownFieldDominance PulldownSequence? PurchaserAccountName PurchaserAccountName PurchaserIdentificationKind PurchaserIdentificationValue PurchasingDepartment PurchasingOrganizationName Purpose QltyBasicData QltyBasicData QltyCueSheet QltyCueSheet QltyEndOfModulation QltyEndOfModulation QltyOperatorComment	no MXF no
PropertyType? Publication PublicationSets? PublishingMediumName PublishingMediumName PublishingOrganizationName PublishingOrganizationName PublishingRegionName PublishingRegionName PublishingServiceName PublishingServiceName PublishingServiceName PublishingServiceName PulldownFieldDominance PulldownFieldDominance PurchaserAccountName PurchaserAccountName PurchaserAccountNumber PurchaserIdentificationKind PurchaserIdentificationValue PurchasingDepartment PurchasingOrganizationName Purpose Purpose QltyBasicData QltyBasicData QltyCueSheet QltyCueSheet QltyEndOfModulation QltyOperatorComment QltyOperatorComment	no MXF no
PropertyType? Publication PublicationSets? PublishingMediumName PublishingOrganizationName PublishingOrganizationName PublishingRegionName PublishingRegionName PublishingServiceName PublishingServiceName PublishingServiceName PublishingServiceName PublishingServiceName PublishingServiceName PulldownFieldDominance PulldownSequence? PurchaserAccountName PurchaserAccountName PurchaserIdentificationKind PurchaserIdentificationValue PurchasingDepartment PurchasingOrganizationName Purpose QltyBasicData QltyBasicData QltyCueSheet QltyCueSheet QltyEndOfModulation QltyEndOfModulation QltyOperatorComment	no MXF no
Properties? PropertyType? Publication PublicationSets? PublishingMediumName PublishingOrganizationName PublishingOrganizationName PublishingRegionName PublishingRegionName PublishingServiceName PublishingServiceName PublishingServiceName PublishingServiceName PublishingServiceName PulldownFieldDominance PulldownSequence? PurchaserAccountName PurchaserAccountName PurchaserIdentificationKind PurchaserIdentificationWalue PurchasingOrganizationName Purpose Purpose Purpose QltyBasicData QltyBasicData QltyCueSheet QltyCueSheet QltyEndOfModulation QltyEndOfModulation QltyOperatorComment QltyOperatorComment QltyQualityEvent	no MXF no
Properties? PropertyType? Publication PublicationSets? PublishingMediumName PublishingMediumName PublishingOrganizationName PublishingOrganizationName PublishingRegionName PublishingRegionName PublishingServiceName PublishingServiceName PublishingServiceName PublishingServiceName PulldownFieldDominance PulldownFieldDominance PulldownSequence? PurchaserAccountName PurchaserAccountNumber PurchaserIdentificationKind PurchaserIdentificationValue PurchasingDepartment PurchasingOrganizationName Purpose Purpose QltyBasicData QltyBasicData QltyCueSheet QltyCueSheet QltyCueSheet QltyEndOfModulation QltyPeratorComment QltyOperatorComment QltyOperatorComment QltyQualityEvent QltyQualityEvent	no MXF no
Properties? PropertyType? Publication PublicationSets? PublishingMediumName PublishingOrganizationName PublishingOrganizationName PublishingRegionName PublishingRegionName PublishingServiceName PublishingServiceName PublishingServiceName PublishingServiceName PublishingServiceName PulldownFieldDominance PulldownSequence? PurchaserAccountName PurchaserAccountName PurchaserIdentificationKind PurchaserIdentificationWalue PurchasingOrganizationName Purpose Purpose Purpose QltyBasicData QltyBasicData QltyCueSheet QltyCueSheet QltyEndOfModulation QltyEndOfModulation QltyOperatorComment QltyOperatorComment QltyQualityEvent	no MXF no

QltyStartOfModulation	no
QltyStartOfModulation	no
QualityFlag	no
QuantizationDefault?	no
RGBAEssenceDescriptor	MXF
RIFFChunkData?	no
RIFFChunkID	no
RIFFChunkLength	no
_	_
RP217DataStreamPID	no
RP217VideoStreamPID	no
RandomIndexMetadata?	no
RandomIndexMetadataV10?	no
Rating	no
RecordedFormat	no
RecordedFormat	no
RecordedTrackNumber	no
RecordingLabelName	no
<del>-</del>	_
RecordingLabelName	no
ReelOrRollNumber	no
RegionCode	no
RegionName	no
RegionName	no
RegisterAction	no
RegisterAdministrationArray?	no
RegisterAdministrationNotes	no
RegisterAdministrationObject?	no
	_
RegisterApproverName	no
RegisterChildEntryArray?	no
RegisterCreationTime	no
RegisterEditorName	no
RegisterEntryAdministrationObject?	no
RegisterEntryArray?	no
RegisterEntryStatus?	no
RegisterItemDefiningDocumentName	no
RegisterItemDefinition	no
	_
RegisterItemHierarchyLevel	no
RegisterItemIntroductionVersion	no
RegisterItemName	no
RegisterItemNotes	no
RegisterItemOriginatorName	no
RegisterItemStatusChangeDateTime	no
RegisterItemSymbol?	no
RegisterItemUL?	no
RegisterKind?	no
RegisterReleaseDateTime	
_	no
RegisterStatusKind?	no
RegisterUserName	no
RegisterUserTime	no
RegisterVersion	no
RegistrantName	no
RelatedMaterialDescription	no
RelatedMaterialDescription	no
RelatedMaterialLocators?	no
RelativePositionInSequenceName	no
RelativePositionInSequenceOffset	no
	_
RelativeScope	no
RelativeTrack	no
ReleasableCountryCode	no
ReleasableCountryCode	no
RenamedType?	no
ResourceID?	no
RestrictionsonUse	no
ReversePlay	no
ReversedByteOrder	no
Rights	MXF
RightsComment	
	no
RightsComment	no
RightsConditionDescription	no
RightsConditionDescription	no
RightsManagementAuthority	no

ExilTool 13.24 Tag Names	
RightsManagementAuthority	no
RightsSets?	no
RightsStartDateTime	no
RightsStopDateTime	no
Rightsholder	no
Rightsholder	no
RoleName	no
RoleName	no
RoomNumber	no
RoomNumber	no
RoomOrSuiteName	no
RoomOrSuiteName	no
RootFormatVersion	no
RootMetaDictionary?	no
RootObjectDirectory?	no
RootPreface?	no
RoundedCaptureFilmFrameRate	no
RoundedTimecodeTimebase	no
RoundingLaw	no
RoundingMethodCode	no
RoyaltyIncomeInformation	no
RoyaltyPaymentInformation	no
Rsiz	no
SDKVersion	no
SICI?	no
SMPTE12MUserDateTime?	no
SMPTE309MUserDateTime?	no
SMPTE337MDataStreamNumber	no
SMPTEUL?	no
SalesContractNumber	no
Salutation	no
Salutation	no
SampleIndex?	no
SampleRate	no
SampledHeight	no
SampledWidth	no
SampledXOffset	no
SampledYOffset	no
SamplingHierarchyCode	no
SamplingStructureCode	no
ScanningDirection	no
SceneFramework	MXF
SceneNumber	no
SceneNumber	no
SceneSettingPeriodSets?	no
SceneShotSets?	no
ScramblingKeyKind	no
ScramblingKeyValue	no
Scripting	MXF
ScriptingKind	no
ScriptingKind	no
ScriptingLocators?	no
ScriptingSets?	no
ScriptingText	no
ScriptingText	no
SeasonEpisodeNumber	no
SeasonEpisodeTitle	no
SecondGivenName	no
SecondGivenName	no
SecondaryExtendedSpokenLanguageCode	no
SecondaryOriginalExtendedSpokenLanguageCode	no
SecondaryOriginalLanguageCode	no
SecondarySpokenLanguageCode	no
SecondaryTitle	no
SecondaryTitle	no
SectorSize	no
SecurityClassification	no
SecurityClassification	no
SecurityClassificationCaveats	no
SecurityClassificationCaveats	no

	ExifTool	13.24 Ta	g Names	
Selected?				no
SensorMode				no
SensorRollAngle				no
SensorSize				no
SensorType				no
SensorTypeCode				no
Sequence?				no
SequenceOffset				no
SequenceSet SeriesNumber				MXF no
SeriesNumber				no
SeriesinaSeriesG	roupCount			no
SetElementType?	-			no
SettingCityName				no
SettingCityName				no
SettingCountryCo	de			no
SettingCountryNa				no
SettingCountryNa	me			no
SettingDateTime				no
SettingDescripti SettingDescripti				no
SettingDescription SettingPeriod	OII			no MXF
SettingPeriodDes	cription			no
SettingPeriodDes	_			no
SettingPostalCod	_			no
SettingPostalCod	.e			no
SettingRegionCod				no
SettingRegionNam				no
SettingRoomNumbe				no
SettingRoomNumbe				no
SettingStateOrPr				no
SettingStateOrPr SettingStreetNam		лсумаше		no no
SettingStreetNam				no
SettingStreetNum		ngName		no
SettingStreetNum				no
SettingTownName				no
SettingTownName				no
ShimName				no
ShootingCountryC				no
ShootingRegionCo				no
ShootingRegionNa	me			no
Shot ShotComment				MXF no
ShotComment				no
ShotCommentKind				no
ShotCommentKind				no
ShotCueWordsSet?				no
ShotDescription				no
ShotDescription				no
ShotDuration				no
ShotList	2			no
ShotLocationSets ShotParticipantR				no
ShotParticipants?	Olesets:			no no
ShotStartPositio	n			no
ShotTrackIDs				no
SideNumber				no
Signal-to-NoiseR	atio			no
SignalFormCode				no
SignalStandard				no
SignalStandard				no
SignatureTuneFla				no
SimpleFlaggingCo				no
SingleSequenceFl Size	ay			no no
SlantRange				no
SlateInformation				no
SlateTitle				no
SliceCount				no

EXILIOOI IJ.21 IAG Names	
SliceNumber	no
SliceOffsetList?	no
Software-OnlySupportFlag	no
SourceClip?	no
SourceContainerFormat?	no
SourceImageCenterXCoordinate	no
SourceImageCenterYCoordinate	no
SourceIndex?	no
SourceKey?	no
SourceLength	no
SourceOrganization	no
SourceOrganization	no
SourcePackage	MXF
SourcePackageID?	no
SourceSpecies?	no
SourceTrackID SourceTrackIDs	no
	no
SourceValue?	no
SpeedChangeEffectFlag	no
SplicingMetadata? StartTimeRelativeToReference	no
StartTimeRelativeToReference	no
StartTimecode	no
StartTimecode StartTimecodeRelativeToReference?	no
	no
StateOrProvinceOrCountyName	no
StateOrProvinceOrCountyName StaticTrack	no MXF
StillFrame?	no
StorageDeviceKind	no
StorageKind	no
StorageKind	no
StorageKindCode	no
StorageMediaID	no
StorageMediaKind	no
StoredANCLineNumber	no
StoredF2Offset	no
StoredVBILineNumber	no
StratumKind	no
StreamData?	no
StreamElementType?	no
StreamID	no
StreamOffset	no
StreamPositionIndicator	no
StreetName	no
StreetName	no
StreetNumber	no
StreetNumber	no
StringElementType?	no
StructuralComponent	MXF
Sub-descriptors?	no
SubDescriptor?	no
SubDescriptors?	no
SubjectAbsoluteHeading	no
SubjectAbsoluteSpeed	no
SubjectDistance	no
SubjectName	no
SubjectName	no
SubjectRelativeHeading	no
SubjectRelativePositionalAccuracy	no
SubjectRelativeSpeed	no
SubtitleDatafileFlag	no
SubtitlesPresent	no
SupplementaryName	no
SupplementaryName	no
SupplementaryOrganizationName	no
SupplementaryOrganizationName	no
SupplierAccountName	no

	FXILIOOI	13.24	Tag	Names	
SupplierAccountName					no
SupplierAccountNumb	er				no
SupplierIdentificat	ionKind				no
SupplierIdentificat	ionValue				no
SupplyContractNumbe	er				no
SupplyingDepartment	Name				no
SupportOrAdministra		ıs			no
SupportOrAdministra					no
SupportOrganization					no
SupportOrganization					no
SystemNameOrNumber					no
TIFFSummary?					no
TaggedValueDefiniti	ons?				no
TaggedValueParentPr					no
TakeNumber	OPCICICS:				no
TapeBatchNumber					
					no
TapeBatchNumber					no
TapeCapacity					no
TapeFormat?					no
TapeFormulation					no
TapeFormulation					no
TapeManufacturer					no
TapeManufacturer					no
TapePartitionCapaci	ty				no
TapeShellKind					no
TapeShellKind					no
TapeStock					no
TapeStock					no
TargetAudience					no
TargetAudience					no
TargetClassOfStrong	Reference	?			no
TargetClassOfWeakRe					no
TargetSet?					no
TargetWidth					no
TechnicalValue					no
TelephoneNumber					no
TelephoneNumber					no
TeletextSubtitlesAv	ailabla				no
TeletextSubtitlesFl					
	ay				no
TemporalOffset	+				no
TerminatingFillerDa	lla				no
TextLocator					MXF
TextlessBlackDurati	.on				no
TextlessMaterial					no
TextualDescriptionK					no
TextualDescription	ind				no
Theme					no
Theme					no
ThemeMusicFlag					no
ThesaurusName					no
ThesaurusName					no
ThirdGivenName					no
ThirdGivenName					no
TimePeriodName					no
TimePeriodName					no
TimeSystemOffset					no
TimeUnitKind					no
TimebaseReferenceTr	ackID				no
TimecodeArray?					no
TimecodeComponent					MXF
TimecodeCreationDat	eTime?				no
TimecodeEndDateTime					no
TimecodeEventEndDat					no
TimecodeEventStartD					no
TimecodeKind					no
TimecodeLastModifyD	ate?				no
TimecodeModifyDate?					no
TimecodeModIIyDate:					_
TimecodeSourcekind TimecodeStartDateTi	mo 2				no
TimecodeStartDateTi					no
rimecodestreampata:					no

	ExifTool	13.24	Tag	Names	
TimecodeTimebase					no
TimecodeTimebase					no
TimecodeUserBitsFla	ag				no
TimepointValue?					no
TimingBiasCorrection					no
TimingBiasCorrection	JIDescript	_1011			no no
TitleKind					no
Titles					MXF
TitlesSets?					no
ToleranceInterpola	tionMethod	?£			no
ToleranceMode?					no
ToleranceWindow?					no
ToolkitVersion TotalCurrencyAmount	_				no no
TotalEpisodeCount	_				no
TotalIncome					no
TotalLinesperFrame					no
TotalNumberInSeque	nce				no
TotalPayment					no
TotalSamplesperLine	9				no
Track TrackID					MXF no
TrackName					no
TrackName					no
TrackNumber					no
TrackNumberBatch					no
Tracks?					no
TrafficID					no
TrailingLines TranscriptReference	2				no no
TranscriptReference					no
TransferFilmFrameRa					no
TransitionEffect?					no
TransmissionID					no
TransportStreamID					no
TripletSequenceNuml TypeDefinitionElem		i a t			no
TypeDefinitionExten			l 1169'	?	no no
TypeDefinitions?	idibiclici	iiciic va.	Lucb	•	no
UCSEncoding					no
UPID?					no
UPN?					no
URL					no
URL URL					no no
URL					no
URN					no
UTCEndDateTime					no
UTCEventEndDateTime					no
UTCEventEndDateTime					no
UTCEventStartDateT: UTCEventStartDateT:					no
UTCInstantDateTime	riile				no no
UTCInstantDateTime					no
UTCLastModifyDate					no
${\tt UTCLastModifyDate}$					no
UTCStartDateTime					no
UTCStartDateTime					no
UTCUserDateTime UniformDataFlag					no
UnknownBWFChunks?					no no
UpstreamAudioCompre	essionAlq	orithm			no
UseDefaultValue	٠, ر				no
UserDataMode?					no
UserName					no
UserName					no
UserPosition V10IndexTableSegmen	n t- 2				no no
VIOINdexTableSegmen VBEEndOffset	.10 ;				no

	EXILIOOI	13.24	Tag	Names	
VBIDataDescriptor					MXF
VBILineCount					
					no
VBIPayloadByteArra;					no
VBIPayloadSampleCo					no
VBIPayloadSampleCo	unt				no
VBIWrappingType					no
VC-1AverageBitrate					no
_					
VC-1BPictureCount					no
VC-1CodedContentTy	pe				no
VC-1IdenticalGOP					no
VC-1Initialization	Metadata?				no
VC-1Level					no
VC-1MaximumBitrate					no
VC-1MaximumGOP					no
VC-1Profile					no
VC-1SingleSequence					no
Value?					_
					no
VariableArrayEleme:	ntType?				no
VersionNumber					no
VersionNumberString	q				no
VersionNumberString	_				no
VersionTitle	3				
					no
VersionTitle					no
VerticalActionSafe:	Percentage	9			no
VerticalDatum					no
VerticalGraphicsSa	feDercent:	ane			no
		age			_
VerticalSub-sampli					no
VideoAndFilmFrameR	elationsh:	ip			no
VideoAverageBitrat	е				no
VideoClipDuration					no
VideoCodingSchemeI	D				
_	U				no
VideoColorKind					no
VideoCompressionAl	gorithm				no
VideoDeviceKind					no
VideoDeviceParamet	erName				no
VideoDeviceParamet					_
	ersecting				no
VideoFixedBitrate					no
VideoIndexArray?					no
VideoLineMap					no
VideoNoiseReductio	nAlgorith	n			no
VideoOrImageCompre					
	_	LICIIII			no
VideoPayloadIdenti					no
VideoPayloadIdenti	fier2002				no
VideoTestParameter					no
VideoTestResult					no
VideoTestResult					
					no
VideoWatermarkKind					no
ViewportAspectRation	0				no
ViewportHeight					no
ViewportImageCente:	rCCoordina	ate			no
ViewportImageCente:	LICOOLUIII	ace			no
ViewportWidth					no
VoiceTalentName					no
WAVESummary?					no
WaveAudioDescripto:	r				MXF
Weighting	_				no
5 5	,				
WhiteReferenceLeve					no
Work-in-ProgressFl	ag				no
WorkingTitle					no
WorkingTitle					no
XMLDocumentText?					no
XMLDocumentText					no
XMLDocumentText					no
XMLDocumentText?					no
XOsiz					no
XTOsiz					
					no
XTsiz					no
Xsiz					no
YOsiz					no
YTOsiz					no
					-

YTsiz	no
Ysiz	no

### MXF Header Tags

Index1	Tag Name	Writable
0	MXFVersion	no
24	FooterPosition	no
32	HeaderSize	no

# DV Tags

The following tags are extracted from DV videos.

Tag Name	Writable
AspectRatio	no
AudioBitsPerSample	no
AudioChannels	no
AudioSampleRate	no
Colorimetry	no
DateTimeOriginal	no
Duration	no
FrameRate	no
ImageHeight	no
ImageWidth	no
TotalBitrate	no
VideoFormat	no
VideoScanType	no

#### Flash Tags

The information below is extracted from SWF (Shockwave Flash) files. Tags with string ID's represent information extracted from the file header.

Tag ID	Tag Name	Writable
'Compressed'	Compressed	no
'Duration'	Duration	no
'FlashVersion'	FlashVersion	no
'FrameCount'	FrameCount	no
'FrameRate'	FrameRate	no
'ImageHeight'	ImageHeight	no
'ImageWidth'	ImageWidth	no
$0 \times 0045$	FlashAttributes	no
0x004d	XMP	XMP

# Flash FLV Tags

Information is extracted from the following packets in FLV (Flash Video) files.

Tag ID	Tag Name	Writable
8000x0	Audio	Flash Audio
0x0009	Video	Flash Video
$0 \times 0012$	Meta	Flash Meta

### Flash Audio Tags

Information extracted from the Flash Audio header.

Tag Name	Writable
AudioEncoding	no
AudioSampleRate	no
AudioBitsPerSample	no
AudioChannels	no
	AudioEncoding AudioSampleRate AudioBitsPerSample

# Flash Video Tags

Information extracted from the Flash Video header.

Tag ID	Tag Name	Writable
'Bit4-7'	VideoEncoding	no

# Flash Meta Tags

Below are a few observed FLV Meta tags, but ExifTool will attempt to extract information from any tag found.

Tag ID	Tag Name	Writable
'audiocodecid' 'audiodatarate' 'audiodelay' 'audiosamplerate' 'audiosamplesize' 'audiosize' 'bytelength' 'canSeekToEnd' 'canseekOntime'	AudioCodecID AudioBitrate AudioDelay AudioSampleRate AudioSampleSize AudioSize ByteLength CanSeekToEnd CanSeekOnTime	no n
<pre>'createdby' 'creationdate' 'cuePoints' 'datasize' 'duration' 'filesize'</pre>	CreatedBy CreateDate CuePoint DataSize Duration FileSizeBytes	no no Flash CuePoint no no no
<pre>'framerate' 'hasAudio' 'hasCuePoints' 'hasKeyframes' 'hasMetadata' 'hasVideo'</pre>	FrameRate HasAudio HasCuePoints HasKeyFrames HasMetadata HasVideo	no no no no no no no
<pre>'height' 'httphostheader' 'keyframesFilepositions' 'keyframesTimes' 'lastkeyframetimestamp'</pre>	ImageHeight HTTPHostHeader KeyFramePositions KeyFramesTimes LastKeyFrameTime	no no no no no
'lasttimestamp' 'liveXML' 'metadatacreator' 'metadatadate' 'pmsg' 'purl'	LastTimeStamp XMP MetadataCreator MetadataDate Message URL	no XMP no no no no
<pre>'sourcedata' 'starttime' 'stereo' 'totaldatarate' 'totalduration' 'videocodecid'</pre>	SourceData StartTime Stereo TotalDataRate TotalDuration VideoCodecID	no no no no no no no
'videodatarate' 'videosize' 'width'	VideoBitrate VideoSize ImageWidth	no no no

### Flash CuePoint Tags

These tag names are added to the CuePoint name to generate complete tag names like "CuePoint0Name".

Tag ID	Tag Name	Writable
'name'	Name	no
'parameters'	Parameter	Flash Parameter
'time'	Time	no
'type'	Туре	no

# Flash Parameter Tags

There are no pre-defined parameter tags, but ExifTool will extract any existing parameters, with tag names like "CuePoint0ParameterXxx".

```
Tag ID Tag Name Writable
-----
[no tags known]
```

#### Real Tags

ExifTool recognizes three basic types of Real audio/video files: 1) RealMedia (RM, RV and RMVB), 2) RealAudio (RA), and 3) Real Metafile (RAM and RPM).

#### Real Media Tags

These Tag ID's are Chunk ID's used in RealMedia and RealVideo (RM, RV and RMVB) files.

Tag ID	Tag Name	Writable
'CONT'	CONT	Real ContentDescr
'MDPR'	MDPR	Real MediaProps
'PROP'	PROP	Real Properties
'RJMD'	RJMD	Real Metadata

#### Real ContentDescr Tags

Sequence	Tag Name	Writable
0	TitleLen?	no
1	Title	no
2	AuthorLen?	no
3	Author	no
4	CopyrightLen?	no
5	Copyright	no
6	CommentLen?	no
7	Comment	no

# Real MediaProps Tags

Sequence	Tag Name	Writable
0	StreamNumber	no
1	StreamMaxBitrate	no
2	StreamAvgBitrate	no
3	StreamMaxPacketSize	no
4	StreamAvgPacketSize	no
5	StreamStartTime	no
6	StreamPreroll	no
7	StreamDuration	no
8	StreamNameLen?	no
9	StreamName	no
10	StreamMimeLen?	no
11	StreamMimeType	no
12	FileInfoLen?	no
13	FileInfoLen2?	no
14	FileInfoVersion	no
15	PhysicalStreams?	no
16	PhysicalStreamNumbers?	no
17	DataOffsets?	no
18	NumRules?	no
19	PhysicalStreamNumberMap?	no
20	NumProperties?	no
21	FileInfoProperties	Real FileInfo

### Real FileInfo Tags

The following tags have been observed in the FileInfo properties, but any other existing information will also be extracted.

Tag ID Tag Name Writable

'Audiences'	Audiences	no
'Audio Format'	AudioFormat	no
'Content Rating'	ContentRating	no
'Creation Date'	CreateDate	no
'Description'	Description	no
'File ID'	FileID	no
'Generated By'	Software	no
'Indexable'	Indexable	no
'Keywords'	Keywords	no
'Modification Date'	ModifyDate	no
'Target Audiences'	TargetAudiences	no
'Video Quality'	VideoQuality	no
'audioMode'	AudioMode	no
'videoMode'	VideoMode	no

#### Real Properties Tags

Sequence	Tag Name	Writable
0	MaxBitrate	no
1	AvgBitrate	no
2	MaxPacketSize	no
3	AvgPacketSize	no
4	NumPackets	no
5	Duration	no
6	Preroll	no
7	<pre>IndexOffset?</pre>	no
8	DataOffset?	no
9	NumStreams	no
10	Flags	no

#### Real Metadata Tags

The tags below represent information which has been observed in the Real Metadata format, but ExifTool will extract any information it finds in this format. (As far as I can tell from the referenced documentation, string values should be plain text, but this is not the case for the only sample file I have been able to obtain containing this information. These tags could also be split into separate subdirectories, but this will wait until I have better documentation or a more complete set of samples.)

Tag ID	Tag Name	Writable
'Album/Name'	AlbumName	no
'Track/Category'	TrackCategory	no
'Track/Comments'	TrackComments	no
'Track/Lyrics'	TrackLyrics	no

### Real Audio Tags

Tags in the following table reference information extracted from various versions of RealAudio (RA) files.

Tag ID	Tag Name	Writa	able
'.ra3'	RA3	Real	AudioV3
'.ra4'	RA4	Real	AudioV4
'.ra5'	RA5	Real	AudioV5

#### Real AudioV3 Tags

Sequence	Tag Name	Writable
0	Channels	no
1	Unknown?	no
2	BytesPerMinute	no
3	AudioBytes	no
4	TitleLen?	no

5	Title	no
6	ArtistLen?	no
7	Artist	no
8	CopyrightLen?	no
9	Copyright	no
10	CommentLen?	no
11	Comment	no

# Real AudioV4 Tags

Sequence	Tag Name	Writable
0	FourCC1?	no
1	AudioFileSize?	no
2	Version2?	no
3	HeaderSize?	no
4	CodecFlavorID?	no
5	CodedFrameSize?	no
6	AudioBytes	no
7	BytesPerMinute	no
8	Unknown?	no
9	SubPacketH?	no
10	AudioFrameSize	no
11	SubPacketSize?	no
12	Unknown?	no
13	SampleRate	no
14	Unknown?	no
15	BitsPerSample	no
16	Channels	no
17	FourCC2Len?	no
18	FourCC2?	no
19	FourCC3Len?	no
20	FourCC3?	no
21	Unknown?	no
22	Unknown?	no
23	TitleLen?	no
24	Title	no
25	ArtistLen?	no
26	Artist	no
27	CopyrightLen?	no
28	Copyright	no
29	CommentLen?	no
30	Comment	no

# Real AudioV5 Tags

Sequence	Tag Name	Writable
0	FourCC1?	no
1	AudioFileSize?	no
2	Version2?	no
3	HeaderSize?	no
4	CodecFlavorID?	no
5	CodedFrameSize?	no
6	AudioBytes	no
7	BytesPerMinute	no
8	Unknown?	no
9	SubPacketH?	no
10	FrameSize?	no
11	SubPacketSize?	no
12	SampleRate	no
13	SampleRate2?	no
14	BitsPerSample	no
15	Channels	no
16	Genr?	no
17	FourCC3?	no

# Real Metafile Tags

Tags representing information extracted from Real Audio Metafile and

RealMedia Plug-in Metafile (RAM and RPM) files.

Tag ID	Tag Name	Writable
'txt'	Text	no
'url'	URL	no

# Red Tags

Tags extracted from Redcode R3D video files.

Tag ID	Tag Name	Writable
'RED1'	Red1Header	Red RED1
'RED2'	Red2Header	Red RED1
0x1000	StartEdgeCode	no
0x1001	StartTimecode	no
0x1002	OtherDate1	no
0x1003	OtherDate2	no
0x1004	OtherDate3	no
0x1005	DateTimeOriginal	no
0x1006	SerialNumber	no
0x1019	CameraType	no
0x101a	ReelNumber	no
0x101b	Take	no
0x1023	DateCreated	no
0x1024	TimeCreated	no
0x1025	FirmwareVersion	no
0x1029	ReelTimecode	no
0x102a	StorageType	no
0x1030	StorageFormatDate	no
0x1031	StorageFormatTime	no
0x1032	StorageSerialNumber	no
0x1033	StorageModel	no
0x1036	AspectRatio	no
0x1042	Revision	no
0x1056	OriginalFileName	no
0x106e	LensMake	no
0x106f	LensNumber	no
0x1070	LensModel	no
0x1071	Model	no
0x107c	CameraOperator	no
0x1086	VideoFormat	no
0x1096	Filter	no
0x10a0	Brain	no
0x10a1	Sensor	no
0x200d	ColorTemperature	no
0x204b 0x2066	RGBCurves	no
0x2066 $0x4037$	OriginalFrameRate	no
0x4037 0x403b	CropArea ISO	no
0x403b 0x406a	FNumber	no
0x406a 0x406b	FocalLength	no no
0x406D	FocusDistance	no
JAUUUC	1 OCADDIBUATION	110

# Red RED1 Tags

Redcode version 1 header.

Index1	Tag Name	Writable
7	RedcodeVersion	no
54	ImageWidth	no
58	ImageHeight	no
62	FrameRate	no
67	OriginalFileName	no

# Red RED2 Tags

Redcode version 2 header.

Index1	Tag Name	Writable
7	RedcodeVersion	no
76	ImageWidth	no
80	ImageHeight	no
86	FrameRate	no

### AIFF Tags

Tags extracted from Audio Interchange File Format (AIFF) files. See <a href="http://www-mmsp.ece.mcgill.ca/Documents/AudioFormats/AIFF/AIFF.html">http://www-mmsp.ece.mcgill.ca/Documents/AudioFormats/AIFF/AIFF.html</a> for the AIFF specification.

Tag ID	Tag Name	Writable
'(c) '	Copyright	no
' ANNO '	Annotation	no
'APPL'	ApplicationData	no
'AUTH'	Author	no
'COMM'	Common	AIFF Common
'COMT'	Comment	AIFF Comment
'FVER'	FormatVersion	AIFF FormatVers
'ID3 '	ID3	ID3
'NAME'	Name	no

#### AIFF Common Tags

Index2	Tag Name	Writable
0	NumChannels	no
1	NumSampleFrames	no
3	SampleSize	no
4	SampleRate	no
9	CompressionType	no
11	CompressorName	no

#### AIFF Comment Tags

Tag ID	Tag Name	Writable	
0x0000	CommentTime	no	
$0 \times 0001$	MarkerID	no	
$0 \times 0002$	Comment	no	

# AIFF FormatVers Tags

Index4 Tag Name	Tag Name	Writable
0	FormatVersionTime	no

# ASF Tags

The ASF format is used by Windows WMA and WMV files, and DIVX videos. Tag ID's aren't listed because they are huge 128-bit GUID's that would ruin the formatting of this table.

Tag Name	Writable
SimpleIndex	no
TimecodeIndex	no
Header	ASF Header
Data	no
XMP	XMP
Index	no
MediaIndex	no

# ASF Header Tags

Tag Name	Writable
Padding	no
ScriptCommand	no

 ${\tt ContentBranding}$ ASF ContentBranding ContentEncryption no DigitalSignature no ExtendedContentEncryption no HeaderExtension ASF HeaderExtension ContentDescription ASF ContentDescr ErrorCorrection no StreamBitrateProps CodecList ASF CodecList FileProperties ASF FileProperties StreamProperties ASF StreamProperties ASF ExtendedDescr ExtendedContentDescr BitrateMutualExclusion no Marker no

# ASF ContentBranding Tags

Tag Name	Writable
BannerImageType	no
BannerImage	no
BannerImageURL	no
CopyrightURL	no

### ASF HeaderExtension Tags

Tag Name	Writable
ExtendedStreamProps	no
AdvancedContentEncryption	no
MetadataLibrary	ASF ExtendedDescr
TimecodeIndexParms	no
Compatibility	no
LanguageList	no
AdvancedMutualExcl	no
BandwidthSharing	no
Reserved1	no
Metadata	ASF ExtendedDescr
GroupMutualExclusion	no
StreamPrioritization	no
IndexParameters	no

## ASF ExtendedDescr Tags

Tag Name	Writable
ASFLeakyBucketPairs	no
ASFPacketCount	no
ASFSecurityObjectsSize	no
AlbumArtist	no
AlbumCoverURL	no
AlbumTitle	no
AspectRatioX	no
AspectRatioY	no
AudioFileURL	no
AudioSourceURL	no
Author	no
AuthorURL	no
AverageLevel	no
BannerImageData	no
BannerImageType	no
BannerImageURL	no
BeatsPerMinute	no
Bitrate	no
Broadcast	no
BufferAverage	no
Can_Skip_Backward	no
Can_Skip_Forward	no
Category	no
Codec	no

EXILIOOI 13.21 Tag Names	
Composer	no
Conductor	no
ContainerFormat	no
ContentDistributor	no
ContentGroupDescription	no
Copyright	no
CopyrightURL CurrentBitrate	no
DRM	no no
DRM ContentID	no
DRM DRMHeader	no
DRM_DRMHeader_ContentDistributor	no
DRM_DRMHeader_ContentID	no
DRM_DRMHeader_IndividualizedVersion	no
DRM_DRMHeader_KeyID	no
DRM_DRMHeader_LicenseAcqURL	no
DRM_DRMHeader_SubscriptionContentID	no
DRM_IndividualizedVersion	no
DRM_KeyID	no
DRM_LASignatureCert	no
DRM_LASignatureLicSrvCert	no
DRM_LASignaturePrivKey	no
DRM_LASignatureRootCert	no
DRM_LicenseAcqURL	no
DRM_V1LicenseAcqURL	no
DVDID	no
Description	no
Director	no
Duration	no
EncodedBy	no
EncodingSettings	no
EncodingTime FileSize	no
Genre	no no
GenreID	no
HasArbitraryDataStream	no
HasAttachedImages	no
HasAudio	no
HasFileTransferStream	no
HasImage	no
HasScript	no
HasVideo	no
ISRC	no
InitialKey	no
IsVBR	no
Is_Protected	no
Is_Trusted	no
Language	no
Lyrics	no
Lyrics_Synchronised	no
MCDI	no
MediaClassPrimaryID MediaClassSecondaryID	no
MediaCredits	no
MediaIsDelay	no no
MediaIsFinale	no
MedialsLive	no
MediaIsPremiere	no
MediaIsRepeat	no
MediaIsSAP	no
MediaIsStereo	no
MediaIsSubtitled	no
MediaIsTape	no
MediaNetworkAffiliation	no
MediaOriginalBroadcastDateTime	no
MediaOriginalChannel	no
MediaStationCallSign	no
MediaStationName	no
ModifiedBy	no
Mood	no

NSC_Address	no
NSC_Description	no
NSC_Email	no
NSC_Name	no
NSC_Phone	no
NumberOfFrames	no
OptimalBitrate	no
OriginalAlbumTitle	no
OriginalArtist	no
OriginalFileName	no
OriginalLyricist	no
OriginalReleaseTime	no
OriginalReleaseYear	no
ParentalRating	no
ParentalRatingReason	no
PartOfSet	no
PeakBitrate	no
PeakValue	no
Period	no
Picture	ASF Picture
PlaylistDelay	no
Producer	no
PromotionURL	no
ProtectionType	no
Provider	no
ProviderCopyright	no
ProviderRating	no
ProviderStyle	no
Publisher	no
RadioStationName	no
RadioStationOwner	no
Rating	no
Seekable	no
SharedUserRating	no
Signature_Name	_
StreamTypeInfo	no
Stridable	no
Subtitle	no
	no
SubtitleDescription	no
SubscriptionContentID	no
Text	no
Title	no
ToolName	no
ToolVersion	no
Track	no
TrackNumber	no
UniqueFileIdentifier	no
UserWebURL	no
VBRPeak	no
VideoClosedCaptioning	no
VideoFrameRate	no
VideoHeight	no
VideoWidth	no
WMADRCAverageReference	no
WMADRCAverageTarget	no
WMADRCPeakReference	no
WMADRCPeakTarget	no
WMCollectionGroupID	no
WMCollectionID	no
WMContentID	no
Writer	no
Year	no

# ASF Picture Tags

Tag Name	Writable
PictureType	no
PictureMIMEType	no
PictureDescription	no

Picture no

# ASF ContentDescr Tags

Tag Name	Writable
Title	no
Author	no
Copyright	no
Description	no
Rating	no

### ASF CodecList Tags

Tag Name	Writable
AudioCodecDescription	no
AudioCodecName	no
OtherCodecDescription	no
OtherCodecName	no
VideoCodecDescription	no
VideoCodecName	no

# ASF FileProperties Tags

Index1	Tag Name	Writable
0	FileID	no
16	FileLength	no
24	CreationDate	no
32	DataPackets	no
40	Duration	no
48	SendDuration	no
56	Preroll	no
64	Flags	no
68	MinPacketSize	no
72	MaxPacketSize	no
76	MaxBitrate	no

# ASF StreamProperties Tags

Tags with index 54 and greater are conditional based on the StreamType.

Index1	Tag Name	Writable
0	StreamType	no
16	ErrorCorrectionType	no
32	TimeOffset	no
48	StreamNumber	no
54	AudioCodecID	no
	ImageWidth	no
56	AudioChannels	no
58	AudioSampleRate	no
	ImageHeight	no

### WTV Tags

Tags found in Windows recorded TV (WTV) videos.

Tag ID	Tag Name	Writable
'table.0.entries.legacy attrib'	Metdata	WTV Metadata

### WTV Metadata Tags

ExifTool will extract any tag found, even if not in this table.

Tag Name	Writable
ATSCContent	no
ActualSoftPostPadding	no

EXIITOOI 13.24 Ta	g Names
ActualSoftPrePadding	no
Bitrate?	no
BrandingImageID	no
BrandingName	no
ContentProtected	no
ContentProtectedPercent	no
DTVContent	no
Duration	no
EncodeTime	no
EndTime	no
ExpirationDate?	no
ExpirationSpan?	no
Genre	no
HDContent	no
HardPostPadding	no
HardPrePadding	no
InBandRatingAttributes	_
InBandRatingLevel	no
<del>-</del>	no
InBandRatingSystem	no
KeepUntil	no
Language	no
MediaClassPrimaryID	no
MediaClassSecondaryID	no
MediaCredits	no
MediaIsDelay	no
MediaIsFinale	no
MediaIsLive	no
MediaIsMovie	no
MediaIsPremiere	no
MediaIsRepeat	no
MediaIsSAP	no
MediaIsSport	no
MediaIsStereo	no
MediaIsSubtitled	no
MediaIsTape	no
MediaNetworkAffiliation	no
MediaOriginalBroadcastDateTime	no
MediaOriginalChannel	no
MediaOriginalChannelSubNumber	no
MediaOriginalRunTime	no
MediaStationCallSign MediaStationName	no
	no
MediaThumbAspectRatioX	no
MediaThumbAspectRatioY	no
MediaThumbHeight	no
MediaThumbRatingAttributes	no
MediaThumbRatingLevel	no
MediaThumbRatingSystem MediaThumbRet	no
MediaThumbStride	no
MediaThumbTimeStamp?	no
MediaThumbWidth	no
OriginalReleaseTime	no
OriginalSoftPostPadding	no
OriginalSoftPrePadding	no
ParentalRating	no
ParentalRatingReason	no
ProgramID	no
Provider	no
ProviderCopyright	no
ProviderRating	no no
Quality	no
RequestID	
ScheduleItemID	no no
SeriesUID	no
ServiceID	no
Subtitle	no
SubtitleDescription	no
Title	no
VideoClosedCaptioning	no
<del></del>	

Watched no

### DICOM Tags

The DICOM format is based on the ACR-NEMA specification, but adds a file header and a number of new tags. ExifTool will extract information from either type of file. The Tag ID's in the following table are the tag group and element numbers in hexadecimal, as given in the DICOM specification (see <a href="http://medical.nema.org/">http://medical.nema.org/</a>). The table below contains tags from the DICOM 2009 and earlier specifications plus some vendor-specific private tags.

Note that DICOM information may be saved in other file formats using the XMP DICOM Tags.

Tag ID	Tag Name	Writable
0002,0000	FileMetaInfoGroupLength	no
0002,0001	FileMetaInfoVersion	no
0002,0002	MediaStorageSOPClassUID	no
0002,0003	MediaStorageSOPInstanceUID	no
0002,0010	TransferSyntaxUID	no
0002,0012	ImplementationClassUID	no
0002,0013	ImplementationVersionName	no
0002,0016	SourceApplicationEntityTitle	no
0002,0100	PrivateInformationCreatorUID	no
0002,0102	PrivateInformation	no
0004,1130	FileSetID	no
0004,1141	FileSetDescriptorFileID	no
0004,1142	SpecificCharacterSetOfFile	no
0004,1200	FirstDirectoryRecordOffset	no
0004,1202	LastDirectoryRecordOffset	no
0004,1212	FileSetConsistencyFlag	no
0004,1220	DirectoryRecordSequence	no
0004,1400	OffsetOfNextDirectoryRecord	no
0004,1410	RecordInUseFlag	no
0004,1420	LowerLevelDirectoryEntityOffset	no
0004,1430	DirectoryRecordType	no
0004,1432	PrivateRecordUID	no
0004,1500	ReferencedFileID	no
0004,1504	MRDRDirectoryRecordOffset	no
0004,1510	ReferencedSOPClassUIDInFile	no
0004,1511	ReferencedSOPInstanceUIDInFile	no
0004,1512	ReferencedTransferSyntaxUIDInFile ReferencedRelatedSOPClassUIDInFile	no
0004,151A 0004,1600	NumberOfReferences	no
0004,1000	IdentifyingGroupLength	no no
0008,0001	LengthToEnd	no
0008,0005	SpecificCharacterSet	no
0008,0006	LanguageCodeSequence	no
0008,0008	ImageType	no
0008,0010	RecognitionCode	no
0008,0012	InstanceCreationDate	no
0008,0013	InstanceCreationTime	no
0008,0014	InstanceCreatorUID	no
0008,0016	SOPClassUID	no
0008,0018	SOPInstanceUID	no
0008,001A	RelatedGeneralSOPClassUID	no
0008,001B	OriginalSpecializedSOPClassUID	no
0008,0020	StudyDate	no
0008,0021	SeriesDate	no
0008,0022	AcquisitionDate	no
0008,0023	ContentDate	no
0008,0024	OverlayDate	no
0008,0025	CurveDate	no
0008,002A	AcquisitionDateTime	no
0008,0030	StudyTime	no
0008,0031	SeriesTime	no
0008,0032	AcquisitionTime	no
0008,0033	ContentTime	no
0008,0034	OverlayTime	no

	ExifTool 13.24 Tag Names -	-
0008,0035	CurveTime	no
0008,0040	DataSetType	no
0008,0041	DataSetSubtype	no
0008,0042	NuclearMedicineSeriesType	no
0008,0050	AccessionNumber	no
0008,0052	QueryRetrieveLevel	no
0008,0054	RetrieveAETitle	no
0008,0056 0008,0058	InstanceAvailability FailedSOPInstanceUIDList	no no
0008,0050	Modality	no
0008,0061	ModalitiesInStudy	no
0008,0062	SOPClassesInStudy	no
0008,0064	ConversionType	no
0008,0068	PresentationIntentType	no
0008,0070	Manufacturer	no
0008,0080	InstitutionName	no
0008,0081	InstitutionAddress	no
0008,0082	InstitutionCodeSequence	no
0008,0090	ReferringPhysicianName	no
0008,0092	ReferringPhysicianAddress	no
0008,0094	ReferringPhysicianTelephoneNumber	no
0008,0096 0008,0100	ReferringPhysicianIDSequence CodeValue	no
0008,0100	CodingSchemeDesignator	no
0008,0102	CodingSchemeVersion	no no
0008,0103	CodeMeaning	no
0008,0105	MappingResource	no
0008,0106	ContextGroupVersion	no
0008,0107	ContextGroupLocalVersion	no
0008,010B	ContextGroupExtensionFlag	no
0008,010C	CodingSchemeUID	no
0008,010D	ContextGroupExtensionCreatorUID	no
0008,010F	ContextIdentifier	no
0008,0110	CodingSchemeIDSequence	no
0008,0112	CodingSchemeRegistry	no
0008,0114	CodingSchemeExternalID	no
0008,0115	CodingSchemeName	no
0008,0116	ResponsibleOrganization	no
0008,0117	ContextUID TimezoneOffsetFromUTC	no
0008,0201 0008,1000	NetworkID	no no
0008,1010	StationName	no
0008,1030	StudyDescription	no
0008,1032	ProcedureCodeSequence	no
0008,103E	SeriesDescription	no
0008,1040	InstitutionalDepartmentName	no
0008,1048	PhysiciansOfRecord	no
0008,1049	PhysiciansOfRecordIDSequence	no
0008,1050	PerformingPhysicianName	no
0008,1052	PerformingPhysicianIDSequence	no
0008,1060	NameOfPhysicianReadingStudy	no
0008,1062	PhysicianReadingStudyIDSequence	no
0008,1070	OperatorsName	no
0008,1072	OperatorIDSequence	no
0008,1080 0008,1084	AdmittingDiagnosesDescription AdmittingDiagnosesCodeSequence	no
0008,1084	ManufacturersModelName	no
0008,1000	ReferencedResultsSequence	no no
0008,1110	ReferencedStudySequence	no
0008,1111	ReferencedProcedureStepSequence	no
0008,1115	ReferencedSeriesSequence	no
0008,1120	ReferencedPatientSequence	no
0008,1125	ReferencedVisitSequence	no
0008,1130	ReferencedOverlaySequence	no
0008,113A	ReferencedWaveformSequence	no
0008,1140	ReferencedImageSequence	no
0008,1145	ReferencedCurveSequence	no
0008,114A	ReferencedInstanceSequence	no
0008,1150	ReferencedSOPClassUID	no
0008,1155	ReferencedSOPInstanceUID	no

	ExifTool 13.24 Tag Names	-
0008,115A	SOPClassesSupported	no
0008,1160	ReferencedFrameNumber	no
0008,1161	SimpleFrameList	no
0008,1162	CalculatedFrameList	no
0008,1163	TimeRange	no
0008,1164	FrameExtractionSequence	no
0008,1195	TransactionUID FailureReason	no
0008,1197 0008,1198	FailedSOPSequence	no
0008,1198	ReferencedSOPSequence	no no
0008,1200	OtherReferencedStudiesSequence	no
0008,1250	RelatedSeriesSequence	no
0008,2110	LossyImageCompression	no
0008,2111	DerivationDescription	no
0008,2112	SourceImageSequence	no
0008,2120	StageName	no
0008,2122	StageNumber	no
0008,2124	NumberOfStages	no
0008,2127	ViewName	no
0008,2128	ViewNumber	no
0008,2129	NumberOfEventTimers	no
0008,212A	NumberOfViewsInStage	no
0008,2130 0008,2132	EventElapsedTimes EventTimerNames	no
0008,2132	EventTimerSequence	no no
0008,2133	EventTimeOffset	no
0008,2135	EventCodeSequence	no
0008,2142	StartTrim	no
0008,2143	StopTrim	no
0008,2144	RecommendedDisplayFrameRate	no
0008,2200	TransducerPosition	no
0008,2204	TransducerOrientation	no
0008,2208	AnatomicStructure	no
0008,2218	AnatomicRegionSequence	no
0008,2220	AnatomicRegionModifierSequence	no
0008,2228	PrimaryAnatomicStructureSequence	no
0008,2229	AnatomicStructureOrRegionSequence AnatomicStructureModifierSequence	no
0008,2230	TransducerPositionSequence	no no
0008,2240	TransducerPositionModifierSequence	no
0008,2244	TransducerOrientationSequence	no
0008,2246	TransducerOrientationModifierSeq	no
0008,2253	AnatomicEntrancePortalCodeSeqTrial	no
0008,2255	AnatomicApproachDirCodeSeqTrial	no
0008,2256	AnatomicPerspectiveDescrTrial	no
0008,2257	AnatomicPerspectiveCodeSeqTrial	no
0008,3001	AlternateRepresentationSequence	no
0008,3010	IrradiationEventUID	no
0008,4000	IdentifyingComments	no
0008,9007	FrameType	no
0008,9092	ReferencedImageEvidenceSequence	no
0008,9121 0008,9123	ReferencedRawDataSequence CreatorVersionUID	no
0008,9123	DerivationImageSequence	no no
0008,9121	SourceImageEvidenceSequence	no
0008,9205	PixelPresentation	no
0008,9206	VolumetricProperties	no
0008,9207	VolumeBasedCalculationTechnique	no
0008,9208	ComplexImageComponent	no
0008,9209	AcquisitionContrast	no
0008,9215	DerivationCodeSequence	no
0008,9237	GrayscalePresentationStateSequence	no
0008,9410	ReferencedOtherPlaneSequence	no
0008,9458	FrameDisplaySequence	no
0008,9459	RecommendedDisplayFrameRateInFloat	no
0008,9460 0009,1001	SkipFrameRangeFlag FullFidelity	no no
0009,1001	SuiteID	no no
0009,1002	ProductID	no
0009,1027	ImageActualDate	no

	EXILIOOI 13.24 Tag Names	
0009,1030	ServiceID	no
0009,1031	MobileLocationNumber	no
0009,10E3	EquipmentUID	no
0009,10E6	GenesisVersionNow	no
0009,10E7	ExamRecordChecksum	no
0009,10E9	ActualSeriesDataTimeStamp	no
0010,0000	PatientGroupLength	no
0010,0010	PatientName	no
0010,0020	PatientID	no
0010,0021	IssuerOfPatientID	no
0010,0022	TypeOfPatientID	no
0010,0030	PatientBirthDate	no
0010,0032	PatientBirthTime	no
0010,0040	PatientSex	no
0010,0050	PatientInsurancePlanCodeSequence	no
0010,0101	PatientPrimaryLanguageCodeSeq	no
0010,0102	PatientPrimaryLanguageCodeModSeq	no
0010,1000	OtherPatientIDs	no
0010,1001	OtherPatientNames	no
0010,1002	OtherPatientIDsSequence	no
0010,1005	PatientBirthName	no
0010,1010	PatientAge	no
0010,1010	PatientSize	
0010,1020		no
	PatientWeight	no
0010,1040	PatientAddress	no
0010,1050	InsurancePlanIdentification	no
0010,1060	PatientMotherBirthName	no
0010,1080	MilitaryRank	no
0010,1081	BranchOfService	no
0010,1090	MedicalRecordLocator	no
0010,2000	MedicalAlerts	no
0010,2110	Allergies	no
0010,2150	CountryOfResidence	no
0010,2152	RegionOfResidence	no
0010,2154	PatientTelephoneNumbers	no
0010,2160	EthnicGroup	no
0010,2180	Occupation	no
0010,21A0	SmokingStatus	no
0010,21B0	AdditionalPatientHistory	no
0010,21C0	PregnancyStatus	no
0010,21D0	LastMenstrualDate	no
0010,21F0	PatientReligiousPreference	no
0010,2201	PatientSpeciesDescription	no
0010,2202	PatientSpeciesCodeSequence	no
0010,2203	PatientSexNeutered	no
0010,2210	AnatomicalOrientationType	no
0010,2292	PatientBreedDescription	no
0010,2293	PatientBreedCodeSequence	no
0010,2294	BreedRegistrationSequence	no
0010,2295	BreedRegistrationNumber	no
0010,2296	BreedRegistryCodeSequence	no
0010,2297	ResponsiblePerson	no
0010,2298	ResponsiblePersonRole	no
0010,2299	ResponsibleOrganization	no
0010,4000	PatientComments	no
0010,9431	ExaminedBodyThickness	no
0011,1010	PatientStatus	no
0012,0010	ClinicalTrialSponsorName	
0012,0010	ClinicalTrialProtocolID	no
0012,0020	ClinicalTrialProtocolName	no
0012,0021	ClinicalTrialSiteID	no
	ClinicalTrialSiteName	no
0012,0031 0012,0040		no
	ClinicalTrialSubjectID	no
0012,0042	ClinicalTrialSubjectReadingID	no
0012,0050	ClinicalTrialTimePointID	no
0012,0051	ClinicalTrialTimePointDescription	no
0012,0060	ClinicalTrialCoordinatingCenter	no
0012,0062	PatientIdentityRemoved	no
0012,0063	DeidentificationMethod	no
0012,0064	DeidentificationMethodCodeSequence	no

	ExifTool 13.24 Tag Names -	-
0012,0071	ClinicalTrialSeriesID	no
0012,0072	ClinicalTrialSeriesDescription	no
0012,0084	DistributionType	no
0012,0085 0018,0000	ConsentForDistributionFlag AcquisitionGroupLength	no
0018,0000	ContrastBolusAgent	no no
0018,0012	ContrastBolusAgentSequence	no
0018,0014	ContrastBolusAdministrationRoute	no
0018,0015	BodyPartExamined	no
0018,0020	ScanningSequence	no
0018,0021	SequenceVariant	no
0018,0022	ScanOptions MDA grainitionTyme	no
0018,0023 0018,0024	MRAcquisitionType SequenceName	no no
0018,0021	AngioFlag	no
0018,0026	InterventionDrugInformationSeq	no
0018,0027	InterventionDrugStopTime	no
0018,0028	InterventionDrugDose	no
0018,0029	InterventionDrugSequence	no
0018,002A	AdditionalDrugSequence	no
0018,0030	Radionuclide Radiopharmaceutical	no
0018,0031 0018,0032	EnergyWindowCenterline	no no
0018,0032	EnergyWindowTotalWidth	no
0018,0034	InterventionDrugName	no
0018,0035	InterventionDrugStartTime	no
0018,0036	InterventionSequence	no
0018,0037	TherapyType	no
0018,0038	InterventionStatus	no
0018,0039	TherapyDescription InterventionDescription	no
0018,003A 0018,0040	CineRate	no no
0018,0042	InitialCineRunState	no
0018,0050	SliceThickness	no
0018,0060	KVP	no
0018,0070	CountsAccumulated	no
0018,0071	AcquisitionTerminationCondition	no
0018,0072	EffectiveDuration	no
0018,0073 0018,0074	AcquisitionStartCondition AcquisitionStartConditionData	no
0018,0074	AcquisitionEndConditionData	no no
0018,0080	RepetitionTime	no
0018,0081	EchoTime	no
0018,0082	InversionTime	no
0018,0083	NumberOfAverages	no
0018,0084	ImagingFrequency	no
0018,0085	ImagedNucleus EchoNumber	no
0018,0086 0018,0087	MagneticFieldStrength	no
0018,0087	SpacingBetweenSlices	no no
0018,0089	NumberOfPhaseEncodingSteps	no
0018,0090	DataCollectionDiameter	no
0018,0091	EchoTrainLength	no
0018,0093	PercentSampling	no
0018,0094	PercentPhaseFieldOfView	no
0018,0095	PixelBandwidth	no
0018,1000 0018,1002	DeviceSerialNumber DeviceUID	no no
0018,1002	DeviceID	no
0018,1004	PlateID	no
0018,1005	GeneratorID	no
0018,1006	GridID	no
0018,1007	CassetteID	no
0018,1008	GantryID	no
0018,1010	SecondaryCaptureDeviceID	no
0018,1011 0018,1012	HardcopyCreationDeviceID DateOfSecondaryCapture	no no
0018,1012	TimeOfSecondaryCapture	no
0018,1016	SecondaryCaptureDeviceManufacturer	
0018,1017	HardcopyDeviceManufacturer	no

	EXIITOOI 13.24 Tag Names	
0018,1018	SecondaryCaptureDeviceModelName	no
0018,1019	SecondaryCaptureDeviceSoftwareVers	no
0018,101A	HardcopyDeviceSoftwareVersion	no
0018,101B	HardcopyDeviceModelName	no
0018,1020	SoftwareVersion	no
0018,1022	VideoImageFormatAcquired	no
0018,1023	DigitalImageFormatAcquired	no
0018,1030 0018,1040	ProtocolName ContrastBolusRoute	no
0018,1040	ContrastBolusVolume	no
0018,1041	ContrastBolusStartTime	no no
0018,1012	ContrastBolusStopTime	no
0018,1044	ContrastBolusTotalDose	no
0018,1045	SyringeCounts	no
0018,1046	ContrastFlowRate	no
0018,1047	ContrastFlowDuration	no
0018,1048	ContrastBolusIngredient	no
0018,1049	ContrastBolusConcentration	no
0018,1050	SpatialResolution	no
0018,1060	TriggerTime	no
0018,1061	TriggerSourceOrType	no
0018,1062	NominalInterval	no
0018,1063	FrameTime	no
0018,1064	CardiacFramingType	no
0018,1065	FrameTimeVector	no
0018,1066	FrameDelay	no
0018,1067	ImageTriggerDelay	no
0018,1068	MultiplexGroupTimeOffset	no
0018,1069 0018,106A	TriggerTimeOffset SynchronizationTrigger	no
0018,100A	SynchronizationChannel	no no
0018,106E	TriggerSamplePosition	no
0018,1070	RadiopharmaceuticalRoute	no
0018,1071	RadiopharmaceuticalVolume	no
0018,1072	RadiopharmaceuticalStartTime	no
0018,1073	RadiopharmaceuticalStopTime	no
0018,1074	RadionuclideTotalDose	no
0018,1075	RadionuclideHalfLife	no
0018,1076	RadionuclidePositronFraction	no
0018,1077	RadiopharmaceuticalSpecActivity	no
0018,1078	RadiopharmaceuticalStartDateTime	no
0018,1079	RadiopharmaceuticalStopDateTime	no
0018,1080	BeatRejectionFlag	no
0018,1081	LowRRValue	no
0018,1082	HighRRValue IntervalsAcquired	no
0018,1083 0018,1084	IntervalsRejected	no
0018,1084	PVCRejection	no no
0018,1086	SkipBeats	no
0018,1088	HeartRate	no
0018,1090	CardiacNumberOfImages	no
0018,1094	TriggerWindow	no
0018,1100	ReconstructionDiameter	no
0018,1110	DistanceSourceToDetector	no
0018,1111	DistanceSourceToPatient	no
0018,1114	EstimatedRadiographicMagnification	no
0018,1120	GantryDetectorTilt	no
0018,1121	GantryDetectorSlew	no
0018,1130	TableHeight	no
0018,1131	TableTraverse	no
0018,1134	TableMotion	no
0018,1135	TableVerticalIncrement	no
0018,1136	TableLateralIncrement	no
0018,1137	TableLongitudinalIncrement	no
0018,1138 0018,113A	TableAngle TableType	no
0018,113A	RotationDirection	no no
0018,1141	AngularPosition	no
0018,1141	RadialPosition	no
0018,1143	ScanArc	no
•		

	ExifTool 13.24 Tag Names	
0018,1144	AngularStep	no
0018,1145	CenterOfRotationOffset	no
0018,1146	RotationOffset	no
0018,1147	FieldOfViewShape	no
0018,1149	FieldOfViewDimensions	no
0018,1150	ExposureTime	no
0018,1151	XRayTubeCurrent	no
0018,1152	Exposure	no
0018,1153	ExposureInMicroAmpSec	no
0018,1154	AveragePulseWidth	no
0018,1155	RadiationSetting	no
0018,1156	RectificationType	no
0018,115A 0018,115E	RadiationMode ImageAreaDoseProduct	no
0018,113E	FilterType	no no
0018,1161	TypeOfFilters	no
0018,1162	IntensifierSize	no
0018,1164	ImagerPixelSpacing	no
0018,1166	Grid	no
0018,1170	GeneratorPower	no
0018,1180	CollimatorGridName	no
0018,1181	CollimatorType	no
0018,1182	FocalDistance	no
0018,1183	XFocusCenter	no
0018,1184	YFocusCenter	no
0018,1190	FocalSpots	no
0018,1191	AnodeTargetMaterial	no
0018,11A0	BodyPartThickness	no
0018,11A2	CompressionForce	no
0018,1200	DateOfLastCalibration	no
0018,1201	TimeOfLastCalibration	no
0018,1210	ConvolutionKernel	no
0018,1240	UpperLowerPixelValues	no
0018,1242	ActualFrameDuration	no
0018,1243	CountRate	no
0018,1244	PreferredPlaybackSequencing	no
0018,1250	ReceiveCoilName	no
0018,1251	TransmitCoilName	no
0018,1260	PlateType	no
0018,1261	PhosphorType	no
0018,1300	ScanVelocity	no
0018,1301	WholeBodyTechnique	no
0018,1302	ScanLength	no
0018,1310	AcquisitionMatrix	no
0018,1312	InPlanePhaseEncodingDirection	no
0018,1314	FlipAngle	no
0018,1315 0018,1316	VariableFlipAngleFlag SAR	no
0018,1318	DB-Dt	no
0018,1318	AcquisitionDeviceProcessingDescr	no no
0018,1401	AcquisitionDeviceProcessingCode	no
0018,1402	CassetteOrientation	no
0018,1403	CassetteSize	no
0018,1404	ExposuresOnPlate	no
0018,1405	RelativeXRayExposure	no
0018,1450	ColumnAngulation	no
0018,1460	TomoLayerHeight	no
0018,1470	TomoAngle	no
0018,1480	TomoTime	no
0018,1490	TomoType	no
0018,1491	TomoClass	no
0018,1495	NumberOfTomosynthesisSourceImages	no
0018,1500	PositionerMotion	no
0018,1508	PositionerType	no
0018,1510	PositionerPrimaryAngle	no
0018,1511	PositionerSecondaryAngle	no
0018,1520	PositionerPrimaryAngleIncrement	no
0018,1521	PositionerSecondaryAngleIncrement	no
0018,1530	DetectorPrimaryAngle	no
0018,1531	DetectorSecondaryAngle	no

	EXIITOOI 13.24 Tag Names	-
0018,1600	ShutterShape	no
0018,1602	ShutterLeftVerticalEdge	no
0018,1604	ShutterRightVerticalEdge	no
0018,1606	ShutterUpperHorizontalEdge	no
0018,1608	ShutterLowerHorizontalEdge	no
0018,1610	CenterOfCircularShutter	no
0018,1612	RadiusOfCircularShutter	no
0018,1620 0018,1622	VerticesOfPolygonalShutter ShutterPresentationValue	no
0018,1623	ShutterOverlayGroup	no no
0018,1624	ShutterPresentationColorCIELabVal	no
0018,1700	CollimatorShape	no
0018,1702	CollimatorLeftVerticalEdge	no
0018,1704	CollimatorRightVerticalEdge	no
0018,1706	CollimatorUpperHorizontalEdge	no
0018,1708	CollimatorLowerHorizontalEdge	no
0018,1710	CenterOfCircularCollimator	no
0018,1712	RadiusOfCircularCollimator	no
0018,1720	VerticesOfPolygonalCollimator	no
0018,1800	AcquisitionTimeSynchronized	no
0018,1801	TimeSource	no
0018,1802	TimeDistributionProtocol	no
0018,1803	NTPSourceAddress	no
0018,2001	PageNumberVector	no
0018,2002 0018,2003	FrameLabelVector	no
0018,2003	FramePrimaryAngleVector FrameSecondaryAngleVector	no
0018,2004	SliceLocationVector	no no
0018,2006	DisplayWindowLabelVector	no
0018,2010	NominalScannedPixelSpacing	no
0018,2020	DigitizingDeviceTransportDirection	no
0018,2030	RotationOfScannedFilm	no
0018,3100	IVUSAcquisition	no
0018,3101	IVUSPullbackRate	no
0018,3102	IVUSGatedRate	no
0018,3103	IVUSPullbackStartFrameNumber	no
0018,3104	IVUSPullbackStopFrameNumber	no
0018,3105	LesionNumber	no
0018,4000	AcquisitionComments	no
0018,5000	OutputPower	no
0018,5010	TransducerData	no
0018,5012 0018,5020	FocusDepth ProcessingFunction	no
0018,5020	PostprocessingFunction	no no
0018,5021	MechanicalIndex	no
0018,5024	BoneThermalIndex	no
0018,5026	CranialThermalIndex	no
0018,5027	SoftTissueThermalIndex	no
0018,5028	SoftTissueFocusThermalIndex	no
0018,5029	SoftTissueSurfaceThermalIndex	no
0018,5030	DynamicRange	no
0018,5040	TotalGain	no
0018,5050	DepthOfScanField	no
0018,5100	PatientPosition	no
0018,5101	ViewPosition	no
0018,5104	ProjectionEponymousNameCodeSeq	no
0018,5210	ImageTransformationMatrix	no
0018,5212	ImageTranslationVector	no
0018,6000 0018,6011	Sensitivity SequenceOfUltrasoundRegions	no
0018,6011	RegionSpatialFormat	no
0018,6012	RegionDataType	no no
0018,6014	RegionFlags	no
0018,6018	RegionLocationMinX0	no
0018,601A	RegionLocationMinY0	no
0018,601C	RegionLocationMaxX1	no
0018,601E	RegionLocationMaxY1	no
0018,6020	ReferencePixelX0	no
0018,6022	ReferencePixelY0	no
0018,6024	PhysicalUnitsXDirection	no

	ExilTool 13.24 Tag Names	-
0018,6026	PhysicalUnitsYDirection	no
0018,6028	ReferencePixelPhysicalValueX	no
0018,602A	ReferencePixelPhysicalValueY	no
0018,602C 0018,602E	PhysicalDeltaX PhysicalDeltaY	no no
0018,6030	TransducerFrequency	no
0018,6031	TransducerType	no
0018,6032	PulseRepetitionFrequency	no
0018,6034	DopplerCorrectionAngle	no
0018,6036	SteeringAngle	no
0018,6038	DopplerSampleVolumeXPosRetired	no
0018,6039 0018,603A	DopplerSampleVolumeXPosition DopplerSampleVolumeYPosRetired	no no
0018,603B	DopplerSampleVolumeYPosition	no
0018,603C	TMLinePositionX0Retired	no
0018,603D	TMLinePositionX0	no
0018,603E	TMLinePositionY0Retired	no
0018,603F	TMLinePositionY0	no
0018,6040	TMLinePositionX1Retired	no
0018,6041 0018,6042	TMLinePositionX1 TMLinePositionY1Retired	no
0018,6042	TMLinePositionY1	no no
0018,6044	PixelComponentOrganization	no
0018,6046	PixelComponentMask	no
0018,6048	PixelComponentRangeStart	no
0018,604A	PixelComponentRangeStop	no
0018,604C	PixelComponentPhysicalUnits	no
0018,604E	PixelComponentDataType	no
0018,6050 0018,6052	NumberOfTableBreakPoints TableOfXBreakPoints	no
0018,6052	TableOfyBreakPoints	no no
0018,6056	NumberOfTableEntries	no
0018,6058	TableOfPixelValues	no
0018,605A	TableOfParameterValues	no
0018,6060	RWaveTimeVector	no
0018,7000	DetectorConditionsNominalFlag	no
0018,7001 0018,7004	DetectorTemperature DetectorType	no
0018,7004	DetectorType DetectorConfiguration	no no
0018,7006	DetectorDescription	no
0018,7008	DetectorMode	no
0018,700A	DetectorID	no
0018,700C	DateOfLastDetectorCalibration	no
0018,700E	TimeOfLastDetectorCalibration	no
0018,7010	DetectorExposuresSinceCalibration	no
0018,7011 0018,7012	DetectorExposuresSinceManufactured DetectorTimeSinceLastExposure	no no
0018,7014	DetectorActiveTime	no
0018,7016	DetectorActiveOffsetFromExposure	no
0018,701A	DetectorBinning	no
0018,7020	DetectorElementPhysicalSize	no
0018,7022	DetectorElementSpacing	no
0018,7024	DetectorActiveShape	no
0018,7026 0018,7028	DetectorActiveDimensions DetectorActiveOrigin	no
0018,7028 0018,702A	DetectorManufacturerName	no no
0018,702B	DetectorManufacturersModelName	no
0018,7030	FieldOfViewOrigin	no
0018,7032	FieldOfViewRotation	no
0018,7034	FieldOfViewHorizontalFlip	no
0018,7040	GridSpagingMaterial	no
0018,7041 0018,7042	GridSpacingMaterial GridThickness	no
0018,7042	GridPitch	no no
0018,7044	GridAspectRatio	no
0018,7048	GridPeriod	no
0018,704C	GridFocalDistance	no
0018,7050	FilterMaterial	no
0018,7052	FilterThicknessMinimum	no
0018,7054	FilterThicknessMaximum	no

	ExilTool 13.24 Tag Names	-
0018,7060	ExposureControlMode	no
0018,7062	ExposureControlModeDescription	no
0018,7064	ExposureStatus	no
0018,7065	PhototimerSetting	no
0018,8150	ExposureTimeInMicroSec	no
0018,8151	XRayTubeCurrentInMicroAmps	no
0018,9004	ContentQualification	no
0018,9005 0018,9006	PulseSequenceName MRImagingModifierSequence	no
0018,9008	EchoPulseSequence	no no
0018,9009	InversionRecovery	no
0018,9010	FlowCompensation	no
0018,9011	MultipleSpinEcho	no
0018,9012	MultiPlanarExcitation	no
0018,9014	PhaseContrast	no
0018,9015	TimeOfFlightContrast	no
0018,9016	Spoiling	no
0018,9017	SteadyStatePulseSequence	no
0018,9018	EchoPlanarPulseSequence	no
0018,9019	TagAngleFirstAxis	no
0018,9020	MagnetizationTransfer	no
0018,9021	T2Preparation	no
0018,9022	BloodSignalNulling	no
0018,9024	SaturationRecovery	no
0018,9025	SpectrallySelectedSuppression	no
0018,9026	SpectrallySelectedExcitation	no
0018,9027	SpatialPresaturation	no
0018,9028	Tagging	no
0018,9029	OversamplingPhase	no
0018,9030	TagSpacingFirstDimension	no
0018,9032	GeometryOfKSpaceTraversal	no
0018,9033	SegmentedKSpaceTraversal	no
0018,9034 0018,9035	RectilinearPhaseEncodeReordering TagThickness	no
0018,9036	PartialFourierDirection	no no
0018,9037	CardiacSynchronizationTechnique	no
0018,9041	ReceiveCoilManufacturerName	no
0018,9042	MRReceiveCoilSequence	no
0018,9043	ReceiveCoilType	no
0018,9044	QuadratureReceiveCoil	no
0018,9045	MultiCoilDefinitionSequence	no
0018,9046	MultiCoilConfiguration	no
0018,9047	MultiCoilElementName	no
0018,9048	MultiCoilElementUsed	no
0018,9049	MRTransmitCoilSequence	no
0018,9050	TransmitCoilManufacturerName	no
0018,9051	TransmitCoilType	no
0018,9052	SpectralWidth	no
0018,9053	ChemicalShiftReference	no
0018,9054	VolumeLocalizationTechnique	no
0018,9058	MRAcquisitionFrequencyEncodeSteps	no
0018,9059	Decoupling	no
0018,9060	DecoupledNucleus	no
0018,9061	DecouplingFrequency	no
0018,9062	DecouplingMethod	no
0018,9063	DecouplingChemicalShiftReference	no
0018,9064	KSpaceFiltering	no
0018,9065	TimeDomainFiltering	no
0018,9066 0018,9067	NumberOfZeroFills BaselineCorrection	no
0018,9069	ParallelReductionFactorInPlane	no no
0018,9070	CardiacRRIntervalSpecified	no
0018,9073	AcquisitionDuration	no
0018,9074	FrameAcquisitionDateTime	no
0018,9075	DiffusionDirectionality	no
0018,9076	DiffusionGradientDirectionSequence	no
0018,9077	ParallelAcquisition	no
0018,9078	ParallelAcquisitionTechnique	no
0018,9079	InversionTimes	no
0018,9080	MetaboliteMapDescription	no

	milliool 13.21 lag names	
0018,9081	PartialFourier	no
0018,9082	EffectiveEchoTime	no
0018,9083	MetaboliteMapCodeSequence	no
0018,9084	ChemicalShiftSequence	no
0018,9085	CardiacSignalSource	
		no
0018,9087	DiffusionBValue	no
0018,9089	DiffusionGradientOrientation	no
0018,9090	VelocityEncodingDirection	no
0018,9091	VelocityEncodingMinimumValue	no
0018,9093	NumberOfKSpaceTrajectories	no
0018,9094	CoverageOfKSpace	no
0018,9095	SpectroscopyAcquisitionPhaseRows	no
0018,9096	ParallelReductFactorInPlaneRetired	no
0018,9098		
	TransmitterFrequency	no
0018,9100	ResonantNucleus	no
0018,9101	FrequencyCorrection	no
0018,9103	MRSpectroscopyFOV-GeometrySequence	no
0018,9104	SlabThickness	no
0018,9105	SlabOrientation	no
0018,9106	MidSlabPosition	no
0018,9107	MRSpatialSaturationSequence	no
0018,9112	MRTimingAndRelatedParametersSeq	no
0018,9112	MREchoSequence	
	<del>-</del>	no
0018,9115	MRModifierSequence	no
0018,9117	MRDiffusionSequence	no
0018,9118	CardiacTriggerSequence	no
0018,9119	MRAveragesSequence	no
0018,9125	MRFOV-GeometrySequence	no
0018,9126	VolumeLocalizationSequence	no
0018,9127	SpectroscopyAcquisitionDataColumns	no
0018,9147	DiffusionAnisotropyType	no
0018,9151	FrameReferenceDateTime	no
0018,9151	MRMetaboliteMapSequence	no
0018,9155	ParallelReductionFactorOutOfPlane	
0018,9159		no
	SpectroscopyOutOfPlanePhaseSteps	no
0018,9166	BulkMotionStatus	no
0018,9168	ParallelReductionFactSecondInPlane	no
0018,9169	CardiacBeatRejectionTechnique	no
0018,9170	RespiratoryMotionCompTechnique	no
0018,9171	RespiratorySignalSource	no
0018,9172	BulkMotionCompensationTechnique	no
0018,9173	BulkMotionSignalSource	no
0018,9174	ApplicableSafetyStandardAgency	no
0018,9175	ApplicableSafetyStandardDescr	no
0018,9176	OperatingModeSequence	no
0018,9177	OperatingModeType	no
0018,9178	OperatingMode	no
0018,9179	SpecificAbsorptionRateDefinition	
		no
0018,9180	GradientOutputType	no
0018,9181	SpecificAbsorptionRateValue	no
0018,9182	GradientOutput	no
0018,9183	FlowCompensationDirection	no
0018,9184	TaggingDelay	no
0018,9185	RespiratoryMotionCompTechDescr	no
0018,9186	RespiratorySignalSourceID	no
0018,9195	Chemical Shifts Min Integrate Limit Hz	no
0018,9196	ChemicalShiftsMaxIntegrateLimitHz	no
0018,9197	MRVelocityEncodingSequence	no
0018,9198	FirstOrderPhaseCorrection	no
0018,9199	WaterReferencedPhaseCorrection	
0018,9200		no
	MRSpectroscopyAcquisitionType	no
0018,9214	RespiratoryCyclePosition	no
0018,9217	VelocityEncodingMaximumValue	no
0018,9218	TagSpacingSecondDimension	no
0018,9219	TagAngleSecondAxis	no
0018,9220	FrameAcquisitionDuration	no
0018,9226	MRImageFrameTypeSequence	no
0018,9227	${\tt MRSpectroscopyFrameTypeSequence}$	no
0018,9231	${\tt MRAcqPhaseEncodingStepsInPlane}$	no
0018,9232	MRAcqPhaseEncodingStepsOutOfPlane	no

	ExilTool 13.24 Tag Names	•
0018,9234	SpectroscopyAcqPhaseColumns	no
0018,9236	CardiacCyclePosition	no
0018,9239	SpecificAbsorptionRateSequence	no
0018,9240	RFEchoTrainLength	no
0018,9241	GradientEchoTrainLength	no
0018,9295	ChemicalShiftsMinIntegrateLimitPPM	no
0018,9296	ChemicalShiftsMaxIntegrateLimitPPM	no
0018,9301 0018,9302	CTAcquisitionTypeSequence AcquisitionType	no
0018,9302	TubeAngle	no no
0018,9304	CTAcquisitionDetailsSequence	no
0018,9305	RevolutionTime	no
0018,9306	SingleCollimationWidth	no
0018,9307	TotalCollimationWidth	no
0018,9308	CTTableDynamicsSequence	no
0018,9309	TableSpeed	no
0018,9310	TableFeedPerRotation	no
0018,9311	SpiralPitchFactor	no
0018,9312	CTGeometrySequence	no
0018,9313	DataCollectionCenterPatient	no
0018,9314	CTReconstructionSequence	no
0018,9315	ReconstructionAlgorithm	no
0018,9316	ConvolutionKernelGroup	no
0018,9317	ReconstructionFieldOfView	no
0018,9318	ReconstructionTargetCenterPatient	no
0018,9319	ReconstructionAngle	no
0018,9320 0018,9321	ImageFilter CTFypogureSeguenge	no
0018,9321	CTExposureSequence ReconstructionPixelSpacing	no no
0018,9322	ExposureModulationType	no
0018,9324	EstimatedDoseSaving	no
0018,9325	CTXRayDetailsSequence	no
0018,9326	CTPositionSequence	no
0018,9327	TablePosition	no
0018,9328	ExposureTimeInMilliSec	no
0018,9329	CTImageFrameTypeSequence	no
0018,9330	XRayTubeCurrentInMilliAmps	no
0018,9332	ExposureInMilliAmpSec	no
0018,9333	ConstantVolumeFlag	no
0018,9334	FluoroscopyFlag	no
0018,9335	SourceToDataCollectionCenterDist	no
0018,9337	ContrastBolusAgentNumber	no
0018,9338 0018,9340	ContrastBolusIngredientCodeSeq ContrastAdministrationProfileSeq	no
0018,9340	ContrastBolusUsageSequence	no
0018,9341	ContrastBolusAgentAdministered	no no
0018,9343	ContrastBolusAgentDetected	no
0018,9344	ContrastBolusAgentPhase	no
0018,9345	CTDIvol	no
0018,9346	CTDIPhantomTypeCodeSequence	no
0018,9351	CalciumScoringMassFactorPatient	no
0018,9352	CalciumScoringMassFactorDevice	no
0018,9353	EnergyWeightingFactor	no
0018,9360	CTAdditionalXRaySourceSequence	no
0018,9401	ProjectionPixelCalibrationSequence	no
0018,9402	DistanceSourceToIsocenter	no
0018,9403	DistanceObjectToTableTop	no
0018,9404	ObjectPixelSpacingInCenterOfBeam	no
0018,9405	PositionerPositionSequence	no
0018,9406	TablePositionSequence	no
0018,9407	CollimatorShapeSequence	no
0018,9412	XA-XRFFrameCharacteristicsSequence	no
0018,9417 0018,9420	FrameAcquisitionSequence XRayReceptorType	no
0018,9420	AcquisitionProtocolName	no no
0018,9423	AcquisitionProtocolDescription	no
0018,9425	ContrastBolusIngredientOpaque	no
0018,9426	DistanceReceptorPlaneToDetHousing	no
0018,9427	IntensifierActiveShape	no
0018,9428	IntensifierActiveDimensions	no

0018,9429	PhysicalDetectorSize	no
0018,9430	PositionOfIsocenterProjection	no
0018,9432	FieldOfViewSequence	no
0018,9433	FieldOfViewDescription	no
0018,9434	ExposureControlSensingRegionsSeq	no
0018,9435	ExposureControlSensingRegionShape	no
0018,9436	ExposureControlSensRegionLeftEdge	no
0018,9437	ExposureControlSensRegionRightEdge	no
0018,9440	CenterOfCircExposControlSensRegion	no
0018,9441	RadiusOfCircExposControlSensRegion	no
0018,9447	ColumnAngulationPatient	no
0018,9449	BeamAngle	no
0018,9451	FrameDetectorParametersSequence	no
0018,9452	CalculatedAnatomyThickness	no
0018,9455	CalibrationSequence	no
0018,9456	ObjectThicknessSequence	no
0018,9457	PlaneIdentification	no
0018,9461	FieldOfViewDimensionsInFloat	no
0018,9462	IsocenterReferenceSystemSequence	no
0018,9463	PositionerIsocenterPrimaryAngle	
		no
0018,9464	PositionerIsocenterSecondaryAngle	no
0018,9465	PositionerIsocenterDetRotAngle	no
0018,9466	TableXPositionToIsocenter	no
0018,9467	TableYPositionToIsocenter	no
0018,9468	TableZPositionToIsocenter	no
0018,9469	TableHorizontalRotationAngle	no
0018,9470	TableHeadTiltAngle	no
0018,9471	TableCradleTiltAngle	no
0018,9472	FrameDisplayShutterSequence	no
0018,9473	AcquiredImageAreaDoseProduct	
		no
0018,9474	CArmPositionerTabletopRelationship	no
0018,9476	XRayGeometrySequence	no
0018,9477	IrradiationEventIDSequence	no
0018,9504	XRay3DFrameTypeSequence	no
0018,9506	ContributingSourcesSequence	no
0018,9507	XRay3DAcquisitionSequence	no
0018,9508	PrimaryPositionerScanArc	no
0018,9509	SecondaryPositionerScanArc	no
0018,9510	PrimaryPositionerScanStartAngle	no
0018,9511	SecondaryPositionerScanStartAngle	no
0018,9514	PrimaryPositionerIncrement	no
0018,9511		
	SecondaryPositionerIncrement	no
0018,9516	StartAcquisitionDateTime	no
0018,9517	EndAcquisitionDateTime	no
0018,9524	ApplicationName	no
0018,9525	ApplicationVersion	no
0018,9526	ApplicationManufacturer	no
0018,9527	AlgorithmType	no
0018,9528	AlgorithmDescription	no
0018,9530	XRay3DReconstructionSequence	no
0018,9531	ReconstructionDescription	no
0018,9538	PerProjectionAcquisitionSequence	no
0018,9601		
	DiffusionBMatrixSequence	no
0018,9602	DiffusionBValueXX	no
0018,9603	DiffusionBValueXY	no
0018,9604	DiffusionBValueXZ	no
0018,9605	DiffusionBValueYY	no
0018,9606	DiffusionBValueYZ	no
0018,9607	DiffusionBValueZZ	no
0018,9701	DecayCorrectionDateTime	no
0018,9715	StartDensityThreshold	no
	TerminationTimeThreshold	
0018,9722		no
0018,9725	DetectorGeometry	no
0018,9727	AxialDetectorDimension	no
0018,9735	PETPositionSequence	no
0018,9739	NumberOfIterations	no
0018,9740	NumberOfSubsets	no
0018,9751	PETFrameTypeSequence	no
0018,9756	ReconstructionType	no
0018,9758	DecayCorrected	no
3 , 2 , 3 0		

	Exillool 13.24 Tag Names	
0018,9759	AttenuationCorrected	no
0018,9760	ScatterCorrected	no
0018,9761	DeadTimeCorrected	no
0018,9762	GantryMotionCorrected	no
0018,9763	PatientMotionCorrected	no
0018,9765	RandomsCorrected	no
0018,9767	SensitivityCalibrated	no
0018,9801 0018,9804	DepthsOfFocus ExclusionStartDatetime	no
0018,9804	ExclusionDuration	no
0018,9807	ImageDataTypeSequence	no no
0018,9808	DataType	no
0018,980B	AliasedDataType	no
0018,A001	Contributing Equipment Sequence	no
0018,A002	ContributionDateTime	no
0018,A003	ContributionDescription	no
0019,1002	NumberOfCellsIInDetector	no
0019,1003	CellNumberAtTheta	no
0019,1004	CellSpacing	no
0019,100F	HorizFrameOfRef	no
0019,1011	SeriesContrast	no
0019,1012	LastPseq	no
0019,1013	StartNumberForBaseline	no
0019,1014	EndNumberForBaseline	no
0019,1015	StartNumberForEnhancedScans	no
0019,1016	EndNumberForEnhancedScans	no
0019,1017	SeriesPlane	no
0019,1018	FirstScanRas	no
0019,1019	FirstScanLocation	no
0019,101A	LastScanRas	no
0019,101B	LastScanLoc	no
0019,101E	DisplayFieldOfView	no
0019,1023	TableSpeed	no
0019,1024	MidScanTime	no
0019,1025 0019,1026	MidScanFlag	no
0019,1026	DegreesOfAzimuth GantryPeriod	no
0019,1027 0019,102A	XRayOnPosition	no no
0019,102A	XRayOffPosition	no
0019,102B	NumberOfTriggers	no
0019,102E	AngleOfFirstView	no
0019,102F	TriggerFrequency	no
0019,1039	ScanFOVType	no
0019,1040	StatReconFlag	no
0019,1041	ComputeType	no
0019,1042	SegmentNumber	no
0019,1043	TotalSegmentsRequested	no
0019,1044	InterscanDelay	no
0019,1047	ViewCompressionFactor	no
0019,104A	TotalNoOfRefChannels	no
0019,104B	DataSizeForScanData	no
0019,1052	ReconPostProcflag	no
0019,1057	CTWaterNumber	no
0019,1058	CTBoneNumber	no
0019,105A	AcquisitionDuration	no
0019,105E	NumberOfChannels	no
0019,105F	IncrementBetweenChannels	no
0019,1060	StartingView NumberOfViews	no
0019,1061 0019,1062	IncrementBetweenViews	no
0019,1002 0019,106A	DependantOnNoViewsProcessed	no no
0019,100A	FieldOfViewInDetectorCells	no
0019,100B	ValueOfBackProjectionButton	no
0019,1070	SetIfFatqEstimatesWereUsed	no
0019,1072	ZChanAvgOverViews	no
0019,1073	AvgOfLeftRefChansOverViews	no
0019,1074	MaxLeftChanOverViews	no
0019,1075	AvgOfRightRefChansOverViews	no
0019,1076	MaxRightChanOverViews	no
0019,107D	SecondEcho	no

	ExifTool 13.24 Tag Names	
0019,107E	NumberOfEchoes	no
0019,107F	TableDelta	no
0019,1081	Contiguous	no
0019,1084	PeakSAR	no
0019,1085	MonitorSAR	no
0019,1087	CardiacRepetitionTime	no
0019,1088	ImagesPerCardiacCycle	no
0019,108A 0019,108B	ActualReceiveGainAnalog ActualReceiveGainDigital	no
0019,100B	DelayAfterTrigger	no no
0019,100B	Swappf	no
0019,1090	PauseInterval	no
0019,1091	PulseTime	no
0019,1092	SliceOffsetOnFreqAxis	no
0019,1093	CenterFrequency	no
0019,1094	TransmitGain	no
0019,1095	AnalogReceiverGain	no
0019,1096	DigitalReceiverGain	no
0019,1097	BitmapDefiningCVs	no
0019,1098	CenterFreqMethod	no
0019,109B	PulseSeqMode	no
0019,109C	PulseSeqName	no
0019,109D	PulseSeqDate InternalPulseSeqName	no
0019,109E 0019,109F	TransmittingCoil	no no
0019,103F	SurfaceCoilType	no
0019,10A1	ExtremityCoilFlag	no
0019,10A2	RawDataRunNumber	no
0019,10A3	CalibratedFieldStrength	no
0019,10A4	SATFatWaterBone	no
0019,10A5	ReceiveBandwidth	no
0019,10A7	UserData01	no
0019,10A8	UserData02	no
0019,10A9	UserData03	no
0019,10AA	UserData04	no
0019,10AB	UserData05	no
0019,10AC	UserData06	no
0019,10AD 0019,10AE	UserData07	no
0019,10AE 0019,10AF	UserData08 UserData09	no no
0019,10AF	UserData10	no
0019,10B1	UserData11	no
0019,10B2	UserData12	no
0019,10B3	UserData13	no
0019,10B4	UserData14	no
0019,10B5	UserData15	no
0019,10B6	UserData16	no
0019,10B7	UserData17	no
0019,10B8	UserData18	no
0019,10B9	UserData19	no
0019,10BA	UserData20	no
0019,10BB	UserData21	no
0019,10BC	UserData22	no
0019,10BD 0019,10BE	UserData23 ProjectionAngle	no
0019,10BE	SaturationPlanes	no
0019,10C0 0019,10C1	SurfaceCoilIntensity	no no
0019,10C2	SATLocationR	no
0019,10C3	SATLocationL	no
0019,10C4	SATLocationA	no
0019,10C5	SATLocationP	no
0019,10C6	SATLocationH	no
0019,10C7	SATLocationF	no
0019,10C8	SATThicknessR-L	no
0019,1009	SATThicknessA-P	no
0019,10CA	SATThicknessH-F	no
0019,10CB	PrescribedFlowAxis	no
0019,10CC	VelocityEncoding	no
0019,10CD	ThicknessDisclaimer	no
0019,10CE	PrescanType	no

	EXIIIOOI 13.24 lag Names	
0019,10CF	PrescanStatus	no
0019,10D0	RawDataType	no
0019,10D2	ProjectionAlgorithm	no
0019,10D3	ProjectionAlgorithm	no
0019,10D5	FractionalEcho	no
0019,10D6	PrepPulse	no
0019,10D7	CardiacPhases	no
0019,10D8	VariableEchoflag	no
0019,10D9	ConcatenatedSAT	no
0019,10DA	ReferenceChannelUsed	no
0019,10DB	BackProjectorCoefficient	no
0019,10DC	PrimarySpeedCorrectionUsed	no
0019,10DD	OverrangeCorrectionUsed	no
0019,10DE	DynamicZAlphaValue	no
0019,10DF	UserData	no
0019,10E0	UserData	no
0019,10E2	VelocityEncodeScale	no
0019,10F2	FastPhases	no
0019,10F9	TransmissionGain	no
0020,0000	RelationshipGroupLength	no
0020,000D	StudyInstanceUID	no
0020,000E	SeriesInstanceUID	no
0020,0010	StudyID	no
0020,0011	SeriesNumber	no
0020,0012	AcquisitionNumber	no
0020,0013	InstanceNumber	no
0020,0014	IsotopeNumber	no
0020,0015	PhaseNumber	no
0020,0016	IntervalNumber	no
0020,0017	TimeSlotNumber	no
0020,0018	AngleNumber	no
0020,0019	ItemNumber	no
0020,0020	PatientOrientation	no
0020,0022	OverlayNumber	no
0020,0024	CurveNumber	no
0020,0026	LookupTableNumber	no
0020,0030	ImagePosition	no
0020,0032	ImagePositionPatient	no
0020,0035	ImageOrientation	no
0020,0037	ImageOrientationPatient	no
0020,0050	Location	no
0020,0052	FrameOfReferenceUID	no
0020,0060	Laterality	no
0020,0062	ImageLaterality	no
0020,0070	ImageGeometryType	no
0020,0080	MaskingImage	no
0020,0100	TemporalPositionIdentifier	no
0020,0105	NumberOfTemporalPositions	no
0020,0110	TemporalResolution	no
0020,0200	SynchronizationFrameOfReferenceUID	no
0020,1000	SeriesInStudy	no
0020,1001	AcquisitionsInSeries	no
0020,1002	ImagesInAcquisition	no
0020,1003	ImagesInSeries	no
0020,1004	AcquisitionsInStudy	no
0020,1005	ImagesInStudy	no
0020,1020	Reference	no
0020,1040	PositionReferenceIndicator	no
0020,1041	SliceLocation	no
0020,1070	OtherStudyNumbers	no
0020,1200	NumberOfPatientRelatedStudies	no
0020,1202	NumberOfPatientRelatedSeries	no
0020,1204	NumberOfPatientRelatedInstances	no
0020,1206	NumberOfStudyRelatedSeries	no
0020,1208	NumberOfStudyRelatedInstances	no
0020,1209	NumberOfSeriesRelatedInstances	no
0020,31xx	SourceImageIDs	no
0020,3401	ModifyingDeviceID	no
0020,3402	ModifiedImageID	no
0020,3403	ModifiedImageDate	no

0020,3404	ModifyingDeviceManufacturer	no
0020,3405	ModifiedImageTime	no
0020,3406	ModifiedImageDescription	no
0020,4000	ImageComments	no
0020,5000	OriginalImageIdentification	no
0020,5002	OriginalImageIdentNomenclature	no
0020,9056	StackID	no
0020,9057 0020,9071	InStackPositionNumber	no
0020,9071	FrameAnatomySequence FrameLaterality	no
0020,9072	FrameContentSequence	no no
0020,9111	PlanePositionSequence	no
0020,9116	PlaneOrientationSequence	no
0020,9110	TemporalPositionIndex	no
0020,9153	TriggerDelayTime	no
0020,9156	FrameAcquisitionNumber	no
0020,9157	DimensionIndexValues	no
0020,9158	FrameComments	no
0020,9161	ConcatenationUID	no
0020,9162	InConcatenationNumber	no
0020,9163	InConcatenationTotalNumber	no
0020,9164	DimensionOrganizationUID	no
0020,9165	DimensionIndexPointer	no
0020,9167	FunctionalGroupPointer	no
0020,9213	DimensionIndexPrivateCreator	no
0020,9221	DimensionOrganizationSequence	no
0020,9222	DimensionIndexSequence	no
0020,9228	ConcatenationFrameOffsetNumber	no
0020,9238	FunctionalGroupPrivateCreator	no
0020,9241	NominalPercentageOfCardiacPhase	no
0020,9245	NominalPercentOfRespiratoryPhase	no
0020,9246	StartingRespiratoryAmplitude	no
0020,9247	StartingRespiratoryPhase	no
0020,9248	EndingRespiratoryAmplitude	no
0020,9249	EndingRespiratoryPhase	no
0020,9250	RespiratoryTriggerType	no
0020,9251	RRIntervalTimeNominal	no
0020,9252	ActualCardiacTriggerDelayTime	no
0020,9253	${\tt RespiratorySynchronizationSequence}$	no
0020,9254	RespiratoryIntervalTime	no
0020,9255	NominalRespiratoryTriggerDelayTime	no
0020,9256	RespiratoryTriggerDelayThreshold	no
0020,9257	ActualRespiratoryTriggerDelayTime	no
0020,9301	ImagePositionVolume	no
0020,9302	ImageOrientationVolume	no
0020,9308	ApexPosition	no
0020,9421	DimensionDescriptionLabel	no
0020,9450	PatientOrientationInFrameSequence	no
0020,9453	FrameLabel	no
0020,9518	AcquisitionIndex	no
0020,9529	ContributingSOPInstancesRefSeq	no
0020,9536	ReconstructionIndex SeriesFromWhichPrescribed	no
0021,1003	GenesisVersionNow	no
0021,1005	SeriesRecordChecksum	no
0021,1007 0021,1018	GenesisVersionNow	no
0021,1018	AcqreconRecordChecksum	no
0021,1019	TableStartLocation	no no
0021,1020	SeriesFromWhichPrescribed	
0021,1035	ImageFromWhichPrescribed	no
0021,1030	ScreenFormat	no no
0021,1037 0021,104A	AnatomicalReferenceForScout	no
0021,104A 0021,104F	LocationsInAcquisition	no
0021,1041	GraphicallyPrescribed	no
0021,1050	RotationFromSourceXRot	no
0021,1051	RotationFromSourceYRot	no
0021,1052	RotationFromSourceZRot	no
0021,1054	ImagePosition	no
0021,1055	ImageOrientation	no
0021,1056	IntegerSlop	no
· ·		

	Exillool 13.24 Tag Names -	-
0021,1057	IntegerSlop	no
0021,1058	IntegerSlop	no
0021,1059	IntegerSlop	no
0021,105A	IntegerSlop	no
0021,105B	FloatSlop	no
0021,105C	FloatSlop	no
0021,105D	FloatSlop	no
0021,105E	FloatSlop	no
0021,105F	FloatSlop	no
0021,1081 0021,1082	AutoWindowLevelAlpha AutoWindowLevelBeta	no
0021,1082	AutoWindowLevelWindow	no
0021,1083	ToWindowLevelLevel	no
0021,1004	TubeFocalSpotPosition	no no
0021,1091	BiopsyPosition	no
0021,1092	BiopsyTLocation	no
0021,1093	BiopsyRefLocation	no
0022,0001	LightPathFilterPassThroughWavelen	no
0022,0002	LightPathFilterPassBand	no
0022,0003	ImagePathFilterPassThroughWavelen	no
0022,0004	ImagePathFilterPassBand	no
0022,0005	PatientEyeMovementCommanded	no
0022,0006	PatientEyeMovementCommandCodeSeq	no
0022,0007	SphericalLensPower	no
0022,0008	CylinderLensPower	no
0022,0009	CylinderAxis	no
0022,000A	EmmetropicMagnification	no
0022,000B	IntraOcularPressure	no
0022,000C	HorizontalFieldOfView	no
0022,000D	PupilDilated	no
0022,000E	DegreeOfDilation	no
0022,0010	StereoBaselineAngle	no
0022,0011	StereoBaselineDisplacement	no
0022,0012	StereoHorizontalPixelOffset	no
0022,0013	StereoVerticalPixelOffset	no
0022,0014	StereoRotation	no
0022,0015	AcquisitionDeviceTypeCodeSequence	no
0022,0016	IlluminationTypeCodeSequence	no
0022,0017	LightPathFilterTypeStackCodeSeq	no
0022,0018	ImagePathFilterTypeStackCodeSeq	no
0022,0019	LensesCodeSequence	no
0022,001A	ChannelDescriptionCodeSequence	no
0022,001B	RefractiveStateSequence	no
0022,001C 0022,001D	MydriaticAgentCodeSequence	no
0022,0010	RelativeImagePositionCodeSequence StereoPairsSequence	no
0022,0020	LeftImageSequence	no no
0022,0021	RightImageSequence	no
0022,0022	AxialLengthOfTheEye	no
0022,0031	OphthalmicFrameLocationSequence	no
0022,0032	ReferenceCoordinates	no
0022,0035	DepthSpatialResolution	no
0022,0036	MaximumDepthDistortion	no
0022,0037	AlongScanSpatialResolution	no
0022,0038	MaximumAlongScanDistortion	no
0022,0039	OphthalmicImageOrientation	no
0022,0041	DepthOfTransverseImage	no
0022,0042	MydriaticAgentConcUnitsSeq	no
0022,0048	AcrossScanSpatialResolution	no
0022,0049	MaximumAcrossScanDistortion	no
0022,004E	MydriaticAgentConcentration	no
0022,0055	IlluminationWaveLength	no
0022,0056	IlluminationPower	no
0022,0057	IlluminationBandwidth	no
0022,0058	MydriaticAgentSequence	no
0023,1001	NumberOfSeriesInStudy	no
0023,1002	NumberOfUnarchivedSeries	no
0023,1010	ReferenceImageField	no
0023,1050	SummaryImage	no
0023,1070	StartTimeSecsInFirstAxial	no

	ExifTool 13.24 Tag Names	-
0023,1074	NoofUpdatesToHeader	no
0023,107D	IndicatesIfTheStudyHasCompleteInfo	no
0025,1006	LastPulseSequenceUsed	no
0025,1007 0025,1010	<pre>ImagesInSeries LandmarkCounter</pre>	no
0025,1010	NumberOfAcquisitions	no no
0025,1014	IndicatesNoofUpdatesToHeader	no
0025,1017	SeriesCompleteFlag	no
0025,1018	NumberOfImagesArchived	no
0025,1019	LastImageNumberUsed	no
0025,101A	PrimaryReceiverSuiteAndHost	no
0027,1006	ImageArchiveFlag	no
0027,1010 0027,101C	ScoutType VmaMamp	no no
0027,101C	VmaPhase	no
0027,101E	VmaMod	no
0027,101F	VmaClip	no
0027,1020	SmartScanOnOffFlag	no
0027,1030	ForeignImageRevision	no
0027,1031	ImagingMode	no
0027,1032	PulseSequence	no
0027,1033 0027,1035	ImagingOptions PlaneType	no
0027,1035	ObliquePlane	no no
0027,1030	RASLetterOfImageLocation	no
0027,1041	ImageLocation	no
0027,1042	CenterRCoordOfPlaneImage	no
0027,1043	CenterACoordOfPlaneImage	no
0027,1044	CenterSCoordOfPlaneImage	no
0027,1045	NormalRCoord	no
0027,1046 0027,1047	NormalACoord NormalSCoord	no
0027,1047	RCoordOfTopRightCorner	no no
0027,1010	ACoordOfTopRightCorner	no
0027,104A	SCoordOfTopRightCorner	no
0027,104B	RCoordOfBottomRightCorner	no
0027,104C	ACoordOfBottomRightCorner	no
0027,104D	SCoordOfBottomRightCorner	no
0027,1050	TableStartLocation	no
0027,1051 0027,1052	TableEndLocation RASLetterForSideOfImage	no
0027,1052	RASLetterForAnteriorPosterior	no no
0027,1053	RASLetterForScoutStartLoc	no
0027,1055	RASLetterForScoutEndLoc	no
0027,1060	ImageDimensionX	no
0027,1061	ImageDimensionY	no
0027,1062	NumberOfExcitations	no
0028,0000	ImagePresentationGroupLength	no
0028,0002 0028,0003	SamplesPerPixel SamplesPerPixelUsed	no
0028,0003	PhotometricInterpretation	no no
0028,0005	ImageDimensions	no
0028,0006	PlanarConfiguration	no
0028,0008	NumberOfFrames	no
0028,0009	FrameIncrementPointer	no
0028,000A	FrameDimensionPointer	no
0028,0010	Rows	no
0028,0011	Columns	no
0028,0012 0028,0014	Planes UltrasoundColorDataPresent	no no
0028,0030	PixelSpacing	no
0028,0031	ZoomFactor	no
0028,0032	ZoomCenter	no
0028,0034	PixelAspectRatio	no
0028,0040	ImageFormat	no
0028,0050	ManipulatedImage	no
0028,0051	CorrectedImage	no
0028,005F 0028,0060	CompressionRecognitionCode CompressionCode	no
0028,0060	CompressionOriginator	no no
2020,0001		-10

0028,0062	CompressionLabel	no
0028,0063	CompressionDescription	no
0028,0065	CompressionSequence	no
0028,0066	CompressionStepPointers	no
0028,0068	RepeatInterval	no
0028,0069	BitsGrouped	no
0028,0070	PerimeterTable	no
0028,0071	PerimeterValue	
		no
0028,0080	PredictorRows	no
0028,0081	PredictorColumns	no
0028,0082	PredictorConstants	no
0028,0090	BlockedPixels	no
=		
0028,0091	BlockRows	no
0028,0092	BlockColumns	no
0028,0093	RowOverlap	no
0028,0094	ColumnOverlap	no
	BitsAllocated	
0028,0100		no
0028,0101	BitsStored	no
0028,0102	HighBit	no
0028,0103	PixelRepresentation	no
0028,0104	SmallestValidPixelValue	no
0028,0105	LargestValidPixelValue	no
0028,0106	SmallestImagePixelValue	no
0028,0107	LargestImagePixelValue	no
0028,0108	SmallestPixelValueInSeries	no
0028,0109	LargestPixelValueInSeries	no
0028,0110	SmallestImagePixelValueInPlane	no
0028,0111	LargestImagePixelValueInPlane	no
0028,0120	PixelPaddingValue	no
0028,0121	PixelPaddingRangeLimit	
		no
0028,0200	ImageLocation	no
0028,0300	QualityControlImage	no
0028,0301	BurnedInAnnotation	no
0028,0400	TransformLabel	no
	TransformVersionNumber	
0028,0401		no
0028,0402	NumberOfTransformSteps	no
0028,0403	SequenceOfCompressedData	no
0028,0404	DetailsOfCoefficients	no
0028,04x2	CoefficientCoding	no
	5	
0028,04x3	CoefficientCodingPointers	no
0028,0700	DCTLabel	no
0028,0701	DataBlockDescription	no
0028,0702	DataBlock	no
	NormalizationFactorFormat	
0028,0710		no
0028,0720	ZonalMapNumberFormat	no
0028,0721	ZonalMapLocation	no
0028,0722	ZonalMapFormat	no
0028,0730	AdaptiveMapFormat	no
•	CodeNumberFormat	
0028,0740		no
0028,08x0	CodeLabel	no
0028,08x2	NumberOfTables	no
0028,08x3	CodeTableLocation	no
0028,08x4	BitsForCodeWord	no
0028,08x8	ImageDataLocation	no
0028,0A02	PixelSpacingCalibrationType	no
0028,0A04	PixelSpacingCalibrationDescription	no
0028,1040	PixelIntensityRelationship	no
0028,1041		
0028,1050	PixelIntensityRelationshipSign	no
	PixelIntensityRelationshipSign WindowCenter	no
0028,1051	PixelIntensityRelationshipSign	
0028,1051	PixelIntensityRelationshipSign WindowCenter WindowWidth	no
0028,1051 0028,1052	PixelIntensityRelationshipSign WindowCenter WindowWidth RescaleIntercept	no no no
0028,1051 0028,1052 0028,1053	PixelIntensityRelationshipSign WindowCenter WindowWidth RescaleIntercept RescaleSlope	no no no no
0028,1051 0028,1052 0028,1053 0028,1054	PixelIntensityRelationshipSign WindowCenter WindowWidth RescaleIntercept RescaleSlope RescaleType	no no no no no
0028,1051 0028,1052 0028,1053 0028,1054 0028,1055	PixelIntensityRelationshipSign WindowCenter WindowWidth RescaleIntercept RescaleSlope RescaleType WindowCenterAndWidthExplanation	no no no no
0028,1051 0028,1052 0028,1053 0028,1054	PixelIntensityRelationshipSign WindowCenter WindowWidth RescaleIntercept RescaleSlope RescaleType	no no no no no
0028,1051 0028,1052 0028,1053 0028,1054 0028,1055	PixelIntensityRelationshipSign WindowCenter WindowWidth RescaleIntercept RescaleSlope RescaleType WindowCenterAndWidthExplanation	no no no no no no
0028,1051 0028,1052 0028,1053 0028,1054 0028,1055 0028,1056 0028,1080	PixelIntensityRelationshipSign WindowCenter WindowWidth RescaleIntercept RescaleSlope RescaleType WindowCenterAndWidthExplanation VOI_LUTFunction GrayScale	no no no no no no no no
0028,1051 0028,1052 0028,1053 0028,1054 0028,1055 0028,1056 0028,1080 0028,1090	PixelIntensityRelationshipSign WindowCenter WindowWidth RescaleIntercept RescaleSlope RescaleType WindowCenterAndWidthExplanation VOI_LUTFunction GrayScale RecommendedViewingMode	no
0028,1051 0028,1052 0028,1053 0028,1054 0028,1055 0028,1056 0028,1080 0028,1090 0028,1100	PixelIntensityRelationshipSign WindowCenter WindowWidth RescaleIntercept RescaleSlope RescaleType WindowCenterAndWidthExplanation VOI_LUTFunction GrayScale RecommendedViewingMode GrayLookupTableDescriptor	no
0028,1051 0028,1052 0028,1053 0028,1054 0028,1055 0028,1056 0028,1080 0028,1090 0028,1100 0028,1101	PixelIntensityRelationshipSign WindowCenter WindowWidth RescaleIntercept RescaleSlope RescaleType WindowCenterAndWidthExplanation VOI_LUTFunction GrayScale RecommendedViewingMode GrayLookupTableDescriptor RedPaletteColorTableDescriptor	no
0028,1051 0028,1052 0028,1053 0028,1054 0028,1055 0028,1056 0028,1080 0028,1090 0028,1100	PixelIntensityRelationshipSign WindowCenter WindowWidth RescaleIntercept RescaleSlope RescaleType WindowCenterAndWidthExplanation VOI_LUTFunction GrayScale RecommendedViewingMode GrayLookupTableDescriptor	no

	Exillool 13.24 Tag Names	
0028,1103	BluePaletteColorTableDescriptor	no
0028,1111	LargeRedPaletteColorTableDescr	no
0028,1112	LargeGreenPaletteColorTableDescr	no
0028,1113 0028,1199	LargeBluePaletteColorTableDescr PaletteColorTableUID	no
0028,1199	GrayLookupTableData	no no
0028,1201	RedPaletteColorTableData	no
0028,1202	GreenPaletteColorTableData	no
0028,1203	BluePaletteColorTableData	no
0028,1211	LargeRedPaletteColorTableData	no
0028,1212	LargeGreenPaletteColorTableData	no
0028,1213	LargeBluePaletteColorTableData	no
0028,1214	LargePaletteColorLookupTableUID	no
0028,1221 0028,1222	SegmentedRedColorTableData SegmentedGreenColorTableData	no
0028,1222	SegmentedGleencolorTableData	no no
0028,1300	BreastImplantPresent	no
0028,1350	PartialView	no
0028,1351	PartialViewDescription	no
0028,1352	PartialViewCodeSequence	no
0028,135A	SpatialLocationsPreserved	no
0028,1402	DataPathAssignment	no
0028,1404	BlendingLUT1Sequence	no
0028,1406	BlendingWeightConstant	no
0028,1408	BlendingLookupTableData	no
0028,140C 0028,140E	BlendingLUT2Sequence DataPathID	no
0028,140E 0028,140F	RGBLUTTransferFunction	no no
0028,1410	AlphaLUTTransferFunction	no
0028,2000	ICCProfile	no
0028,2110	LossyImageCompression	no
0028,2112	LossyImageCompressionRatio	no
0028,2114	${\tt LossyImageCompressionMethod}$	no
0028,3000	ModalityLUTSequence	no
0028,3002	LUTDescriptor	no
0028,3003	LUTExplanation	no
0028,3004 0028,3006	ModalityLUTType LUTData	no
0028,3000	VOILUTSequence	no no
0028,3110	SoftcopyVOILUTSequence	no
0028,4000	ImagePresentationComments	no
0028,5000	BiPlaneAcquisitionSequence	no
0028,6010	RepresentativeFrameNumber	no
0028,6020	FrameNumbersOfInterest	no
0028,6022	FrameOfInterestDescription	no
0028,6023	FrameOfInterestType	no
0028,6030 0028,6040	MaskPointers RWavePointer	no
0028,6040	MaskSubtractionSequence	no no
0028,6101	MaskOperation	no
0028,6102	ApplicableFrameRange	no
0028,6110	MaskFrameNumbers	no
0028,6112	ContrastFrameAveraging	no
0028,6114	MaskSubPixelShift	no
0028,6120	TIDOffset	no
0028,6190	MaskOperationExplanation	no
0028,7FE0	PixelDataProviderURL DataPointRows	no
0028,9001 0028,9002	DataPointColumns	no
0028,9002	SignalDomainColumns	no no
0028,9099	LargestMonochromePixelValue	no
0028,9108	DataRepresentation	no
0028,9110	PixelMeasuresSequence	no
0028,9132	FrameVOILUTSequence	no
0028,9145	PixelValueTransformationSequence	no
0028,9235	SignalDomainRows	no
0028,9411	DisplayFilterPercentage	no
0028,9415	FramePixelShiftSequence	no
0028,9416 0028,9422	SubtractionItemID PixelIntensityRelationshipLUTSeq	no
0040,9444	r rverrincenarchveracronsurbro196d	no

	ExifTool 13.24 Tag Names	
0028,9443	FramePixelDataPropertiesSequence	no
0028,9444	GeometricalProperties	no
0028,9445	GeometricMaximumDistortion	no
0028,9446	ImageProcessingApplied	no
0028,9454	MaskSelectionMode	no
0028,9474	LUTFunction	no
0028,9478	MaskVisibilityPercentage	no
0028,9501	PixelShiftSequence	no
0028,9502	RegionPixelShiftSequence	no
0028,9503	VerticesOfTheRegion	no
0028,9506	PixelShiftFrameRange	no
0028,9507	LUTFrameRange	no
0028,9520	ImageToEquipmentMappingMatrix	no
0028,9537	EquipmentCoordinateSystemID	no
0029,1004	LowerRangeOfPixels1a	no
0029,1005	LowerRangeOfPixels1b	no
0029,1006 0029,1007	LowerRangeOfPixels1c LowerRangeOfPixels1d	no
0029,1007	LowerRangeOfFixels1e	no no
0029,1009	LowerRangeOfPixels1f	no
0029,100A	LowerRangeOfPixels1g	no
0029,1015	LowerRangeOfPixels1h	no
0029,1016	LowerRangeOfPixels1i	no
0029,1017	LowerRangeOfPixels2	no
0029,1018	UpperRangeOfPixels2	no
0029,101A	LenOfTotHdrInBytes	no
0029,1026	VersionOfTheHdrStruct	no
0029,1034	AdvantageCompOverflow	no
0029,1035	AdvantageCompUnderflow	no
0032,0000	StudyGroupLength	no
0032,000A	StudyStatusID	no
0032,000C	StudyPriorityID	no
0032,0012	StudyIDIssuer	no
0032,0032	StudyVerifiedDate	no
0032,0033	StudyVerifiedTime	no
0032,0034 0032,0035	StudyReadDate StudyReadTime	no
0032,0033	ScheduledStudyStartDate	no no
0032,1000	ScheduledStudyStartTime	no
0032,1010	ScheduledStudyStopDate	no
0032,1011	ScheduledStudyStopTime	no
0032,1020	ScheduledStudyLocation	no
0032,1021	ScheduledStudyLocationAETitle	no
0032,1030	ReasonForStudy	no
0032,1031	RequestingPhysicianIDSequence	no
0032,1032	RequestingPhysician	no
0032,1033	RequestingService	no
0032,1040	StudyArrivalDate	no
0032,1041	StudyArrivalTime	no
0032,1050	StudyCompletionDate	no
0032,1051	StudyCompletionTime	no
0032,1055	StudyComponentStatusID	no
0032,1060	RequestedProcedureDescription	no
0032,1064 0032,1070	RequestedProcedureCodeSequence RequestedContrastAgent	no
0032,1070	StudyComments	no no
0032,4000	ReferencedPatientAliasSequence	no
0038,0008	VisitStatusID	no
0038,0010	AdmissionID	no
0038,0011	IssuerOfAdmissionID	no
0038,0016	RouteOfAdmissions	no
0038,001A	ScheduledAdmissionDate	no
0038,001B	ScheduledAdmissionTime	no
0038,001C	ScheduledDischargeDate	no
0038,001D	ScheduledDischargeTime	no
0038,001E	ScheduledPatientInstitResidence	no
0038,0020	AdmittingDate	no
0038,0021	AdmittingTime	no
0038,0030	DischargeDate	no
0038,0032	DischargeTime	no

	ExifTool 13.24 Tag Names	-
0038,0040	DischargeDiagnosisDescription	no
0038,0044	DischargeDiagnosisCodeSequence	no
0038,0050	SpecialNeeds	no
0038,0060	ServiceEpisodeID	no
0038,0061	IssuerOfServiceEpisodeID	no
0038,0062	ServiceEpisodeDescription	no
0038,0100	PertinentDocumentsSequence	no
0038,0300 0038,0400	CurrentPatientLocation PatientInstitutionResidence	no
0038,0400	PatientState	no
0038,0500	PatientClinicalTrialParticipSeq	no no
0038,4000	VisitComments	no
003A,0004	WaveformOriginality	no
003A,0005	NumberOfWaveformChannels	no
003A,0010	NumberOfWaveformSamples	no
003A,001A	SamplingFrequency	no
003A,0020	MultiplexGroupLabel	no
003A,0200	ChannelDefinitionSequence	no
003A,0202	WaveformChannelNumber	no
003A,0203	ChannelLabel	no
003A,0205	ChannelStatus	no
003A,0208	ChannelSourceSequence	no
003A,0209	ChannelSourceModifiersSequence	no
003A,020A 003A,020C	SourceWaveformSequence ChannelDerivationDescription	no
003A,020C	ChannelSensitivity	no no
003A,0210	ChannelSensitivityUnitsSequence	no
003A,0212	ChannelSensitivityCorrectionFactor	no
003A,0213	ChannelBaseline	no
003A,0214	ChannelTimeSkew	no
003A,0215	ChannelSampleSkew	no
003A,0218	ChannelOffset	no
003A,021A	WaveformBitsStored	no
003A,0220	FilterLowFrequency	no
003A,0221	FilterHighFrequency	no
003A,0222	NotchFilterFrequency	no
003A,0223	NotchFilterBandwidth	no
003A,0230 003A,0231	WaveformDataDisplayScale	no
003A,0231	WaveformDisplayBkgCIELabValue WaveformPresentationGroupSequence	no no
003A,0240	PresentationGroupNumber	no
003A,0242	ChannelDisplaySequence	no
003A,0244	ChannelRecommendDisplayCIELabValue	no
003A,0245	ChannelPosition	no
003A,0246	DisplayShadingFlag	no
003A,0247	FractionalChannelDisplayScale	no
003A,0248	AbsoluteChannelDisplayScale	no
003A,0300	${\tt MultiplexAudioChannelsDescrCodeSeq}$	no
003A,0301	ChannelIdentificationCode	no
003A,0302	ChannelMode	no
0040,0001	ScheduledStationAETitle	no
0040,0002	ScheduledProcedureStepStartDate	no
0040,0003	ScheduledProcedureStepStartTime	no
0040,0004 0040,0005	ScheduledProcedureStepEndDate ScheduledProcedureStepEndTime	no
0040,0005	ScheduledPerformingPhysiciansName	no no
0040,0007	ScheduledProcedureStepDescription	no
0040,0008	ScheduledProtocolCodeSequence	no
0040,0009	ScheduledProcedureStepID	no
0040,000A	StageCodeSequence	no
0040,000B	ScheduledPerformingPhysicianIDSeq	no
0040,0010	ScheduledStationName	no
0040,0011	ScheduledProcedureStepLocation	no
0040,0012	PreMedication	no
0040,0020	ScheduledProcedureStepStatus	no
0040,0031	LocalNamespaceEntityID	no
0040,0032	UniversalEntityID	no
0040,0033	UniversalEntityIDType	no
0040,0035	IdentifierTypeCode	no
0040,0036	AssigningFacilitySequence	no

	EXIITOOI 13.24 Tag Names	_
0040,0100	ScheduledProcedureStepSequence	no
0040,0220	ReferencedNonImageCompositeSOPSeq	no
0040,0241	PerformedStationAETitle	no
0040,0242 0040,0243	PerformedStationName PerformedLocation	no no
0040,0244	PerformedProcedureStepStartDate	no
0040,0245	PerformedProcedureStepStartTime	no
0040,0250	PerformedProcedureStepEndDate	no
0040,0251	PerformedProcedureStepEndTime	no
0040,0252	PerformedProcedureStepStatus	no
0040,0253 0040,0254	PerformedProcedureStepID PerformedProcedureStepDescription	no
0040,0254	PerformedProcedureTypeDescription	no no
0040,0260	PerformedProtocolCodeSequence	no
0040,0261	PerformedProtocolType	no
0040,0270	ScheduledStepAttributesSequence	no
0040,0275	RequestAttributesSequence	no
0040,0280	CommentsOnPerformedProcedureStep	no
0040,0281 0040,0293	ProcStepDiscontinueReasonCodeSeq	no
0040,0293	QuantitySequence Quantity	no no
0040,0295	MeasuringUnitsSequence	no
0040,0296	BillingItemSequence	no
0040,0300	TotalTimeOfFluoroscopy	no
0040,0301	TotalNumberOfExposures	no
0040,0302	EntranceDose	no
0040,0303	ExposedArea	no
0040,0306 0040,0307	DistanceSourceToEntrance DistanceSourceToSupport	no no
0040,030F	ExposureDoseSequence	no
0040,0310	CommentsOnRadiationDose	no
0040,0312	XRayOutput	no
0040,0314	HalfValueLayer	no
0040,0316	OrganDose	no
0040,0318 0040,0320	OrganExposed BillingProcedureStepSequence	no
0040,0320	FilmConsumptionSequence	no no
0040,0324	BillingSuppliesAndDevicesSequence	no
0040,0330	ReferencedProcedureStepSequence	no
0040,0340	PerformedSeriesSequence	no
0040,0400	CommentsOnScheduledProcedureStep	no
0040,0440 0040,0441	ProtocolContextSequence	no
0040,0441 0040,050A	ContentItemModifierSequence SpecimenAccessionNumber	no no
0040,0512	ContainerIdentifier	no
0040,051A	ContainerDescription	no
0040,0550	SpecimenSequence	no
0040,0551	SpecimenIdentifier	no
0040,0552	SpecimenDescriptionSequenceTrial	no
0040,0553	SpecimenDescriptionTrial	no
0040,0554 0040,0555	SpecimenUID AcquisitionContextSequence	no no
0040,0556	AcquisitionContextDescription	no
0040,059A	SpecimenTypeCodeSequence	no
0040,0600	SpecimenShortDescription	no
0040,06FA	SlideIdentifier	no
0040,071A	ImageCenterPointCoordinatesSeq	no
0040,072A 0040,073A	XOffsetInSlideCoordinateSystem YOffsetInSlideCoordinateSystem	no
0040,073A	ZOffsetInSlideCoordinateSystem	no no
0040,08D8	PixelSpacingSequence	no
0040,08DA	CoordinateSystemAxisCodeSequence	no
0040,08EA	MeasurementUnitsCodeSequence	no
0040,09F8	VitalStainCodeSequenceTrial	no
0040,1001	RequestedProcedureID	no
0040,1002 0040,1003	ReasonForRequestedProcedure RequestedProcedurePriority	no no
0040,1004	PatientTransportArrangements	no
0040,1005	RequestedProcedureLocation	no
0040,1006	PlacerOrderNumber-Procedure	no

	ExilTool 13.24 Tag Names	•
0040,1007	FillerOrderNumber-Procedure	no
0040,1008	ConfidentialityCode	no
0040,1009	ReportingPriority	no
0040,100A 0040,1010	ReasonForRequestedProcedureCodeSeq NamesOfIntendedRecipientsOfResults	no no
0040,1011	IntendedRecipientsOfResultsIDSeq	no
0040,1101	PersonIdentificationCodeSequence	no
0040,1102	PersonAddress	no
0040,1103	PersonTelephoneNumbers	no
0040,1400	RequestedProcedureComments	no
0040,2001	ReasonForImagingServiceRequest	no
0040,2004 0040,2005	<pre>IssueDateOfImagingServiceRequest IssueTimeOfImagingServiceRequest</pre>	no no
0040,2005	PlacerOrderNum-ImagingServiceReq	no
0040,2007	FillerOrderNum-ImagingServiceReq	no
0040,2008	OrderEnteredBy	no
0040,2009	OrderEntererLocation	no
0040,2010	OrderCallbackPhoneNumber	no
0040,2016	PlacerOrderNum-ImagingServiceReq	no
0040,2017	FillerOrderNum-ImagingServiceReq	no
0040,2400 0040,3001	<pre>ImagingServiceRequestComments ConfidentialityOnPatientDataDescr</pre>	no no
0040,3001	GenPurposeScheduledProcStepStatus	no
0040,4002	GenPurposePerformedProcStepStatus	no
0040,4003	GenPurposeSchedProcStepPriority	no
0040,4004	${\tt SchedProcessingApplicationsCodeSeq}$	no
0040,4005	SchedProcedureStepStartDateAndTime	no
0040,4006	MultipleCopiesFlag	no
0040,4007	PerformedProcessingAppsCodeSeq	no
0040,4009 0040,4010	HumanPerformerCodeSequence SchedProcStepModificationDateTime	no no
0040,4011	ExpectedCompletionDateAndTime	no
0040,4015	ResultingGenPurposePerfProcStepSeq	no
0040,4016	RefGenPurposeSchedProcStepSeq	no
0040,4018	ScheduledWorkitemCodeSequence	no
0040,4019	PerformedWorkitemCodeSequence	no
0040,4020	InputAvailabilityFlag	no
0040,4021 0040,4022	InputInformationSequence RelevantInformationSequence	no no
0040,4022	RefGenPurSchedProcStepTransUID	no
0040,4025	ScheduledStationNameCodeSequence	no
0040,4026	ScheduledStationClassCodeSequence	no
0040,4027	SchedStationGeographicLocCodeSeq	no
0040,4028	PerformedStationNameCodeSequence	no
0040,4029	PerformedStationClassCodeSequence	no
0040,4030 0040,4031	PerformedStationGeogLocCodeSeq RequestedSubsequentWorkItemCodeSeq	no
0040,4031	NonDICOMOutputCodeSequence	no no
0040,4033	OutputInformationSequence	no
0040,4034	ScheduledHumanPerformersSequence	no
0040,4035	ActualHumanPerformersSequence	no
0040,4036	HumanPerformersOrganization	no
0040,4037	HumanPerformerName	no
0040,4040 0040,8302	RawDataHandling EntranceDoseInMilliGy	no
0040,8302	RefImageRealWorldValueMappingSeq	no no
0040,9096	RealWorldValueMappingSequence	no
0040,9098	PixelValueMappingCodeSequence	no
0040,9210	LUTLabel	no
0040,9211	RealWorldValueLastValueMapped	no
0040,9212	RealWorldValueLUTData	no
0040,9216	RealWorldValueFirstValueMapped	no
0040,9224 0040,9225	RealWorldValueIntercept RealWorldValueSlope	no
0040,9223 0040,A010	RelationshipType	no no
0040,A027	VerifyingOrganization	no
0040,A030	VerificationDateTime	no
0040,A032	ObservationDateTime	no
0040,A040	ValueType	no
0040,A043	ConceptNameCodeSequence	no

	ExifTool 13.24 Tag Names	•
0040,A050	ContinuityOfContent	no
0040,A073	VerifyingObserverSequence	no
0040,A075	VerifyingObserverName	no
0040,A078	AuthorObserverSequence	no
0040,A07A	ParticipantSequence	no
0040,A07C	CustodialOrganizationSequence	no
0040,A080	ParticipationType	no
0040,A082 0040,A084	ParticipationDateTime ObserverType	no no
0040,A084	VerifyingObserverIdentCodeSequence	no
0040,A090	EquivalentCDADocumentSequence	no
0040,A0B0	ReferencedWaveformChannels	no
0040,A120	DateTime	no
0040,A121	Date	no
0040,A122	Time	no
0040,A123	PersonName	no
0040,A124	UID	no
0040,A130	TemporalRangeType	no
0040,A132	ReferencedSamplePositions	no
0040,A136 0040,A138	ReferencedFrameNumbers ReferencedTimeOffsets	no
0040,A138	ReferencedIlmeoIlsets ReferencedDateTime	no
0040,A13A	TextValue	no no
0040,A168	ConceptCodeSequence	no
0040,A170	PurposeOfReferenceCodeSequence	no
0040,A180	AnnotationGroupNumber	no
0040,A195	ModifierCodeSequence	no
0040,A300	MeasuredValueSequence	no
0040,A301	NumericValueQualifierCodeSequence	no
0040,A30A	NumericValue	no
0040,A353	AddressTrial	no
0040,A354	TelephoneNumberTrial	no
0040,A360	PredecessorDocumentsSequence	no
0040,A370 0040,A372	ReferencedRequestSequence PerformedProcedureCodeSequence	no
0040,A372	CurrentRequestedProcEvidenceSeq	no no
0040,A385	PertinentOtherEvidenceSequence	no
0040,A390	HL7StructuredDocumentRefSeq	no
0040,A491	CompletionFlag	no
0040,A492	CompletionFlagDescription	no
0040,A493	VerificationFlag	no
0040,A494	ArchiveRequested	no
0040,A496	PreliminaryFlag	no
0040,A504	ContentTemplateSequence	no
0040,A525	IdenticalDocumentsSequence	no
0040,A730 0040,B020	ContentSequence AnnotationSequence	no
0040,B020	TemplateIdentifier	no no
0040,DB06	TemplateVersion	no
0040,DB07	TemplateLocalVersion	no
0040,DB0B	TemplateExtensionFlag	no
0040,DB0C	TemplateExtensionOrganizationUID	no
0040,DB0D	TemplateExtensionCreatorUID	no
0040,DB73	ReferencedContentItemIdentifier	no
0040,E001	HL7InstanceIdentifier	no
0040,E004	HL7DocumentEffectiveTime	no
0040,E006	HL7DocumentTypeCodeSequence	no
0040,E010 0040,E011	RetrieveURI RetrieveLocationUID	no
0040,8011	DocumentTitle	no
0042,0010	EncapsulatedDocument	no no
0042,0012	MIMETypeOfEncapsulatedDocument	no
0042,0013	SourceInstanceSequence	no
0042,0014	ListOfMIMETypes	no
0043,1001	BitmapOfPrescanOptions	no
0043,1002	GradientOffsetInX	no
0043,1003	GradientOffsetInY	no
0043,1004	GradientOffsetInZ	no
0043,1005	ImgIsOriginalOrUnoriginal	no
0043,1006	NumberOfEPIShots	no

	ExifTool 13.24 Tag Names -	-
0043,1007	ViewsPerSegment	no
0043,1008	RespiratoryRateBpm	no
0043,1009	RespiratoryTriggerPoint	no
0043,100A	TypeOfReceiverUsed	no
0043,100B	PeakRateOfChangeOfGradientField	no
0043,100C	LimitsInUnitsOfPercent	no
0043,100D	PSDEstimatedLimit	no
0043,100E	PSDEstimatedLimitInTeslaPerSecond	no
0043,100F	Saravghead	no
0043,1010	WindowValue	no
0043,1011	TotalInputViews	no
0043,1012	X-RayChain_	no
0043,1013	DeconKernelParameters	no
0043,1014	CalibrationParameters	no
0043,1015	TotalOutputViews	no
0043,1016	NumberOfOverranges	no
0043,1017	IBHImageScaleFactors BBHCoefficients	no
0043,1018 0043,1019	NumberOfBBHChainsToBlend	no
0043,1019 0043,101A	StartingChannelNumber	no
0013,101A 0043,101B	PpscanParameters	no no
0013,101B	GEImageIntegrity	no
0043,101D	LevelValue	no
0043,101E	DeltaStartTime	no
0043,101F	MaxOverrangesInAView	no
0043,1020	AvgOverrangesAllViews	no
0043,1021	CorrectedAfterGlowTerms	no
0043,1025	ReferenceChannels	no
0043,1026	NoViewsRefChansBlocked	no
0043,1027	ScanPitchRatio	no
0043,1028	UniqueImageIden	no
0043,1029	HistogramTables	no
0043,102A	UserDefinedData	no
0043,102B	PrivateScanOptions	no
0043,102C	EffectiveEchoSpacing	no
0043,102D	StringSlopField1	no
0043,102E	StringSlopField2	no
0043,102F 0043,1030	RawDataType RawDataType	no
0043,1030	RACordOfTargetReconCenter	no no
0043,1032	RawDataType	no
0043,1033	NegScanspacing	no
0043,1034	OffsetFrequency	no
0043,1035	UserUsageTag	no
0043,1036	UserFillMapMSW	no
0043,1037	UserFillMapLSW	no
0043,1038	User25-48	no
0043,1039	SlopInt6-9	no
0043,1040	TriggerOnPosition	no
0043,1041	DegreeOfRotation	no
0043,1042	DASTriggerSource	no
0043,1043	DASFpaGain	no
0043,1044	DASOutputSource	no
0043,1045	DASAdInput	no
0043,1046	DASCalMode	no
0043,1047	DASCalFrequency	no
0043,1048 0043,1049	DASRegXm DASAutoZero	no
0043,1045 0043,104A	StartingChannelOfView	no
0043,104A	DASXmPattern	no no
0043,104C	TGGCTriggerMode	no
0043,104D	StartScanToXrayOnDelay	no
0043,104E	DurationOfXrayOn	no
0043,1060	SlopInt10-17	no
0043,1061	ScannerStudyEntityUID	no
0043,1062	ScannerStudyID	no
0043,106f	ScannerTableEntry	no
0044,0001	ProductPackageIdentifier	no
0044,0002	SubstanceAdministrationApproval	no
0044,0003	ApprovalStatusFurtherDescription	no

	ExifTool 13.24 Tag Names -	-
0044,0004	ApprovalStatusDateTime	no
0044,0007	ProductTypeCodeSequence	no
0044,0008	ProductName	no
0044,0009	ProductDescription	no
0044,000A	ProductLotIdentifier	no
0044,000B	ProductExpirationDateTime	no
0044,0010	SubstanceAdministrationDateTime SubstanceAdministrationNotes	no
0044,0011 0044,0012	SubstanceAdministrationDeviceID	no no
0044,0012	ProductParameterSequence	no
0044,0019	SubstanceAdminParameterSeq	no
0045,1001	NumberOfMacroRowsInDetector	no
0045,1002	MacroWidthAtISOCenter	no
0045,1003	DASType	no
0045,1004	DASGain	no
0045,1005	DASTemperature	no
0045,1006	TableDirectionInOrOut	no
0045,1007	ZSmoothingFactor	no
0045,1008	ViewWeightingMode	no
0045,1009 0045,100A	SigmaRowNumberWhichRowsWereUsed	no
0045,100A 0045,100B	MinimumDasValueFoundInTheScanData MaximumOffsetShiftValueUsed	no
0045,100B	NumberOfViewsShifted	no no
0045,100D	ZTrackingFlag	no
0045,100E	MeanZError	no
0045,100F	ZTrackingMaximumError	no
0045,1010	StartingViewForRow2a	no
0045,1011	NumberOfViewsInRow2a	no
0045,1012	StartingViewForRow1a	no
0045,1013	SigmaMode	no
0045,1014	NumberOfViewsInRowla	no
0045,1015	StartingViewForRow2b	no
0045,1016	NumberOfViewsInRow2b	no
0045,1017	StartingViewForRow1b NumberOfViewsInRow1b	no
0045,1018 0045,1019	AirFilterCalibrationDate	no
0045,1019 0045,101A	AirFilterCalibrationTime	no no
0045,101B	PhantomCalibrationDate	no
0045,101C	PhantomCalibrationTime	no
0045,101D	ZSlopeCalibrationDate	no
0045,101E	ZSlopeCalibrationTime	no
0045,101F	CrosstalkCalibrationDate	no
0045,1020	CrosstalkCalibrationTime	no
0045,1021	IterboneOptionFlag	no
0045,1022	PeristalticFlagOption	no
0046,0012	LensDescription	no
0046,0014	RightLensSequence	no
0046,0015 0046,0018	LeftLensSequence CylinderSequence	no
0046,0018	PrismSequence	no no
0046,0030	HorizontalPrismPower	no
0046,0032	HorizontalPrismBase	no
0046,0034	VerticalPrismPower	no
0046,0036	VerticalPrismBase	no
0046,0038	LensSegmentType	no
0046,0040	OpticalTransmittance	no
0046,0042	ChannelWidth	no
0046,0044	PupilSize	no
0046,0046	CornealSize	no
0046,0060	DistancePupillaryDistance	no
0046,0062 0046,0064	NearPupillaryDistance OtherPupillaryDistance	no
0046,0064	RadiusOfCurvature	no
0046,0075	KeratometricPower	no no
0046,0077	KeratometricAxis	no
0046,0092	BackgroundColor	no
0046,0094	Optotype	no
0046,0095	OptotypePresentation	no
0046,0100	AddNearSequence	no
0046,0101	AddIntermediateSequence	no

	EXITION 13.24 Tag Names -	-
0046,0102	AddOtherSequence	no
0046,0104	AddPower	no
0046,0106	ViewingDistance	no
0046,0125	ViewingDistanceType	no
0046,0135	VisualAcuityModifiers	no
0046,0137	DecimalVisualAcuity	no
0046,0139	OptotypeDetailedDefinition	no
0046,0146 0046,0147	SpherePower CylinderPower	no
0050,0147	CalibrationImage	no no
0050,0001	DeviceSequence	no
0050,0014	DeviceLength	no
0050,0015	ContainerComponentWidth	no
0050,0016	DeviceDiameter	no
0050,0017	DeviceDiameterUnits	no
0050,0018	DeviceVolume	no
0050,0019	InterMarkerDistance	no
0050,001B	ContainerComponentID	no
0050,0020	DeviceDescription	no
0054,0010	EnergyWindowVector	no
0054,0011	NumberOfEnergyWindows	no
0054,0012	EnergyWindowInformationSequence	no
0054,0013	EnergyWindowRangeSequence	no
0054,0014	EnergyWindowLowerLimit	no
0054,0015 0054,0016	EnergyWindowUpperLimit	no
0054,0018	RadiopharmaceuticalInformationSeq	no
0054,0017	ResidualSyringeCounts EnergyWindowName	no no
0054,0010	DetectorVector	no
0054,0020	NumberOfDetectors	no
0054,0022	DetectorInformationSequence	no
0054,0030	PhaseVector	no
0054,0031	NumberOfPhases	no
0054,0032	PhaseInformationSequence	no
0054,0033	NumberOfFramesInPhase	no
0054,0036	PhaseDelay	no
0054,0038	PauseBetweenFrames	no
0054,0039	PhaseDescription	no
0054,0050	RotationVector	no
0054,0051	NumberOfRotations	no
0054,0052	RotationInformationSequence	no
0054,0053 0054,0060	NumberOfFramesInRotation RRIntervalVector	no no
0054,0061	NumberOfRRIntervals	no
0054,0062	GatedInformationSequence	no
0054,0063	DataInformationSequence	no
0054,0070	TimeSlotVector	no
0054,0071	NumberOfTimeSlots	no
0054,0072	TimeSlotInformationSequence	no
0054,0073	TimeSlotTime	no
0054,0080	SliceVector	no
0054,0081	NumberOfSlices	no
0054,0090	AngularViewVector	no
0054,0100	TimeSliceVector	no
0054,0101	NumberOfTimeSlices	no
0054,0200	StartAngle	no
0054,0202	TypeOfDetectorMotion	no
0054,0210	TriggerVector	no
0054,0211 0054,0220	NumberOfTriggersInPhase ViewCodeSequence	no
0054,0220	ViewModifierCodeSequence	no no
0054,0222	RadionuclideCodeSequence	no
0054,0300	AdministrationRouteCodeSequence	no
0054,0304	RadiopharmaceuticalCodeSequence	no
0054,0306	CalibrationDataSequence	no
0054,0308	EnergyWindowNumber	no
0054,0400	ImageID	no
0054,0410	PatientOrientationCodeSequence	no
0054,0412	PatientOrientationModifierCodeSeq	no
0054,0414	PatientGantryRelationshipCodeSeq	no

	ExifTool 13.24 Tag Names	-
0054,0500	SliceProgressionDirection	no
0054,1000	SeriesType	no
0054,1001	Units	no
0054,1002	CountsSource	no
0054,1004	ReprojectionMethod	no
0054,1100 0054,1101	RandomsCorrectionMethod AttenuationCorrectionMethod	no
0054,1101	DecayCorrection	no no
0054,1102	ReconstructionMethod	no
0054,1104	DetectorLinesOfResponseUsed	no
0054,1105	ScatterCorrectionMethod	no
0054,1200	AxialAcceptance	no
0054,1201	AxialMash	no
0054,1202	TransverseMash	no
0054,1203	DetectorElementSize	no
0054,1210	CoincidenceWindowWidth	no
0054,1220	SecondaryCountsType	no
0054,1300	FrameReferenceTime	no
0054,1310 0054,1311	PrimaryCountsAccumulated SecondaryCountsAccumulated	no
0054,1311	SliceSensitivityFactor	no no
0054,1320	DecayFactor	no
0054,1322	DoseCalibrationFactor	no
0054,1323	ScatterFractionFactor	no
0054,1324	DeadTimeFactor	no
0054,1330	ImageIndex	no
0054,1400	CountsIncluded	no
0054,1401	DeadTimeCorrectionFlag	no
0060,3000	HistogramSequence	no
0060,3002	HistogramNumberOfBins	no
0060,3004	HistogramFirstBinValue	no
0060,3006 0060,3008	HistogramLastBinValue HistogramBinWidth	no
0060,3008	HistogramExplanation	no no
0060,3020	HistogramData	no
0062,0001	SegmentationType	no
0062,0002	SegmentSequence	no
0062,0003	SegmentedPropertyCategoryCodeSeq	no
0062,0004	SegmentNumber	no
0062,0005	SegmentLabel	no
0062,0006	SegmentDescription	no
0062,0008	SegmentAlgorithmType	no
0062,0009 0062,000A	SegmentAlgorithmName SegmentIdentificationSequence	no
0062,000A 0062,000B	ReferencedSegmentNumber	no no
0062,000E	RecommendedDisplayGrayscaleValue	no
0062,000D	RecommendedDisplayCIELabValue	no
0062,000E	MaximumFractionalValue	no
0062,000F	SegmentedPropertyTypeCodeSequence	no
0062,0010	SegmentationFractionalType	no
0064,0002	DeformableRegistrationSequence	no
0064,0003	SourceFrameOfReferenceUID	no
0064,0005	DeformableRegistrationGridSequence	no
0064,0007	GridDimensions	no
0064,0008 0064,0009	GridResolution VectorGridData	no
0064,0009 0064,000F	PreDeformationMatrixRegistSeq	no no
0064,0001	PostDeformationMatrixRegistSeq	no
0066,0001	NumberOfSurfaces	no
0066,0002	SurfaceSequence	no
0066,0003	SurfaceNumber	no
0066,0004	SurfaceComments	no
0066,0009	SurfaceProcessing	no
0066,000A	SurfaceProcessingRatio	no
0066,000E	FiniteVolume	no
0066,0010	Manifold	no
0066,0011	SurfacePointsSequence	no
0066,0015 0066,0016	NumberOfSurfacePoints PointCoordinatesData	no
0066,0017	PointPositionAccuracy	no no
3000,001	1 OTHER ODICIOINCOURACY	110

	Exillool 13.24 rag Names	•
0066,0018	MeanPointDistance	no
0066,0019	MaximumPointDistance	no
0066,001B	AxisOfRotation	no
0066,001C	CenterOfRotation	no
0066,001E	NumberOfVectors	no
0066,001F	VectorDimensionality	no
0066,0020	VectorAccuracy	no
0066,0021	VectorCoordinateData	no
0066,0023	TrianglePointIndexList	no
0066,0024 0066,0025	EdgePointIndexList VertexPointIndexList	no
0066,0026	TriangleStripSequence	no no
0066,0027	TriangleFanSequence	no
0066,0028	LineSequence	no
0066,0029	PrimitivePointIndexList	no
0066,002A	SurfaceCount	no
0066,002F	AlgorithmFamilyCodeSequ	no
0066,0031	AlgorithmVersion	no
0066,0032	AlgorithmParameters	no
0066,0034	FacetSequence	no
0066,0036	AlgorithmName	no
0070,0001	GraphicAnnotationSequence	no
0070,0002	GraphicLayer	no
0070,0003	BoundingBoxAnnotationUnits	no
0070,0004	AnchorPointAnnotationUnits	no
0070,0005	GraphicAnnotationUnits	no
0070,0006	UnformattedTextValue	no
0070,0008	TextObjectSequence	no
0070,0009	GraphicObjectSequence	no
0070,0010 0070,0011	BoundingBoxTopLeftHandCorner BoundingBoxBottomRightHandCorner	no
0070,0011	BoundingBoxTextHorizJustification	no no
0070,0012	AnchorPoint	no
0070,0011	AnchorPointVisibility	no
0070,0020	GraphicDimensions	no
0070,0021	NumberOfGraphicPoints	no
0070,0022	GraphicData	no
0070,0023	GraphicType	no
0070,0024	GraphicFilled	no
0070,0040	ImageRotationRetired	no
0070,0041	ImageHorizontalFlip	no
0070,0042	ImageRotation	no
0070,0050	DisplayedAreaTopLeftTrial	no
0070,0051	DisplayedAreaBottomRightTrial	no
0070,0052	DisplayedAreaTopLeft	no
0070,0053	DisplayedAreaBottomRight	no
0070,005A	DisplayedAreaSelectionSequence	no
0070,0060 0070,0062	GraphicLayerSequence GraphicLayerOrder	no
0070,0062	GraphicLayerRecDisplayGraysclValue	no
0070,0067	GraphicLayerRecDisplayRGBValue	no no
0070,0068	GraphicLayerDescription	no
0070,0080	ContentLabel	no
0070,0081	ContentDescription	no
0070,0082	PresentationCreationDate	no
0070,0083	PresentationCreationTime	no
0070,0084	ContentCreatorName	no
0070,0086	ContentCreatorIDCodeSequence	no
0070,0100	PresentationSizeMode	no
0070,0101	PresentationPixelSpacing	no
0070,0102	PresentationPixelAspectRatio	no
0070,0103	PresentationPixelMagRatio	no
0070,0306	ShapeType	no
0070,0308	RegistrationSequence	no
0070,0309	MatrixRegistrationSequence	no
0070,030A	MatrixSequence	no
0070,030C	FrameOfRefTransformationMatrixType	no
0070,030D	RegistrationTypeCodeSequence	no
0070,030F	Fiducial Description	no
0070,0310	FiducialIdentifier	no

	ExifTool 13.24 Tag Names -	-
0070,0311	FiducialIdentifierCodeSequence	no
0070,0312	ContourUncertaintyRadius	no
0070,0314	UsedFiducialsSequence	no
0070,0318	GraphicCoordinatesDataSequence	no
0070,031A	FiducialUID	no
0070,031C	FiducialSetSequence	no
0070,031E	FiducialSequence	no
0070,0401	GraphicLayerRecomDisplayCIELabVal	no
0070,0402	BlendingSequence	no
0070,0403	RelativeOpacity	no
0070,0404	ReferencedSpatialRegistrationSeq	no
0070,0405	BlendingPosition	no
0072,0002 0072,0004	HangingProtocolName	no
0072,0004	HangingProtocolDescription HangingProtocolLevel	no no
0072,0008	HangingProtocolCreator	no
0072,000A	HangingProtocolCreationDateTime	no
0072,000C	HangingProtocolDefinitionSequence	no
0072,000E	HangingProtocolUserIDCodeSequence	no
0072,0010	HangingProtocolUserGroupName	no
0072,0012	SourceHangingProtocolSequence	no
0072,0014	NumberOfPriorsReferenced	no
0072,0020	ImageSetsSequence	no
0072,0022	ImageSetSelectorSequence	no
0072,0024	ImageSetSelectorUsageFlag	no
0072,0026	SelectorAttribute	no
0072,0028	SelectorValueNumber	no
0072,0030	TimeBasedImageSetsSequence	no
0072,0032	ImageSetNumber	no
0072,0034	ImageSetSelectorCategory	no
0072,0038	RelativeTime	no
0072,003A	RelativeTimeUnits	no
0072,003C	AbstractPriorValue	no
0072,003E	AbstractPriorCodeSequence	no
0072,0040	ImageSetLabel	no
0072,0050 0072,0052	SelectorAttributeVR SelectorSequencePointer	no
0072,0052	SelectorSeqPointerPrivateCreator	no no
0072,0051	SelectorAttributePrivateCreator	no
0072,0060	SelectorATValue	no
0072,0062	SelectorCSValue	no
0072,0064	SelectorISValue	no
0072,0066	SelectorLOValue	no
0072,0068	SelectorLTValue	no
0072,006A	SelectorPNValue	no
0072,006C	SelectorSHValue	no
0072,006E	SelectorSTValue	no
0072,0070	SelectorUTValue	no
0072,0072	SelectorDSValue	no
0072,0074 0072,0076	SelectorFDValue SelectorFLValue	no
0072,0078	SelectorULValue	no
0072,0078 0072,007A	SelectorUSValue	no no
0072,007H	SelectorSLValue	no
0072,007E	SelectorSSValue	no
0072,0080	SelectorCodeSequenceValue	no
0072,0100	NumberOfScreens	no
0072,0102	NominalScreenDefinitionSequence	no
0072,0104	NumberOfVerticalPixels	no
0072,0106	NumberOfHorizontalPixels	no
0072,0108	DisplayEnvironmentSpatialPosition	no
0072,010A	ScreenMinimumGrayscaleBitDepth	no
0072,010C	ScreenMinimumColorBitDepth	no
0072,010E	ApplicationMaximumRepaintTime	no
0072,0200	DisplaySetsSequence	no
0072,0202	DisplaySetNumber	no
0072,0203	DisplaySetLabel	no
0072,0204	DisplaySetPresentationGroup	no
0072,0206	DisplaySetPresentationGroupDescr	no
0072,0208	PartialDataDisplayHandling	no

0072,0210	SynchronizedScrollingSequence	no
0072,0212	DisplaySetScrollingGroup	no
0072,0214	NavigationIndicatorSequence	no
0072,0216	NavigationDisplaySet	no
0072,0218	ReferenceDisplaySets	no
0072,0210	ImageBoxesSequence	no
-	_	
0072,0302	ImageBoxNumber	no
0072,0304	ImageBoxLayoutType	no
0072,0306	ImageBoxTileHorizontalDimension	no
0072,0308	ImageBoxTileVerticalDimension	no
0072,0310	ImageBoxScrollDirection	no
0072,0312	ImageBoxSmallScrollType	no
0072,0314	ImageBoxSmallScrollAmount	no
0072,0311	ImageBoxLargeScrollType	no
0072,0318		
	ImageBoxLargeScrollAmount	no
0072,0320	ImageBoxOverlapPriority	no
0072,0330	CineRelativeToRealTime	no
0072,0400	FilterOperationsSequence	no
0072,0402	FilterByCategory	no
0072,0404	FilterByAttributePresence	no
0072,0406	FilterByOperator	no
0072,0432	SynchronizedImageBoxList	no
0072,0434	TypeOfSynchronization	no
0072,0500	BlendingOperationType	
		no
0072,0510	ReformattingOperationType	no
0072,0512	ReformattingThickness	no
0072,0514	ReformattingInterval	no
0072,0516	ReformattingOpInitialViewDir	no
0072,0520	RenderingType3D	no
0072,0600	SortingOperationsSequence	no
0072,0602	SortByCategory	no
0072,0604	SortingDirection	no
0072,0700	DisplaySetPatientOrientation	no
0072,0702	VOIType	no
0072,0704	PseudoColorType	no
0072,0706	ShowGrayscaleInverted	no
0072,0700	ShowImageTrueSizeFlag	
		no
0072,0712	ShowGraphicAnnotationFlag	no
0072,0714	ShowPatientDemographicsFlag	no
0072,0716	ShowAcquisitionTechniquesFlag	no
0072,0717	DisplaySetHorizontalJustification	no
0072,0718	DisplaySetVerticalJustification	no
0074,1000	UnifiedProcedureStepState	no
0074,1002	UPSProgressInformationSequence	no
0074,1004	UnifiedProcedureStepProgress	no
0074,1006	UnifiedProcedureStepProgressDescr	no
0074,1008	<del>-</del>	
	UnitiedProcedureStepComURISed	no
	UnifiedProcedureStepComURISeq	no
0074,100a	ContactURI	no
0074,100a 0074,100c	ContactURI ContactDisplayName	no no
0074,100a 0074,100c 0074,1020	ContactURI ContactDisplayName BeamTaskSequence	no no no
0074,100a 0074,100c 0074,1020 0074,1022	ContactURI ContactDisplayName BeamTaskSequence BeamTaskType	no no
0074,100a 0074,100c 0074,1020 0074,1022 0074,1024	ContactURI ContactDisplayName BeamTaskSequence BeamTaskType BeamOrderIndex	no no no
0074,100a 0074,100c 0074,1020 0074,1022 0074,1024 0074,1030	ContactURI ContactDisplayName BeamTaskSequence BeamTaskType	no no no no
0074,100a 0074,100c 0074,1020 0074,1022 0074,1024	ContactURI ContactDisplayName BeamTaskSequence BeamTaskType BeamOrderIndex	no no no no no
0074,100a 0074,100c 0074,1020 0074,1022 0074,1024 0074,1030	ContactURI ContactDisplayName BeamTaskSequence BeamTaskType BeamOrderIndex DeliveryVerificationImageSequence	no no no no no no
0074,100a 0074,100c 0074,1020 0074,1022 0074,1024 0074,1030 0074,1032 0074,1034	ContactURI ContactDisplayName BeamTaskSequence BeamTaskType BeamOrderIndex DeliveryVerificationImageSequence VerificationImageTiming DoubleExposureFlag	no no no no no no
0074,100a 0074,100c 0074,1020 0074,1022 0074,1024 0074,1030 0074,1032 0074,1034 0074,1036	ContactURI ContactDisplayName BeamTaskSequence BeamTaskType BeamOrderIndex DeliveryVerificationImageSequence VerificationImageTiming DoubleExposureFlag DoubleExposureOrdering	no
0074,100a 0074,100c 0074,1020 0074,1022 0074,1024 0074,1030 0074,1032 0074,1034 0074,1036 0074,1038	ContactURI ContactDisplayName BeamTaskSequence BeamTaskType BeamOrderIndex DeliveryVerificationImageSequence VerificationImageTiming DoubleExposureFlag DoubleExposureOrdering DoubleExposureMeterset	no n
0074,100a 0074,100c 0074,1020 0074,1022 0074,1024 0074,1030 0074,1032 0074,1034 0074,1036 0074,1038 0074,103A	ContactURI ContactDisplayName BeamTaskSequence BeamTaskType BeamOrderIndex DeliveryVerificationImageSequence VerificationImageTiming DoubleExposureFlag DoubleExposureOrdering DoubleExposureMeterset DoubleExposureFieldDelta	no n
0074,100a 0074,100c 0074,1022 0074,1024 0074,1030 0074,1032 0074,1034 0074,1036 0074,1038 0074,103A 0074,103A	ContactURI ContactDisplayName BeamTaskSequence BeamTaskType BeamOrderIndex DeliveryVerificationImageSequence VerificationImageTiming DoubleExposureFlag DoubleExposureOrdering DoubleExposureMeterset DoubleExposureFieldDelta RelatedReferenceRTImageSequence	no n
0074,100a 0074,100c 0074,1020 0074,1022 0074,1030 0074,1032 0074,1034 0074,1036 0074,1038 0074,103A 0074,103A 0074,103A 0074,1040	ContactURI ContactDisplayName BeamTaskSequence BeamTaskType BeamOrderIndex DeliveryVerificationImageSequence VerificationImageTiming DoubleExposureFlag DoubleExposureOrdering DoubleExposureMeterset DoubleExposureFieldDelta RelatedReferenceRTImageSequence GeneralMachineVerificationSequence	no n
0074,100a 0074,100c 0074,1022 0074,1024 0074,1030 0074,1032 0074,1034 0074,1036 0074,1038 0074,103A 0074,103A 0074,1040 0074,1042	ContactURI ContactDisplayName BeamTaskSequence BeamTaskType BeamOrderIndex DeliveryVerificationImageSequence VerificationImageTiming DoubleExposureFlag DoubleExposureOrdering DoubleExposureMeterset DoubleExposureFieldDelta RelatedReferenceRTImageSequence GeneralMachineVerificationSequence ConventionalMachineVerificationSeq	no n
0074,100a 0074,100c 0074,1022 0074,1024 0074,1030 0074,1034 0074,1036 0074,1038 0074,1038 0074,103A 0074,103A 0074,1040 0074,1042 0074,1044	ContactURI ContactDisplayName BeamTaskSequence BeamTaskType BeamOrderIndex DeliveryVerificationImageSequence VerificationImageTiming DoubleExposureFlag DoubleExposureOrdering DoubleExposureMeterset DoubleExposureFieldDelta RelatedReferenceRTImageSequence GeneralMachineVerificationSequence ConventionalMachineVerificationSeq IonMachineVerificationSequence	no n
0074,100a 0074,100c 0074,1022 0074,1024 0074,1030 0074,1032 0074,1034 0074,1036 0074,1038 0074,103A 0074,103A 0074,1040 0074,1042 0074,1044 0074,1044	ContactURI ContactDisplayName BeamTaskSequence BeamTaskType BeamOrderIndex DeliveryVerificationImageSequence VerificationImageTiming DoubleExposureFlag DoubleExposureOrdering DoubleExposureMeterset DoubleExposureFieldDelta RelatedReferenceRTImageSequence GeneralMachineVerificationSequence ConventionalMachineVerificationSeq IonMachineVerificationSequence FailedAttributesSequence	no n
0074,100a 0074,1020 0074,1022 0074,1024 0074,1030 0074,1032 0074,1034 0074,1036 0074,1038 0074,1038 0074,103A 0074,1040 0074,1040 0074,1042 0074,1044 0074,1048 0074,1048	ContactURI ContactDisplayName BeamTaskSequence BeamTaskType BeamOrderIndex DeliveryVerificationImageSequence VerificationImageTiming DoubleExposureFlag DoubleExposureOrdering DoubleExposureMeterset DoubleExposureFieldDelta RelatedReferenceRTImageSequence GeneralMachineVerificationSequence ConventionalMachineVerificationSeq IonMachineVerificationSequence FailedAttributesSequence OverriddenAttributesSequence	no n
0074,100a 0074,100c 0074,1022 0074,1024 0074,1030 0074,1032 0074,1034 0074,1036 0074,1038 0074,103A 0074,103A 0074,1040 0074,1042 0074,1044 0074,1044	ContactURI ContactDisplayName BeamTaskSequence BeamTaskType BeamOrderIndex DeliveryVerificationImageSequence VerificationImageTiming DoubleExposureFlag DoubleExposureOrdering DoubleExposureMeterset DoubleExposureFieldDelta RelatedReferenceRTImageSequence GeneralMachineVerificationSequence ConventionalMachineVerificationSeq IonMachineVerificationSequence FailedAttributesSequence	no n
0074,100a 0074,1020 0074,1022 0074,1024 0074,1030 0074,1032 0074,1034 0074,1036 0074,1038 0074,1038 0074,103A 0074,1040 0074,1040 0074,1042 0074,1044 0074,1048 0074,1048	ContactURI ContactDisplayName BeamTaskSequence BeamTaskType BeamOrderIndex DeliveryVerificationImageSequence VerificationImageTiming DoubleExposureFlag DoubleExposureOrdering DoubleExposureMeterset DoubleExposureFieldDelta RelatedReferenceRTImageSequence GeneralMachineVerificationSequence ConventionalMachineVerificationSeq IonMachineVerificationSequence FailedAttributesSequence OverriddenAttributesSequence	no n
0074,100a 0074,1020 0074,1022 0074,1024 0074,1030 0074,1032 0074,1034 0074,1036 0074,1038 0074,1038 0074,103A 0074,1040 0074,1042 0074,1044 0074,1046 0074,1048 0074,104A 0074,104A	ContactURI ContactDisplayName BeamTaskSequence BeamTaskType BeamOrderIndex DeliveryVerificationImageSequence VerificationImageTiming DoubleExposureFlag DoubleExposureOrdering DoubleExposureMeterset DoubleExposureFieldDelta RelatedReferenceRTImageSequence GeneralMachineVerificationSequence ConventionalMachineVerificationSeq IonMachineVerificationSequence FailedAttributesSequence OverriddenAttributesSequence ConventionalControlPointVerifySeq	no n
0074,100a 0074,100c 0074,1022 0074,1024 0074,1030 0074,1032 0074,1034 0074,1036 0074,1038 0074,1038 0074,103A 0074,1040 0074,1042 0074,1044 0074,1044 0074,1048 0074,104A 0074,104C 0074,104E 0074,104E	ContactURI ContactDisplayName BeamTaskSequence BeamTaskType BeamOrderIndex DeliveryVerificationImageSequence VerificationImageTiming DoubleExposureFlag DoubleExposureOrdering DoubleExposureMeterset DoubleExposureFieldDelta RelatedReferenceRTImageSequence GeneralMachineVerificationSequence ConventionalMachineVerificationSeq IonMachineVerificationSequence FailedAttributesSequence OverriddenAttributesSequence ConventionalControlPointVerifySeq IonControlPointVerificationSeq	no n
0074,100a 0074,100c 0074,1022 0074,1024 0074,1030 0074,1032 0074,1034 0074,1036 0074,1038 0074,1038 0074,103A 0074,1040 0074,1042 0074,1044 0074,1044 0074,1048 0074,104A 0074,104A 0074,104C 0074,104E	ContactURI ContactDisplayName BeamTaskSequence BeamTaskType BeamOrderIndex DeliveryVerificationImageSequence VerificationImageTiming DoubleExposureFlag DoubleExposureOrdering DoubleExposureMeterset DoubleExposureFieldDelta RelatedReferenceRTImageSequence GeneralMachineVerificationSequence ConventionalMachineVerificationSeq IonMachineVerificationSequence FailedAttributesSequence OverriddenAttributesSequence ConventionalControlPointVerifySeq IonControlPointVerificationSeq AttributeOccurrenceSequence	no n
0074,100a 0074,100c 0074,1022 0074,1024 0074,1030 0074,1032 0074,1034 0074,1036 0074,1038 0074,103A 0074,103A 0074,1040 0074,1042 0074,1044 0074,1044 0074,1048 0074,104C 0074,104E 0074,1050 0074,1050	ContactURI ContactDisplayName BeamTaskSequence BeamTaskType BeamOrderIndex DeliveryVerificationImageSequence VerificationImageTiming DoubleExposureFlag DoubleExposureOrdering DoubleExposureMeterset DoubleExposureFieldDelta RelatedReferenceRTImageSequence GeneralMachineVerificationSequence ConventionalMachineVerificationSeq IonMachineVerificationSequence FailedAttributesSequence OverriddenAttributesSequence ConventionalControlPointVerifySeq IonControlPointVerificationSeq AttributeOccurrenceSequence AttributeOccurrencePointer	no n

	ExifTool 13.24 Tag Names -	
0074,1200	ScheduledProcedureStepPriority	no
0074,1202	WorklistLabel	no
0074,1204	ProcedureStepLabel	no
0074,1210	ScheduledProcessingParametersSeq	no
0074,1212	PerformedProcessingParametersSeq	no
0074,1216	UPSPerformedProcedureSequence	no
0074,1220	RelatedProcedureStepSequence	no
0074,1222 0074,1230	ProcedureStepRelationshipType DeletionLock	no
0074,1230	ReceivingAE	no no
0074,1234	RequestingAE	no
0074,1238	ReasonForCancellation	no
0074,1242	SCPStatus	no
0074,1244	SubscriptionListStatus	no
0074,1246	UPSListStatus	no
0088,0130	StorageMediaFileSetID	no
0088,0140	StorageMediaFileSetUID	no
0088,0200	IconImageSequence	no
0088,0904	TopicTitle	no
0088,0906	TopicSubject	no
0088,0910	TopicAuthor	no
0088,0912	TopicKeywords	no
0100,0410	SOPInstanceStatus SOPAuthorizationDateAndTime	no
0100,0420 0100,0424	SOPAuthorizationComment	no
0100,0424	AuthorizationEquipmentCertNumber	no no
0400,0005	MACIDNumber	no
0400,0010	MACCalculationTransferSyntaxUID	no
0400,0015	MACAlgorithm	no
0400,0020	DataElementsSigned	no
0400,0100	DigitalSignatureUID	no
0400,0105	DigitalSignatureDateTime	no
0400,0110	CertificateType	no
0400,0115	CertificateOfSigner	no
0400,0120	Signature	no
0400,0305	CertifiedTimestampType	no
0400,0310	CertifiedTimestamp	no
0400,0401 0400,0402	DigitalSignaturePurposeCodeSeq	no
0400,0402	ReferencedDigitalSignatureSeq ReferencedSOPInstanceMACSeq	no
0400,0403	MAC	no no
0400,0500	EncryptedAttributesSequence	no
0400,0510	EncryptedContentTransferSyntaxUID	no
0400,0520	EncryptedContent	no
0400,0550	ModifiedAttributesSequence	no
0400,0561	OriginalAttributesSequence	no
0400,0562	AttributeModificationDateTime	no
0400,0563	ModifyingSystem	no
0400,0564	SourceOfPreviousValues	no
0400,0565	ReasonForTheAttributeModification	no
1000,xxx0	EscapeTriplet	no
1000,xxx1	RunLengthTriplet	no
1000,xxx2	HuffmanTableSize	no
1000,xxx3 1000,xxx4	HuffmanTableTriplet ShiftTableSize	no
1000,xxx4 1000,xxx5	ShiftTableSize ShiftTableTriplet	no no
1010,xxxx	ZonalMap	no
2000,0010	NumberOfCopies	no
2000,001E	PrinterConfigurationSequence	no
2000,0020	PrintPriority	no
2000,0030	MediumType	no
2000,0040	FilmDestination	no
2000,0050	FilmSessionLabel	no
2000,0060	MemoryAllocation	no
2000,0061	MaximumMemoryAllocation	no
2000,0062	ColorImagePrintingFlag	no
2000,0063	CollationFlag	no
2000,0065	AnnotationFlag	no
2000,0067	ImageOverlayFlag	no
2000,0069	PresentationLUTFlag	no

	ExifTool 13.24 Tag Names	
2000,006A	ImageBoxPresentationLUTFlag	no
2000,00A0	MemoryBitDepth	no
2000,00A1	PrintingBitDepth	no
2000,00A2	MediaInstalledSequence	no
2000,00A4	OtherMediaAvailableSequence	no
2000,00A8	SupportedImageDisplayFormatSeq	no
2000,0500	ReferencedFilmBoxSequence	no
2000,0510 2010,0010	ReferencedStoredPrintSequence ImageDisplayFormat	no
2010,0010	AnnotationDisplayFormatID	no
2010,0030	FilmOrientation	no no
2010,0010	FilmSizeID	no
2010,0052	PrinterResolutionID	no
2010,0054	DefaultPrinterResolutionID	no
2010,0060	MagnificationType	no
2010,0080	SmoothingType	no
2010,00A6	DefaultMagnificationType	no
2010,00A7	OtherMagnificationTypesAvailable	no
2010,00A8	DefaultSmoothingType	no
2010,00A9	OtherSmoothingTypesAvailable	no
2010,0100	BorderDensity	no
2010,0110	EmptyImageDensity	no
2010,0120	MinDensity	no
2010,0130	MaxDensity	no
2010,0140	Trim	no
2010,0150	ConfigurationInformation	no
2010,0152	ConfigurationInformationDescr	no
2010,0154 2010,015E	MaximumCollatedFilms Illumination	no
2010,015E	ReflectedAmbientLight	no
2010,0100	PrinterPixelSpacing	no no
2010,0500	ReferencedFilmSessionSequence	no
2010,0510	ReferencedImageBoxSequence	no
2010,0520	ReferencedBasicAnnotationBoxSeq	no
2020,0010	ImageBoxPosition	no
2020,0020	Polarity	no
2020,0030	RequestedImageSize	no
2020,0040	RequestedDecimate-CropBehavior	no
2020,0050	RequestedResolutionID	no
2020,00A0	RequestedImageSizeFlag	no
2020,00A2	DecimateCropResult	no
2020,0110	BasicGrayscaleImageSequence	no
2020,0111	BasicColorImageSequence	no
2020,0130	ReferencedImageOverlayBoxSequence	no
2020,0140	ReferencedVOILUTBoxSequence	no
2030,0010	AnnotationPosition	no
2030,0020 2040,0010	TextString ReferencedOverlayPlaneSequence	no
2040,0010	ReferencedOverlayPlaneGroups	no no
2040,0020	OverlayPixelDataSequence	no
2040,0060	OverlayMagnificationType	no
2040,0070	OverlaySmoothingType	no
2040,0072	OverlayOrImageMagnification	no
2040,0074	MagnifyToNumberOfColumns	no
2040,0080	OverlayForegroundDensity	no
2040,0082	OverlayBackgroundDensity	no
2040,0090	OverlayMode	no
2040,0100	ThresholdDensity	no
2040,0500	ReferencedImageBoxSequence	no
2050,0010	PresentationLUTSequence	no
2050,0020	PresentationLUTShape	no
2050,0500	ReferencedPresentationLUTSequence	no
2100,0010	PrintJobID	no
2100,0020	ExecutionStatus	no
2100,0030	ExecutionStatusInfo	no
2100,0040	CreationDate	no
2100,0050	CreationTime	no
2100,0070 2100,0140	Originator DestinationAE	no
2100,0140	OwnerID	no no
2100,0100	OWITCE ID	110

	ExilTool 13.24 Tag Names	•
2100,0170	NumberOfFilms	no
2100,0500	ReferencedPrintJobSequence	no
2110,0010	PrinterStatus	no
2110,0020 2110,0030	PrinterStatusInfo PrinterName	no
2110,0030	PrintQueueID	no no
2120,0010	QueueStatus	no
2120,0050	PrintJobDescriptionSequence	no
2120,0070	ReferencedPrintJobSequence	no
2130,0010	PrintManagementCapabilitiesSeq	no
2130,0015	PrinterCharacteristicsSequence	no
2130,0030	FilmBoxContentSequence	no
2130,0040 2130,0050	ImageBoxContentSequence AnnotationContentSequence	no
2130,0050	ImageOverlayBoxContentSequence	no no
2130,0080	PresentationLUTContentSequence	no
2130,00A0	ProposedStudySequence	no
2130,00C0	OriginalImageSequence	no
2200,0001	${\tt LabelFromInfoExtractedFromInstance}$	no
2200,0002	LabelText	no
2200,0003	LabelStyleSelection	no
2200,0004 2200,0005	MediaDisposition BarcodeValue	no
2200,0005	BarcodeSymbology	no no
2200,0007	AllowMediaSplitting	no
2200,0008	IncludeNonDICOMObjects	no
2200,0009	IncludeDisplayApplication	no
2200,000A	SaveCompInstancesAfterMediaCreate	no
2200,000B	TotalNumberMediaPiecesCreated	no
2200,000C	RequestedMediaApplicationProfile	no
2200,000D 2200,000E	ReferencedStorageMediaSequence FailureAttributes	no
2200,000E 2200,000F	AllowLossyCompression	no no
2200,0001	RequestPriority	no
3002,0002	RTImageLabel	no
3002,0003	RTImageName	no
3002,0004	RTImageDescription	no
3002,000A	ReportedValuesOrigin	no
3002,000C	RTImagePlane	no
3002,000D 3002,000E	XRayImageReceptorTranslation XRayImageReceptorAngle	no
3002,000E 3002,0010	RTImageOrientation	no no
3002,0011	ImagePlanePixelSpacing	no
3002,0012	RTImagePosition	no
3002,0020	RadiationMachineName	no
3002,0022	RadiationMachineSAD	no
3002,0024	RadiationMachineSSD	no
3002,0026	RTImageSID	no
3002,0028 3002,0029	SourceToReferenceObjectDistance FractionNumber	no
3002,0029	ExposureSequence	no no
3002,0030	MetersetExposure	no
3002,0034	DiaphragmPosition	no
3002,0040	FluenceMapSequence	no
3002,0041	FluenceDataSource	no
3002,0042	FluenceDataScale	no
3002,0051	FluenceMode	no
3002,0052	FluenceModeID	no
3004,0001 3004,0002	DVHType DoseUnits	no no
3004,0002	DoseType	no
3004,0006	DoseComment	no
3004,0008	NormalizationPoint	no
3004,000A	DoseSummationType	no
3004,000C	GridFrameOffsetVector	no
3004,000E	DoseGridScaling	no
3004,0010	RTDoseROISequence	no
3004,0012 3004,0014	DoseValue TissueHeterogeneityCorrection	no
3004,0014	DVHNormalizationPoint	no no
2001,0010	- ,, OI GII DIII OIII	-10

	ExilTool 13.24 Tag Names	•
3004,0042	DVHNormalizationDoseValue	no
3004,0050	DVHSequence	no
3004,0052	DVHDoseScaling	no
3004,0054	DVHVolumeUnits	no
3004,0056	DVHNumberOfBins	no
3004,0058	DVHData	no
3004,0060 3004,0062	DVHReferencedROISequence DVHROIContributionType	no
3004,0002	DVHMinimumDose	no no
3004,0072	DVHMaximumDose	no
3004,0074	DVHMeanDose	no
3006,0002	StructureSetLabel	no
3006,0004	StructureSetName	no
3006,0006	StructureSetDescription	no
3006,0008	StructureSetDate	no
3006,0009	StructureSetTime	no
3006,0010	ReferencedFrameOfReferenceSequence	no
3006,0012	RTReferencedStudySequence	no
3006,0014	RTReferencedSeriesSequence	no
3006,0016	ContourImageSequence	no
3006,0020 3006,0022	StructureSetROISequence ROINumber	no
3006,0022	ReferencedFrameOfReferenceUID	no no
3006,0021	ROIName	no
3006,0028	ROIDescription	no
3006,002A	ROIDisplayColor	no
3006,002C	ROIVolume	no
3006,0030	RTRelatedROISequence	no
3006,0033	RTROIRelationship	no
3006,0036	ROIGenerationAlgorithm	no
3006,0038	ROIGenerationDescription	no
3006,0039	ROIContourSequence	no
3006,0040	ContourSequence	no
3006,0042 3006,0044	ContourGeometricType ContourSlabThickness	no
3006,0044	ContourOffsetVector	no no
3006,0045	NumberOfContourPoints	no
3006,0048	ContourNumber	no
3006,0049	AttachedContours	no
3006,0050	ContourData	no
3006,0080	RTROIObservationsSequence	no
3006,0082	ObservationNumber	no
3006,0084	ReferencedROINumber	no
3006,0085	ROIObservationLabel	no
3006,0086	RTROIIdentificationCodeSequence	no
3006,0088	ROIObservationDescription	no
3006,00A0 3006,00A4	RelatedRTROIObservationsSequence	no
3006,00A4 3006,00A6	RTROIInterpretedType ROIInterpreter	no no
3006,00A0	ROIPhysicalPropertiesSequence	no
3006,00B2	ROIPhysicalProperty	no
3006,00B4	ROIPhysicalPropertyValue	no
3006,00B6	ROIElementalCompositionSequence	no
3006,00B7	ROIElementalCompAtomicNumber	no
3006,00B8	${\tt ROIElementalCompAtomicMassFraction}$	no
3006,00C0	FrameOfReferenceRelationshipSeq	no
3006,00C2	RelatedFrameOfReferenceUID	no
3006,00C4	FrameOfReferenceTransformType	no
3006,0006	FrameOfReferenceTransformMatrix	no
3006,00C8	FrameOfReferenceTransformComment	no
3008,0010 3008,0012	MeasuredDoseReferenceSequence MeasuredDoseDescription	no
3008,0012	MeasuredDoseDescription MeasuredDoseType	no no
3008,0014	MeasuredDoseValue	no
3008,0020	TreatmentSessionBeamSequence	no
3008,0021	TreatmentSessionIonBeamSequence	no
3008,0022	CurrentFractionNumber	no
3008,0024	TreatmentControlPointDate	no
3008,0025	TreatmentControlPointTime	no
3008,002A	TreatmentTerminationStatus	no

3008,002B	TreatmentTerminationCode	no
3008,002C	TreatmentVerificationStatus	no
3008,0030	ReferencedTreatmentRecordSequence	no
3008,0032	SpecifiedPrimaryMeterset	no
3008,0033	SpecifiedSecondaryMeterset	no
3008,0036	DeliveredPrimaryMeterset	no
3008,0037	DeliveredSecondaryMeterset	no
3008,003A	SpecifiedTreatmentTime	no
3008,003B	DeliveredTreatmentTime	no
3008,0040	ControlPointDeliverySequence	no
3008,0041	IonControlPointDeliverySequence	no
3008,0042	SpecifiedMeterset	no
3008,0044	DeliveredMeterset	no
3008,0045	MetersetRateSet	no
3008,0046	MetersetRateDelivered	no
3008,0047	ScanSpotMetersetsDelivered	no
3008,0048	DoseRateDelivered	no
3008,0050	TreatmentSummaryCalcDoseRefSeq	no
3008,0052	CumulativeDoseToDoseReference	no
3008,0054	FirstTreatmentDate	no
3008,0056	MostRecentTreatmentDate	no
3008,005A	NumberOfFractionsDelivered	no
3008,0060	OverrideSequence	no
3008,0061	ParameterSequencePointer	no
3008,0062	OverrideParameterPointer	no
3008,0063	ParameterItemIndex	no
3008,0064	MeasuredDoseReferenceNumber	no
3008,0065	ParameterPointer	no
3008,0066	OverrideReason	no
3008,0068	CorrectedParameterSequence	no
3008,006A	CorrectionValue	no
3008,0070	CalculatedDoseReferenceSequence	no
3008,0072 3008,0074	CalculatedDoseReferenceNumber	no
	CalculatedDoseReferenceDescription CalculatedDoseReferenceDoseValue	no
3008,0076	StartMeterset	no
3008,0078 3008,007A	EndMeterset	no
3008,007A 3008,0080	ReferencedMeasuredDoseReferenceSeq	no no
3008,0080	ReferencedMeasuredDoseReferenceNum	
3008,0082	ReferencedCalculatedDoseRefSeq	no
3008,0090	ReferencedCalculatedDoseRefNumber	no
3008,00A0	BeamLimitingDeviceLeafPairsSeq	no
3008,00R0	RecordedWedgeSequence	no
3008,00C0	RecordedCompensatorSequence	no
3008,00D0	RecordedBlockSequence	no
3008,00E0	TreatmentSummaryMeasuredDoseRefSeq	no
3008,00F0	RecordedSnoutSequence	no
3008,00F2	RecordedRangeShifterSequence	no
3008,00F4	RecordedLateralSpreadingDeviceSeq	no
3008,00F6	RecordedRangeModulatorSequence	no
3008,0100	RecordedSourceSequence	no
3008,0105	SourceSerialNumber	no
3008,0110	TreatmentSessionAppSetupSeq	no
3008,0116	ApplicationSetupCheck	no
3008,0120	RecordedBrachyAccessoryDeviceSeq	no
3008,0122	ReferencedBrachyAccessoryDeviceNum	no
3008,0130	RecordedChannelSequence	no
3008,0132	SpecifiedChannelTotalTime	no
3008,0134	DeliveredChannelTotalTime	no
3008,0136	SpecifiedNumberOfPulses	no
3008,0138	DeliveredNumberOfPulses	no
3008,013A	SpecifiedPulseRepetitionInterval	no
3008,013C	DeliveredPulseRepetitionInterval	no
3008,0140	RecordedSourceApplicatorSequence	no
3008,0142	ReferencedSourceApplicatorNumber	no
3008,0150	RecordedChannelShieldSequence	no
3008,0152	ReferencedChannelShieldNumber	no
3008,0160	BrachyControlPointDeliveredSeq	no
3008,0162	SafePositionExitDate	no
3008,0164	SafePositionExitTime	no

	EXIITOOI 13.24 Tag Names -	-
3008,0166	SafePositionReturnDate	no
3008,0168	SafePositionReturnTime	no
3008,0200	CurrentTreatmentStatus	no
3008,0202	TreatmentStatusComment	no
3008,0220	FractionGroupSummarySequence	no
3008,0223	ReferencedFractionNumber	no
3008,0224	FractionGroupType	no
3008,0230 3008,0240	BeamStopperPosition FractionStatusSummarySequence	no
3008,0240	TreatmentDate	no no
3008,0250	TreatmentTime	no
300A,0002	RTPlanLabel	no
300A,0003	RTPlanName	no
300A,0004	RTPlanDescription	no
300A,0006	RTPlanDate	no
300A,0007	RTPlanTime	no
300A,0009	TreatmentProtocols	no
300A,000A	PlanIntent	no
300A,000B	TreatmentSites	no
300A,000C	RTPlanGeometry	no
300A,000E	PrescriptionDescription	no
300A,0010	DoseReferenceSequence	no
300A,0012	DoseReferenceNumber	no
300A,0013	DoseReferenceUID	no
300A,0014	DoseReferenceStructureType	no
300A,0015	NominalBeamEnergyUnit	no
300A,0016 300A,0018	DoseReferenceDescription DoseReferencePointCoordinates	no
300A,0018 300A,001A	NominalPriorDose	no no
300A,001A	DoseReferenceType	no
300A,0020	ConstraintWeight	no
300A,0022	DeliveryWarningDose	no
300A,0023	DeliveryMaximumDose	no
300A,0025	TargetMinimumDose	no
300A,0026	TargetPrescriptionDose	no
300A,0027	TargetMaximumDose	no
300A,0028	TargetUnderdoseVolumeFraction	no
300A,002A	OrganAtRiskFullVolumeDose	no
300A,002B	OrganAtRiskLimitDose	no
300A,002C	OrganAtRiskMaximumDose	no
300A,002D	OrganAtRiskOverdoseVolumeFraction	no
300A,0040	ToleranceTableSequence	no
300A,0042 300A,0043	ToleranceTableNumber ToleranceTableLabel	no
300A,0043	GantryAngleTolerance	no
300A,0044	BeamLimitingDeviceAngleTolerance	no no
300A,0010	BeamLimitingDeviceToleranceSeq	no
300A,004A	BeamLimitingDevicePositionTol	no
300A,004B	SnoutPositionTolerance	no
300A,004C	PatientSupportAngleTolerance	no
300A,004E	TableTopEccentricAngleTolerance	no
300A,004F	TableTopPitchAngleTolerance	no
300A,0050	TableTopRollAngleTolerance	no
300A,0051	TableTopVerticalPositionTolerance	no
300A,0052	TableTopLongitudinalPositionTol	no
300A,0053	TableTopLateralPositionTolerance	no
300A,0055	RTPlanRelationship	no
300A,0070	FractionGroupSequence	no
300A,0071	FractionGroupNumber	no
300A,0072	FractionGroupDescription NumberOfFractionsPlanned	no
300A,0078 300A,0079	NumberFractionPatternDigitsPerDay	no
300A,0079 300A,007A	RepeatFractionCycleLength	no no
300A,007A	FractionPattern	no
300A,007B	NumberOfBeams	no
300A,0082	BeamDoseSpecificationPoint	no
300A,0084	BeamDose	no
300A,0086	BeamMeterset	no
300A,0088	BeamDosePointDepth	no
300A,0089	BeamDosePointEquivalentDepth	no

	ExilTool 13.24 Tag Names	-
300A,008A	BeamDosePointSSD	no
300A,00A0	NumberOfBrachyApplicationSetups	no
300A,00A2	BrachyAppSetupDoseSpecPoint	no
300A,00A4	BrachyApplicationSetupDose	no
300A,00B0	BeamSequence	no
300A,00B2	TreatmentMachineName	no
300A,00B3	PrimaryDosimeterUnit	no
300A,00B4	SourceAxisDistance	no
300A,00B6 300A,00B8	BeamLimitingDeviceSequence RTBeamLimitingDeviceType	no
300A,00B8	SourceToBeamLimitingDeviceDistance	no no
300A,00BA	IsocenterToBeamLimitingDeviceDist	no
300A,00BC	NumberOfLeafJawPairs	no
300A,00BE	LeafPositionBoundaries	no
300A,00C0	BeamNumber	no
300A,00C2	BeamName	no
300A,00C3	BeamDescription	no
300A,00C4	BeamType	no
300A,00C6	RadiationType	no
300A,00C7	HighDoseTechniqueType	no
300A,00C8	ReferenceImageNumber	no
300A,00CA	PlannedVerificationImageSequence	no
300A,00CC	ImagingDeviceSpecificAcqParams	no
300A,00CE	TreatmentDeliveryType	no
300A,00D0	NumberOfWedges	no
300A,00D1	WedgeSequence	no
300A,00D2	WedgeNumber	no
300A,00D3	WedgeType	no
300A,00D4	WedgeID	no
300A,00D5	WedgeAngle	no
300A,00D6	WedgeFactor	no
300A,00D7	TotalWedgeTrayWaterEquivThickness	no
300A,00D8	WedgeOrientation	no
300A,00D9	<pre>IsocenterToWedgeTrayDistance SourceToWedgeTrayDistance</pre>	no
300A,00DA 300A,00DB	WedgeThinEdgePosition	no
300A,00DB	BolusID	no
300A,00DC	BolusDescription	no no
300A,00E0	NumberOfCompensators	no
300A,00E1	MaterialID	no
300A,00E2	TotalCompensatorTrayFactor	no
300A,00E3	CompensatorSequence	no
300A,00E4	CompensatorNumber	no
300A,00E5	CompensatorID	no
300A,00E6	SourceToCompensatorTrayDistance	no
300A,00E7	CompensatorRows	no
300A,00E8	CompensatorColumns	no
300A,00E9	CompensatorPixelSpacing	no
300A,00EA	CompensatorPosition	no
300A,00EB	CompensatorTransmissionData	no
300A,00EC	CompensatorThicknessData	no
300A,00ED	NumberOfBoli	no
300A,00EE	CompensatorType	no
300A,00F0	NumberOfBlocks	no
300A,00F2	TotalBlockTrayFactor	no
300A,00F3	TotalBlockTrayWaterEquivThickness	no
300A,00F4	BlockSequence	no
300A,00F5	BlockTrayID	no
300A,00F6	SourceToBlockTrayDistance	no
300A,00F7	IsocenterToBlockTrayDistance	no
300A,00F8	BlockType	no
300A,00F9 300A,00FA	AccessoryCode BlockDivergence	no
300A,00FA	BlockMountingPosition	no no
300A,00FB	BlockNumber	no
300A,00FE	BlockName	no
300A,001E	BlockThickness	no
300A,0100	BlockTransmission	no
300A,0104	BlockNumberOfPoints	no
300A,0106	BlockData	no
,		•

	ExifTool 13.24 Tag Names	-
300A,0107	ApplicatorSequence	no
300A,0108	ApplicatorID	no
300A,0109	ApplicatorType	no
300A,010A	ApplicatorDescription	no
300A,010C	CumulativeDoseReferenceCoefficient	no
300A,010E	FinalCumulativeMetersetWeight	no
300A,0110	NumberOfControlPoints	no
300A,0111	ControlPointSequence	no
300A,0112	ControlPointIndex	no
300A,0114	NominalBeamEnergy	no
300A,0115	DoseRateSet	no
300A,0116	WedgePositionSequence	no
300A,0118 300A,011A	WedgePosition BeamLimitingDevicePositionSequence	no
300A,011A	LeafJawPositions	no no
300A,011E	GantryAngle	no
300A,011E	GantryRotationDirection	no
300A,0120	BeamLimitingDeviceAngle	no
300A,0121	BeamLimitingDeviceRotateDirection	no
300A,0122	PatientSupportAngle	no
300A,0123	PatientSupportRotationDirection	no
300A,0124	TableTopEccentricAxisDistance	no
300A,0125	TableTopEccentricAngle	no
300A,0126	TableTopEccentricRotateDirection	no
300A,0128	TableTopVerticalPosition	no
300A,0129	TableTopLongitudinalPosition	no
300A,012A	TableTopLateralPosition	no
300A,012C	IsocenterPosition	no
300A,012E	SurfaceEntryPoint	no
300A,0130	SourceToSurfaceDistance	no
300A,0134	CumulativeMetersetWeight	no
300A,0140	TableTopPitchAngle	no
300A,0142	TableTopPitchRotationDirection	no
300A,0144	TableTopRollAngle	no
300A,0146	TableTopRollRotationDirection	no
300A,0148	HeadFixationAngle	no
300A,014A	GantryPitchAngle	no
300A,014C	GantryPitchRotationDirection	no
300A,014E	GantryPitchAngleTolerance	no
300A,0180	PatientSetupSequence	no
300A,0182	PatientSetupNumber	no
300A,0183	PatientSetupLabel	no
300A,0184	PatientAdditionalPosition	no
300A,0190 300A,0192	FixationDeviceSequence	no
300A,0192 300A,0194	FixationDeviceType FixationDeviceLabel	no
300A,0194 300A,0196	FixationDeviceDescription	no
300A,0190	FixationDevicePosition	no
300A,0190	FixationDevicePitchAngle	no no
300A,019A	FixationDeviceRollAngle	no
300A,01A0	ShieldingDeviceSequence	no
300A,01A2	ShieldingDeviceType	no
300A,01A4	ShieldingDeviceLabel	no
300A,01A6	ShieldingDeviceDescription	no
300A,01A8	ShieldingDevicePosition	no
300A,01B0	SetupTechnique	no
300A,01B2	SetupTechniqueDescription	no
300A,01B4	SetupDeviceSequence	no
300A,01B6	SetupDeviceType	no
300A,01B8	SetupDeviceLabel	no
300A,01BA	SetupDeviceDescription	no
300A,01BC	SetupDeviceParameter	no
300A,01D0	SetupReferenceDescription	no
300A,01D2	TableTopVerticalSetupDisplacement	no
300A,01D4	TableTopLongitudinalSetupDisplace	no
300A,01D6	TableTopLateralSetupDisplacement	no
300A,0200	BrachyTreatmentTechnique	no
300A,0202	BrachyTreatmentType	no
300A,0206	TreatmentMachineSequence	no
300A,0210	SourceSequence	no

no

300A,0212 SourceNumber

300A,0212	Sourcenumber	110
300A,0214	SourceType	no
300A,0216	SourceManufacturer	no
300A,0218	ActiveSourceDiameter	no
300A,021A	ActiveSourceLength	no
300A,0222	SourceEncapsulationNomThickness	no
300A,0224	SourceEncapsulationNomTransmission	no
300A,0226	SourceIsotopeName	no
300A,0228	SourceIsotopeHalfLife	no
300A,0229	SourceStrengthUnits	no
300A,022A	ReferenceAirKermaRate	no
300A,022B	SourceStrength	no
300A,022C	SourceStrengthReferenceDate	no
300A,022E	SourceStrengthReferenceTime	no
300A,0230	ApplicationSetupSequence	no
300A,0232	ApplicationSetupType	no
300A,0234	ApplicationSetupNumber	no
300A,0236	ApplicationSetupName	no
300A,0238	ApplicationSetupManufacturer	no
300A,0240	TemplateNumber	no
300A,0242	TemplateType	no
300A,0244		
	TemplateName	no
300A,0250	TotalReferenceAirKerma	no
300A,0260	BrachyAccessoryDeviceSequence	no
300A,0262	BrachyAccessoryDeviceNumber	no
300A,0263	BrachyAccessoryDeviceID	no
300A,0264	BrachyAccessoryDeviceType	no
		_
300A,0266	BrachyAccessoryDeviceName	no
300A,026A	BrachyAccessoryDeviceNomThickness	no
300A,026C	BrachyAccessoryDevNomTransmission	no
300A,0280	ChannelSequence	no
300A,0282	ChannelNumber	
		no
300A,0284	ChannelLength	no
300A,0286	ChannelTotalTime	no
300A,0288	SourceMovementType	no
300A,028A	NumberOfPulses	no
300A,028C	PulseRepetitionInterval	no
300A,0290	SourceApplicatorNumber	no
300A,0291	SourceApplicatorID	no
300A,0292	SourceApplicatorType	no
300A,0294	SourceApplicatorName	no
300A,0296	SourceApplicatorLength	no
300A,0298	SourceApplicatorManufacturer	no
300A,029C	SourceApplicatorWallNomThickness	no
300A,029E	SourceApplicatorWallNomTrans	no
300A,02A0	SourceApplicatorStepSize	no
300A,02A2	TransferTubeNumber	no
300A,02A4	TransferTubeLength	no
300A,02B0	ChannelShieldSequence	no
300A,02B2	ChannelShieldNumber	no
300A,02B3	ChannelShieldID	no
300A,02B4	ChannelShieldName	no
300A,02B8	ChannelShieldNominalThickness	
		no
300A,02BA	ChannelShieldNominalTransmission	no
300A,02C8	FinalCumulativeTimeWeight	no
300A,02D0	BrachyControlPointSequence	no
300A,02D2		no
	ControlPointRelativePosition	
2007 0204	ControlPointRelativePosition	
300A,02D4	ControlPoint3DPosition	no
300A,02D6	ControlPoint3DPosition CumulativeTimeWeight	
	ControlPoint3DPosition	no
300A,02D6 300A,02E0	ControlPoint3DPosition CumulativeTimeWeight CompensatorDivergence	no no
300A,02D6 300A,02E0 300A,02E1	ControlPoint3DPosition CumulativeTimeWeight CompensatorDivergence CompensatorMountingPosition	no no no no
300A,02D6 300A,02E0 300A,02E1 300A,02E2	ControlPoint3DPosition CumulativeTimeWeight CompensatorDivergence CompensatorMountingPosition SourceToCompensatorDistance	no no no no no
300A,02D6 300A,02E0 300A,02E1 300A,02E2 300A,02E3	ControlPoint3DPosition CumulativeTimeWeight CompensatorDivergence CompensatorMountingPosition SourceToCompensatorDistance TotalCompTrayWaterEquivThickness	no no no no no no
300A,02D6 300A,02E0 300A,02E1 300A,02E2 300A,02E3 300A,02E4	ControlPoint3DPosition CumulativeTimeWeight CompensatorDivergence CompensatorMountingPosition SourceToCompensatorDistance TotalCompTrayWaterEquivThickness IsocenterToCompensatorTrayDistance	no no no no no
300A,02D6 300A,02E0 300A,02E1 300A,02E2 300A,02E3	ControlPoint3DPosition CumulativeTimeWeight CompensatorDivergence CompensatorMountingPosition SourceToCompensatorDistance TotalCompTrayWaterEquivThickness	no no no no no no
300A,02D6 300A,02E0 300A,02E1 300A,02E2 300A,02E3 300A,02E4 300A,02E5	ControlPoint3DPosition CumulativeTimeWeight CompensatorDivergence CompensatorMountingPosition SourceToCompensatorDistance TotalCompTrayWaterEquivThickness IsocenterToCompensatorTrayDistance CompensatorColumnOffset	no no no no no no
300A,02D6 300A,02E0 300A,02E1 300A,02E2 300A,02E3 300A,02E4 300A,02E5 300A,02E6	ControlPoint3DPosition CumulativeTimeWeight CompensatorDivergence CompensatorMountingPosition SourceToCompensatorDistance TotalCompTrayWaterEquivThickness IsocenterToCompensatorTrayDistance CompensatorColumnOffset IsocenterToCompensatorDistances	no
300A,02D6 300A,02E0 300A,02E1 300A,02E2 300A,02E3 300A,02E4 300A,02E5 300A,02E6 300A,02E7	ControlPoint3DPosition CumulativeTimeWeight CompensatorDivergence CompensatorMountingPosition SourceToCompensatorDistance TotalCompTrayWaterEquivThickness IsocenterToCompensatorTrayDistance CompensatorColumnOffset IsocenterToCompensatorDistances CompensatorRelStoppingPowerRatio	no
300A,02D6 300A,02E0 300A,02E1 300A,02E2 300A,02E3 300A,02E4 300A,02E5 300A,02E6 300A,02E7 300A,02E8	ControlPoint3DPosition CumulativeTimeWeight CompensatorDivergence CompensatorMountingPosition SourceToCompensatorDistance TotalCompTrayWaterEquivThickness IsocenterToCompensatorTrayDistance CompensatorColumnOffset IsocenterToCompensatorDistances CompensatorRelStoppingPowerRatio CompensatorMillingToolDiameter	no n
300A,02D6 300A,02E0 300A,02E1 300A,02E2 300A,02E3 300A,02E4 300A,02E5 300A,02E6 300A,02E7 300A,02E8 300A,02E8	ControlPoint3DPosition CumulativeTimeWeight CompensatorDivergence CompensatorMountingPosition SourceToCompensatorDistance TotalCompTrayWaterEquivThickness IsocenterToCompensatorTrayDistance CompensatorColumnOffset IsocenterToCompensatorDistances CompensatorRelStoppingPowerRatio CompensatorMillingToolDiameter IonRangeCompensatorSequence	no
300A,02D6 300A,02E0 300A,02E1 300A,02E2 300A,02E3 300A,02E4 300A,02E5 300A,02E6 300A,02E7 300A,02E8	ControlPoint3DPosition CumulativeTimeWeight CompensatorDivergence CompensatorMountingPosition SourceToCompensatorDistance TotalCompTrayWaterEquivThickness IsocenterToCompensatorTrayDistance CompensatorColumnOffset IsocenterToCompensatorDistances CompensatorRelStoppingPowerRatio CompensatorMillingToolDiameter	no n

300A,0302         RadiationAmasnumber         no           300A,0306         RadiationChargeState         no           300A,0308         ScanMode         no           300A,0308         VirtualSourceAxisDistances         no           300A,030C         SnoutDeosition         no           300A,030D         SnoutDosition         no           300A,031D         NumberOfRangeShifters         no           300A,0312         NumberOfRangeShifters         no           300A,0314         RangeShifterSequence         no           300A,0318         RangeShifterType         no           300A,0318         RangeShifterType         no           300A,0320         RangeShifterDescription         no           300A,0321         LateralSpreadingDeviceSequence         no           300A,0322         LateralSpreadingDeviceSumber         no           300A,0333         LateralSpreadingDeviceType         no           300A,0334         LateralSpreadingDeviceType         no           300A,0334         LateralSpreadingDeviceType         no           300A,0334         LateralSpreadingDeviceType         no           300A,0340         NumberofRangeModulators         no           300A,0342 <t< th=""></t<>
300A,0306         RadiationChargeState         no           300A,030A         VirtualSourceAxisDistances         no           300A,030C         SnoutSequence         no           300A,030F         SnoutDouble         no           300A,030F         SnoutID         no           300A,0312         NumberOfRangeShifterS         no           300A,0316         RangeShifterSequence         no           300A,0316         RangeShifterTD         no           300A,0318         RangeShifterTDescription         no           300A,0322         RangeShifterEDescription         no           300A,0330         NumberOfLateralSpreadingDeviceSequence         no           300A,0331         LateralSpreadingDeviceSequence         no           300A,0332         LateralSpreadingDeviceID         no           300A,0334         LateralSpreadingDeviceID         no           300A,0335         LateralSpreadingDevicePype         no           300A,0336         LateralSpreadingDevicePype         no           300A,0336         LateralSpreadingDevicePype         no           300A,0336         LateralSpreadingDevicePype         no           300A,0340         RangeModulatorSequence         no           300A,
300A,030A         VirtualSourceAxisDistances         no           300A,030C         SnoutSequence         no           300A,030D         SnoutDeosition         no           300A,030D         SnoutDo         no           300A,031D         NumberOfRangeShifters         no           300A,0312         NumberOfRangeShifterS         no           300A,0314         RangeShifterSequence         no           300A,0318         RangeShifterTD         no           300A,0318         RangeShifterTbeorription         no           300A,0320         RangeShifterDescription         no           300A,0321         LateralSpreadingDeviceSequence         no           300A,0332         LateralSpreadingDeviceInmber         no           300A,0334         LateralSpreadingDeviceType         no           300A,0336         LateralSpreadingDeviceType         no           300A,0331         LateralSpreadingDeviceType         no           300A,0334         LateralSpreadingDeviceType         no           300A,0334         LateralSpreadingDeviceType         no           300A,0340         NumberofRangeModulators         no           300A,0342         RangeModulatorType         no           300A,0344
300A, 030A         VirtualSourceAxisDistances         no           300A, 030D         SnoutSequence         no           300A, 030F         SnoutID         no           300A, 031E         NumberOfRangeShifters         no           300A, 0312         RangeShifterSequence         no           300A, 0316         RangeShifterID         no           300A, 0312         RangeShifterID         no           300A, 0320         RangeShifterDescription         no           300A, 0321         RangeShifterDescription         no           300A, 0332         LateralSpreadingDeviceSequence         no           300A, 0334         LateralSpreadingDeviceID         no           300A, 0334         LateralSpreadingDeviceType         no           300A, 0334         LateralSpreadingDeviceDescription         no           300A, 0334         LateralSpreadingDeviceDescription         no           300A, 0334         LateralSpreadingDeviceDescription         no           300A, 0334         LateralSpreadingDeviceDescription         no           300A, 0340         NumberOfRangeModulatorS         no           300A, 0341         RangeModulatorNumber         no           300A, 0342         RangeModulatorType         no     <
300A,030C         SnoutSequence         no           300A,030F         SnoutDosition         no           300A,031F         SnoutDosition         no           300A,031L         NumberOfRangeShifterS         no           300A,0312         RangeShifterSequence         no           300A,0316         RangeShifterTD         no           300A,0318         RangeShifterTDP         no           300A,0320         RangeShifterTDP         no           300A,0321         RangeShifterTDP         no           300A,0332         RangeShifterTSpe         no           300A,0332         LateralSpreadingDeviceSequence         no           300A,0334         LateralSpreadingDeviceTD         no           300A,0336         LateralSpreadingDeviceDescription         no           300A,0336         LateralSpreadingDeviceDescription         no           300A,0334         LateralSpreadingDeviceDescription         no           300A,0334         LateralSpreadingDeviceDescription         no           300A,0334         RangeModulatorSequence         no           300A,0342         RangeModulatorSequence         no           300A,0344         RangeModulatorType         no           300A,0345         <
300A,030D         SnoutPosition         no           300A,031E         NumberOfRangeShifters         no           300A,0314         RangeShifterSequence         no           300A,0318         RangeShifterID         no           300A,0318         RangeShifterID         no           300A,0320         RangeShifterType         no           300A,0322         RangeShifterDescription         no           300A,0332         LateralSpreadingDeviceSequence         no           300A,0334         LateralSpreadingDeviceNumber         no           300A,0336         LateralSpreadingDeviceType         no           300A,0336         LateralSpreadingDeviceDescription         no           300A,0336         LateralSpreadingDeviceDescription         no           300A,0336         LateralSpreadingDeviceDescription         no           300A,0336         LateralSpreadingDeviceDescription         no           300A,0337         LateralSpreadingDeviceDescription         no           300A,0342         RangeModulatorSequence         no           300A,0344         RangeModulatorID         no           300A,0348         RangeModulatorType         no           300A,0346         RangeModulatorType         no
300A,030F         SnoutID         no           300A,0312         NumberOfRangeShifterS         no           300A,0316         RangeShifterSequence         no           300A,0318         RangeShifterID         no           300A,0320         RangeShifterType         no           300A,0321         RangeShifterTDescription         no           300A,0330         NumberOfLateralSpreadingDeviceSequence         no           300A,0334         LateralSpreadingDeviceSequence         no           300A,0336         LateralSpreadingDeviceType         no           300A,0336         LateralSpreadingDeviceType         no           300A,0336         LateralSpreadingDevWaterEquivThick         no           300A,0336         LateralSpreadingDevWaterEquivThick         no           300A,0340         NumberOfRangeModulatorS         no           300A,0340         NumberOfRangeModulatorS         no           300A,0341         RangeModulatorSequence         no           300A,0342         RangeModulatorType         no           300A,0344         RangeModulatorDescription         no           300A,0345         PatientSupportModulationID         no           300A,0346         RangeModulatorDescription         no </td
300A,0312NumberOfRangeShiftersno300A,0316RangeShifterSequenceno300A,0316RangeShifterInDno300A,0320RangeShifterIDno300A,0320RangeShifterTypeno300A,0330NumberOfLateralSpreadingDevicesno300A,0331LateralSpreadingDeviceSequenceno300A,0332LateralSpreadingDeviceIDno300A,0333LateralSpreadingDeviceTypeno300A,0334LateralSpreadingDeviceDescriptionno300A,0335LateralSpreadingDeviceDescriptionno300A,0336LateralSpreadingDevideDescriptionno300A,0337LateralSpreadingDevWaterEquivThickno300A,0340NumberOfRangeModulatorsno300A,0341RangeModulatorSequenceno300A,0342RangeModulatorSequenceno300A,0343RangeModulatorTypeno300A,0344RangeModulatorTypeno300A,0345RangeModulatorTypeno300A,0346RangeModulatorTypeno300A,0347PatientSupportTypeno300A,0350PatientSupportTypeno300A,0351PatientSupportTypeno300A,0352PatientSupportTDno300A,0354FixationLightPolarAngleno300A,0355FixationLightPolarAngleno300A,0360RangeShifterSettingno300A,0361RangeShifterSettingno300A,0362RangeModulatorSettingsno300A,0363Rang
300A,0314 RangeShifterSequence no 300A,0318 RangeShifterID no 300A,0320 RangeShifterID no 300A,0320 RangeShifterType no 300A,0322 RangeShifterType no 300A,0322 RangeShifterDescription no 300A,0332 LateralSpreadingDeviceSequence no 300A,0334 LateralSpreadingDeviceSequence no 300A,0336 LateralSpreadingDeviceID no 300A,0338 LateralSpreadingDeviceID no 300A,0338 LateralSpreadingDeviceDescription no 300A,0330 LateralSpreadingDeviceDescription no 300A,0331 LateralSpreadingDeviceDescription no 300A,0332 LateralSpreadingDeviceDescription no 300A,0334 LateralSpreadingDeviceDescription no 300A,0336 RangeModulatorSequence no 300A,0340 NumberOfRangeModulators no 300A,0341 RangeModulatorSequence no 300A,0342 RangeModulatorNumber no 300A,0343 RangeModulatorID no 300A,0346 RangeModulatorID no 300A,0348 RangeModulatorType no 300A,0340 RangeModulatorDescription no 300A,0340 PatientSupportType no 300A,0350 PatientSupportType no 300A,0351 PatientSupportType no 300A,0352 PatientSupportType no 300A,0354 PatientSupportType no 300A,0355 FixationLightAzimuthalAngle no 300A,0356 FixationLightPolarAngle no 300A,0358 MetersetRate no 300A,0360 RangeShifterSetting no 300A,0361 IsocenterToRangeShifterDistance no 300A,0362 RangeShifterSetting no 300A,0363 RangeShifterSetting no 300A,0364 IsocenterToRangeShifterDistance no 300A,0370 LateralSpreadingDeviceSetting no 300A,0371 LateralSpreadingDeviceSetting no 300A,0372 RangeModulatorSettingSsequence no 300A,0373 RangeModulatorGatingStartValue no 300A,0384 RangeModulatorGatingStartValue no 300A,0385 RangeModulatorGatingStartValue no 300A,0386 RangeModulatorGatingStartValue no 300A,0387 ScanSpotPositionMap no 300A,0398 ScanSpotPositionMap no 300A,0398 ScanSpotPositionMap no 300A,0399 NumberOfPaintings no 300A,0390 NumberOfPaintings no 300A,0391 IonToleranceTableSequence no 300A,0393 IonToleranceTableSequence no 300A,0394 IonBeamEimitingDeviceSequence no 300A,0395 IonBeamSequence no 300A,0396 IonBeamSequence no 300A,0397 IonBeamSequence no 300A,0398 IonControlPointSequence no 300A,0390 Scatpoint n
300A,0316 RangeShifterNumber no 300A,0318 RangeShifterID no 300A,0320 RangeShifterType no 300A,0320 RangeShifterType no 300A,0332 RangeShifterDescription no 300A,0330 NumberOfLateralSpreadingDeviceSequence no 300A,0334 LateralSpreadingDeviceSequence no 300A,0336 LateralSpreadingDeviceID no 300A,0336 LateralSpreadingDeviceID no 300A,0336 LateralSpreadingDeviceID no 300A,0336 LateralSpreadingDeviceDescription no 300A,0330 LateralSpreadingDevWaterEquivThick no 300A,0340 NumberOfRangeModulators no 300A,0340 RangeModulatorSequence no 300A,0344 RangeModulatorSequence no 300A,0344 RangeModulatorSequence no 300A,0346 RangeModulatorID no 300A,0348 RangeModulatorID no 300A,0348 RangeModulatorID no 300A,0348 RangeModulatorID no 300A,0340 BeamCurrentModulationID no 300A,0350 PatientSupportID no 300A,0350 PatientSupportID no 300A,0354 PatientSupportID no 300A,0356 FixationLightPolarAngle no 300A,0356 FixationLightPolarAngle no 300A,0356 RangeShifterSetting no 300A,0356 RangeShifterSetting no 300A,0360 RangeShifterSetting no 300A,0370 LateralSpreadingDeviceSetting no 300A,0370 LateralSpreadingDeviceSetting no 300A,0370 RangeModulatorGatingStartValue no 300A,0380 RangeModulatorGatingStartValue no 300A,0381 Formal Device Setting no 300A,0382 RangeModulatorGatingStartValue no 300A,0384 RangeModulatorGatingStartValue no 300A,0389 ScanSpotTuneID no 300A,0380 ScanSpotTuneID no 300A,0380 ScanSpotTuneID no 300A,0381 Formal DeviceSetting no 300A,0382 RangeModulatorGatingStartValue no 300A,0384 InoBeamLimitingDeviceSequence no 300A,0386 InoBockSequence no 300A,0386 InoBockSequence no 300A,0380 SetupImageSequen
300A,0318 RangeShifterID no 300A,0322 RangeShifterType no 300A,0322 RangeShifterDescription no 300A,0323 NumberOfLateralSpreadingDevices no 300A,0334 LateralSpreadingDeviceSequence no 300A,0336 LateralSpreadingDeviceNumber no 300A,0336 LateralSpreadingDeviceType no 300A,0336 LateralSpreadingDeviceDescription no 300A,0336 LateralSpreadingDeviceDescription no 300A,0336 LateralSpreadingDeviceDescription no 300A,0336 LateralSpreadingDevWaterEquivThick no 300A,0336 RangeModulatorSequence no 300A,0340 NumberOfRangeModulators no 300A,0341 RangeModulatorSequence no 300A,0342 RangeModulatorID no 300A,0348 RangeModulatorID no 300A,0348 RangeModulatorType no 300A,0340 RangeModulatorDescription no 300A,0350 PatientSupportType no 300A,0350 PatientSupportType no 300A,0351 PatientSupportType no 300A,0352 PatientSupportType no 300A,0353 FixationLightAzimuthalAngle no 300A,0356 FixationLightPolarAngle no 300A,0356 RangeShifterSetting no 300A,0366 RangeShifterSetting no 300A,0366 RangeShifterSetting no 300A,0367 LateralSpreadingDeviceSettingSeq no 300A,0368 RangeShifterWaterEquivThickness no 300A,0360 RangeShifterWaterEquivThickness no 300A,0361 IsocenterToRangeShifterDistance no 300A,0362 RangeModulatorGatingStartValue no 300A,0370 LateralSpreadingDeviceSetting no 300A,0381 RangeModulatorGatingStartValue no 300A,0382 RangeModulatorGatingStartValue no 300A,0384 RangeModulatorGatingStartValue no 300A,0385 ScanSpotTuneID no 300A,0396 ScanSpotTuneID no 300A,0398 ScanSpotTuneID no 300A,0398 ScanSpotPositions no 300A,0398 ScanSpotPositionsequence no 300A,030A IonToleranceTableSequence no 300A,030A IonBeamLimitingDeviceSequence no 300A,030A IonBeamLimitingDeviceSequence no 300A,030A IonBeamLimitingDeviceSequence no 300A,030A IonBeamLimitingDeviceSequence no 300A,030A IonBeamCequence no 300A,030A IonWedgeSequence no 300A,0402 SetupImageSequence no
300A,0320 RangeShifterType 300A,0322 RangeShifterDescription 300A,0322 LateralSpreadingDeviceSequence 300A,0334 LateralSpreadingDeviceNumber 300A,0336 LateralSpreadingDeviceNumber 300A,0338 LateralSpreadingDeviceDescription 300A,0338 LateralSpreadingDeviceDescription 300A,0338 LateralSpreadingDeviceDescription 300A,0330 NumberOfRangeModulatorS 300A,0340 NumberOfRangeModulatorS 300A,0341 RangeModulatorSequence 300A,0342 RangeModulatorSequence 300A,0344 RangeModulatorID 300A,0348 RangeModulatorType 300A,0348 RangeModulatorType 300A,0348 RangeModulatorType 300A,0340 RangeModulatorType 300A,0351 PatientSupportType 300A,0352 PatientSupportID 300A,0354 PatientSupportID 300A,0355 FixationLightPolarAngle 300A,0356 FixationLightPolarAngle 300A,0357 MetersetRate 300A,0360 RangeShifterSetting no 300A,0361 SocenterToRangeShifterDistance 300A,0362 RangeShifterWaterEquivThickness 300A,0370 LateralSpreadingDeviceSetting no 300A,0370 LateralSpreadingDeviceSetting no 300A,0370 RangeModulatorSetting no 300A,0370 RangeShifterWaterEquivThickness 300A,0370 RangeShifterWaterEquivThickness 300A,0370 RangeShifterWaterEquivThickness 300A,0370 RangeShifterWaterEquivThickness 300A,0370 RangeShifterWaterEquivThickness 300A,0370 ScenterToRangeShifterDistance 300A,0370 RangeModulatorGatingStartValue 300A,0380 RangeModulatorGatingStartValue 300A,0381 SocenterToRangeModulatorDistance 300A,0382 RangeModulatorGatingStartValue 300A,0383 ScanSpotPositionMap 300A,0398 ScanSpotPositionMap 300A,0398 ScanSpotPositionMap 300A,0398 ScanSpotPositionMap 300A,0398 ScanSpotPositionMap 300A,0398 ScanSpotPositionS 300A,0398 ScanSpotPositionMap 30
300A,0322 RangeShifterDescription
300A,0330NumberOfLateralSpreadingDevicesno300A,0332LateralSpreadingDeviceSequenceno300A,0334LateralSpreadingDeviceIDno300A,0336LateralSpreadingDeviceTypeno300A,0338LateralSpreadingDeviceDescriptionno300A,0330LateralSpreadingDevWaterEquivThickno300A,0340NumberOfRangeModulatorsno300A,0341RangeModulatorSequenceno300A,0342RangeModulatorIDno300A,0343RangeModulatorTypeno300A,0344RangeModulatorTypeno300A,0345RangeModulatorTypeno300A,0346RangeModulatorDescriptionno300A,0351PatientSupportTypeno300A,0352PatientSupportIDno300A,0353PatientSupportAccessoryCodeno300A,0354PatientSupportAccessoryCodeno300A,0355FixationLightPolarAngleno300A,0356FixationLightPolarAngleno300A,0357RangeShifterSettingsSequenceno300A,0360RangeShifterSettingno300A,0361RangeShifterWaterEquivThicknessno300A,0372LateralSpreadingDeviceSettingno300A,0374LateralSpreadingDeviceSettingno300A,0372LateralSpreadingDeviceSettingno300A,0384RangeModulatorGatingStapValueno300A,0384RangeModulatorGatingStapValueno300A,0384RangeModulatorGatingStapValueno300A,0384<
300A,0332 LateralSpreadingDeviceSequence no 300A,0334 LateralSpreadingDeviceNumber no 300A,0336 LateralSpreadingDeviceID no 300A,0338 LateralSpreadingDeviceID no 300A,0338 LateralSpreadingDeviceDescription no 300A,033C LateralSpreadingDeviceDescription no 300A,0340 NumberOfRangeModulatorS no 300A,0342 RangeModulatorSequence no 300A,0344 RangeModulatorID no 300A,0348 RangeModulatorID no 300A,0348 RangeModulatorID no 300A,0348 RangeModulatorID no 300A,0340 BeamCurrentModulationID no 300A,0340 BeamCurrentModulationID no 300A,0350 PatientSupportIType no 300A,0350 FixationLightAzimuthalAngle no 300A,0356 FixationLightAzimuthalAngle no 300A,0356 RangeShifterSetting no 300A,0360 RangeShifterSetting no 300A,0361 RangeShifterSetting no 300A,0362 RangeShifterSetting no 300A,0364 RangeShifterWaterEquivThickness no 300A,0370 LateralSpreadingDeviceSetting no 300A,0371 LateralSpreadingDeviceSetting no 300A,0372 RangeModulatorSettingSequence no 300A,0374 RangeModulatorSettingSequence no 300A,0382 RangeModulatorGatingStartValue no 300A,0382 RangeModulatorGatingStartValue no 300A,0384 RangeModulatorGatingStartValue no 300A,0385 ScanningSpotSize no 300A,0386 ScansSpotMetersetWeights no 300A,0386 ScansSpotMete
300A,0334 LateralSpreadingDeviceNumber no 300A,0336 LateralSpreadingDeviceTD no 300A,0338 LateralSpreadingDeviceType no 300A,033A LateralSpreadingDeviceDscription no 300A,033C LateralSpreadingDevWaterEquivThick no 300A,0340 NumberOfRangeModulators no 300A,0342 RangeModulatorSequence no 300A,0344 RangeModulatorNumber no 300A,0348 RangeModulatorTD no 300A,0348 RangeModulatorType no 300A,0348 RangeModulatorType no 300A,0340 PatientSupportType no 300A,0350 PatientSupportType no 300A,0351 PatientSupportType no 300A,0352 PatientSupportType no 300A,0354 FixationLightAzimuthalAngle no 300A,0358 FixationLightAzimuthalAngle no 300A,0358 FixationLightPolarAngle no 300A,0358 FixationLightPolarAngle no 300A,0350 RangeShifterSettingSequence no 300A,0360 RangeShifterSettingSequence no 300A,0360 RangeShifterWaterEquivThickness no 300A,0360 RangeShifterWaterEquivThickness no 300A,0370 LateralSpreadingDeviceSetting no 300A,0370 RangeModulatorSettingSequence no 300A,0380 RangeModulatorSettingSequence no 300A,0381 RangeModulatorGatingStartValue no 300A,0382 RangeModulatorGatingStartValue no 300A,0384 ScanSpotPositionMap no 300A,0394 ScanSpotMetersetWeights no 300A,0394 ScanSpotPositionMap no 300A,0394 ScanSpotPositionMap no 300A,0394 ScanSpotPositionMap no 300A,0394 ScanSpotMetersetWeights no 300A,0394 IonBeamLimitingDeviceSequence no 300A,039A IonWedgePositionSequence no 300A,030A IonWedgePositionSequence no 300A,0400 ReferencedSetupImageSequence no 300A,0400
300A,0336 LateralSpreadingDeviceID no 300A,0338 LateralSpreadingDeviceType no 300A,033A LateralSpreadingDeviceDescription no 300A,033C LateralSpreadingDevideDescription no 300A,034C NumberOfRangeModulators no 300A,034D RangeModulatorSequence no 300A,034E RangeModulatorSequence no 300A,034E RangeModulatorID no 300A,034E RangeModulatorID no 300A,034B RangeModulatorID no 300A,034A RangeModulatorDescription no 300A,034C BeamCurrentModulationID no 300A,035D PatientSupportType no 300A,035D PatientSupportID no 300A,035E PatientSupportID no 300A,035E PixationLightPolarAngle no 300A,035E FixationLightPolarAngle no 300A,035E RangeShifterSetting no 300A,035E RangeShifterSetting no 300A,036D RangeShifterSetting no 300A,036D RangeShifterSetting no 300A,036D RangeShifterWaterEquivThickness no 300A,036D RangeShifterWaterEquivThickness no 300A,037D LateralSpreadingDeviceSetting no 300A,037D LateralSpreadingDeviceSetting no 300A,037D LateralSpreadingDeviceSetting no 300A,037D RangeModulatorGatingStartValue no 300A,038D RangeModulatorGa
300A,0338 LateralSpreadingDeviceType no 300A,033C LateralSpreadingDeviceDescription no 300A,033C NumberOfRangeModulatorS no 300A,0340 NumberOfRangeModulatorS no 300A,0342 RangeModulatorSequence no 300A,0344 RangeModulatorID no 300A,0348 RangeModulatorID no 300A,0348 RangeModulatorType no 300A,0344 RangeModulatorType no 300A,0340 BeamCurrentModulationID no 300A,0350 PatientSupportID no 300A,0350 PatientSupportID no 300A,0354 PatientSupportID no 300A,0356 FixationLightAzimuthalAngle no 300A,0356 FixationLightPolarAngle no 300A,0356 RangeShifterSettingSequence no 300A,0360 RangeShifterSetting no 300A,0364 IsocenterToRangeShifterDistance no 300A,0364 RangeShifterWaterEquivThickness no 300A,0366 RangeShifterWaterEquivThickness no 300A,0370 LateralSpreadingDeviceSetting no 300A,0371 IsocenterToLateralSpreadingDevDist no 300A,0372 RangeModulatorSettingSequence no 300A,0380 RangeModulatorGatingStartValue no 300A,0384 ScanSpotPositionMap no 300A,0394 ScanSpotPositionMap no 300A,0398 ScanSpotPositionMap no 300A,0398 ScanSpotMetersetWeights no 300A,0398 ScanSpotMetersetWeights no 300A,0398 IonToleranceTableSequence no 300A,0384 IonBeamLimitingDeviceSequence no 300A,0384 IonWedgeSequence no 300A,030A IonWedgePositionSequence no 300A,0400 ReferencedSetupImageSequence no 300A,0400
300A,033A LateralSpreadingDeviceDescription no 300A,033C LateralSpreadingDevWaterEquivThick no 300A,0340 NumberOfRangeModulators no 300A,0342 RangeModulatorSequence no 300A,0344 RangeModulatorID no 300A,0346 RangeModulatorID no 300A,0348 RangeModulatorType no 300A,0348 RangeModulatorDescription no 300A,034C BeamCurrentModulationID no 300A,0350 PatientSupportType no 300A,0351 PatientSupportID no 300A,0354 PatientSupportAccessoryCode no 300A,0356 FixationLightAzimuthalAngle no 300A,0356 FixationLightPolarAngle no 300A,0356 RangeShifterSettingsSequence no 300A,0360 RangeShifterSettingsSequence no 300A,0360 RangeShifterSetting no 300A,0361 RangeShifterWaterEquivThickness no 300A,0362 RangeShifterWaterEquivThickness no 300A,0370 LateralSpreadingDeviceSetting no 300A,0371 IsocenterToLateralSpreadingDevDist no 300A,0380 RangeModulatorSettingStartValue no 300A,0384 RangeModulatorSettingStartValue no 300A,0384 RangeModulatorGatingStartValue no 300A,0384 RangeModulatorGatingStopValue no 300A,038
300A,033C LateralSpreadingDevWaterEquivThick no 300A,0340 NumberOfRangeModulators no 300A,0342 RangeModulatorSequence no 300A,0344 RangeModulatorID no 300A,0348 RangeModulatorType no 300A,0348 RangeModulatorDescription no 300A,034A RangeModulatorDescription no 300A,034C BeamCurrentModulationID no 300A,035D PatientSupportType no 300A,0352 PatientSupportID no 300A,0354 FixationLightAzimuthalAngle no 300A,0356 FixationLightPolarAngle no 300A,0356 FixationLightPolarAngle no 300A,0356 RangeShifterSetting no 300A,0360 RangeShifterSetting no 300A,0361 RangeShifterSetting no 300A,0362 RangeShifterWaterEquivThickness no 300A,0364 IsocenterToRangeShifterDistance no 300A,0364 RangeShifterWaterEquivThickness no 300A,0370 LateralSpreadingDeviceSetting no 300A,0371 LateralSpreadingDeviceSetting no 300A,0372 LateralSpreadingDeviceSetting no 300A,0374 RangeModulatorSettingSequence no 300A,0380 RangeModulatorGatingStartValue no 300A,0384 RangeModulatorGatingStartValue no 300A,0390 ScanSpotTuneID no 300A,0391 ScanSpotPositionMap no 300A,0394 ScanSpotPositionMap no 300A,0396 ScanSpotMetersetWeights no 300A,0396 ScanSpotMetersetWeights no 300A,0398 ScanSpotPositionMap
300A,0340 NumberOfRangeModulators no 300A,0342 RangeModulatorSequence no 300A,0344 RangeModulatorID no 300A,0348 RangeModulatorID no 300A,0348 RangeModulatorType no 300A,0340 RangeModulatorDescription no 300A,0340 RangeModulatorDescription no 300A,0340 BeamCurrentModulationID no 300A,0350 PatientSupportType no 300A,0351 PatientSupportID no 300A,0352 FixationLightAzimuthalAngle no 300A,0355 FixationLightPolarAngle no 300A,0356 FixationLightPolarAngle no 300A,0357 RangeShifterSettingSequence no 300A,0358 RangeShifterSetting no 300A,0360 RangeShifterSetting 300A,0360 RangeShifterSetting 300A,0360 RangeShifterWaterEquivThickness no 300A,0360 RangeShifterWaterEquivThickness no 300A,0370 LateralSpreadingDeviceSettingsSeq no 300A,0371 IsocenterToLateralSpreadingDevDist no 300A,0372 LateralSpreadingDeviceSetting no 300A,0374 IsocenterToLateralSpreadingDevDist no 300A,0380 RangeModulatorSettingsSequence no 300A,0381 RangeModulatorGatingStartValue no 300A,0382 RangeModulatorGatingStartValue no 300A,0384 RangeModulatorGatingStartValue no 300A,0384 RangeModulatorGatingStopValue no 300A,0384 RangeModulatorGatingStopValue no 300A,0385 ScanSpotTuneID no 300A,0396 ScanSpotPositions no 300A,0398 ScanSpotPositionMap no 300A,0399 ScanSpotPositionMap no 300A,0399 ScanSpotPositionMap no 300A,0390 ScanSpotMetersetWeights no 300A,0390 ScanSpotPositionMap
300A,0342RangeModulatorSequenceno300A,0346RangeModulatorIDno300A,0348RangeModulatorTypeno300A,0348RangeModulatorDescriptionno300A,0340RangeModulatorDescriptionno300A,0341RangeModulatorDescriptionno300A,0342BeamCurrentModulationIDno300A,0350PatientSupportTypeno300A,0351PatientSupportAccessoryCodeno300A,0352PatientSupportAccessoryCodeno300A,0353FixationLightPolarAngleno300A,0354FixationLightPolarAngleno300A,0355FixationLightPolarAngleno300A,0360RangeShifterSettingSequenceno300A,0361RangeShifterSettingno300A,0362RangeShifterWaterEquivThicknessno300A,0363RangeShifterWaterEquivThicknessno300A,0374IsocenterToRangeShifterDistanceno300A,0372LateralSpreadingDeviceSettingno300A,0373IsocenterToLateralSpreadingDevDistno300A,0384RangeModulatorSettingSsequenceno300A,0385RangeModulatorGatingStartValueno300A,0386RangeModulatorGatingStopValueno300A,0387ScanSpotTuneIDno300A,0398ScanSpotTuneIDno300A,0399ScanSpotTuneIDno300A,0394ScanSpotTuneIDno300A,0395ScanSpotMetersetWeightsno300A,0396ScanSpotMetersetWeights <td< td=""></td<>
300A,0344 RangeModulatorNumber no 300A,0348 RangeModulatorID no 300A,0348 RangeModulatorType no 300A,034A RangeModulatorDescription no 300A,034C BeamCurrentModulationID no 300A,0350 PatientSupportType no 300A,0352 PatientSupportID no 300A,0354 PatientSupportAccessoryCode no 300A,0355 FixationLightAzimuthalAngle no 300A,0356 FixationLightPolarAngle no 300A,0358 FixationLightPolarAngle no 300A,0350 RangeShifterSettingSequence no 300A,0360 RangeShifterSetting no 300A,0361 RangeShifterSetting no 300A,0362 RangeShifterWaterEquivThickness no 300A,0364 IsocenterToRangeShifterDistance no 300A,0370 LateralSpreadingDeviceSettingsSeq no 300A,0371 LateralSpreadingDeviceSetting no 300A,0372 RangeModulatorSettingsSequence no 300A,0372 RangeModulatorSettingSequence no 300A,0381 RangeModulatorGatingStartValue no 300A,0382 RangeModulatorGatingStartValue no 300A,0384 IsocenterToRangeModulatorDistance no 300A,0389 RangeModulatorGatingStopValue no 300A,0390 ScanSpotTuneID no 300A,0391 ScanSpotTuneID no 300A,0392 NumberOfScanSpotPositions no 300A,0394 ScanSpotPositionMap no 300A,0395 ScanSpotMetersetWeights no 300A,0396 ScanSpotMetersetWeights no 300A,0397 IonToleranceTableSequence no 300A,0398 IonToleranceTableSequence no 300A,0399 IonBeamSequence no 300A,0394 IonBeamLimitingDeviceSequence no 300A,0394 IonBeamLimitingDeviceSequence no 300A,0394 IonBeamLimitingDeviceSequence no 300A,0394 IonWedgeSequence no 300A,039A IonWedgeSequence no 300A,030A IonWedgeSequence no 300A,0400 ReferencedSetupImageSequence no
300A,0346 RangeModulatorID no 300A,0348 RangeModulatorType no 300A,034C BeamCurrentModulationID no 300A,035C PatientSupportType no 300A,035D PatientSupportType no 300A,035D PatientSupportID no 300A,035E FixationLightAzimuthalAngle no 300A,035E FixationLightPolarAngle no 300A,035E RangeShifterSettingSequence no 300A,036C RangeShifterSetting no 300A,036E RangeShifterSetting no 300A,036E RangeShifterWaterEquivThickness no 300A,036E RangeShifterWaterEquivThickness no 300A,0370 LateralSpreadingDeviceSetting no 300A,0371 IsocenterToLateralSpreadingDevDist no 300A,0372 RangeModulatorSettingSequence no 300A,0380 RangeModulatorSettingSequence no 300A,0381 RangeModulatorGatingStartValue no 300A,0382 RangeModulatorGatingStartValue no 300A,0384 RangeModulatorGatingStopValue no 300A,0389 ScanSpotTuneID no 300A,0390 ScanSpotTuneID no 300A,0391 ScanSpotPositions no 300A,0392 NumberOfScanSpotPositions no 300A,0393 ScanSpotMetersetWeights no 300A,0394 ScanSpotDesitionMap no 300A,0395 ScanSpotMetersetWeights no 300A,0396 ScanSpotMetersetWeights no 300A,0397 IonToleranceTableSequence no 300A,0340 IonBeamLimitingDeviceSequence no 300A,0341 IonBeamLimitingDeviceSequence no 300A,0342 IonBeamSequence no 300A,0343 IonControlPointSequence no 300A,0344 IonBeamLimitingDeviceSequence no 300A,0346 IonWedgeSequence no 300A,0347 IonWedgeSequence no 300A,0340 ReferencedSetupImageSequence no 300A,0401 ReferencedSetupImageSequence no
300A,034A RangeModulatorDescription no 300A,034C BeamCurrentModulationID no 300A,035D PatientSupportType no 300A,0351 PatientSupportID no 300A,0354 PatientSupportAccessoryCode no 300A,0356 FixationLightAzimuthalAngle no 300A,0358 FixationLightPolarAngle no 300A,035A MetersetRate no 300A,0360 RangeShifterSettingSsequence no 300A,0362 RangeShifterSetting no 300A,0364 IsocenterToRangeShifterDistance no 300A,0366 RangeShifterWaterEquivThickness no 300A,0370 LateralSpreadingDeviceSetting no 300A,0371 LateralSpreadingDeviceSetting no 300A,0372 LateralSpreadingDeviceSetting no 300A,0372 RangeModulatorSettingSsequence no 300A,0381 RangeModulatorSettingSsequence no 300A,0382 RangeModulatorGatingStartValue no 300A,0384 RangeModulatorGatingStartValue no 300A,0384 RangeModulatorGatingStopValue no 300A,0384 RangeModulatorGatingStopValue no 300A,0384 ScanSpotTuneID no 300A,0392 NumberOfScanSpotPositions no 300A,0393 ScanSpotMetersetWeights no 300A,0394 ScanSpotMetersetWeights no 300A,0395 ScanSpotMetersetWeights no 300A,0396 ScanSpotMetersetWeights no 300A,0397 NumberOfPaintings no 300A,0398 ScanningSpotSize no 300A,0399 NumberOfPaintings no 300A,0390 IonToleranceTableSequence no 300A,03A0 IonBeamLimitingDeviceSequence no 300A,03A1 IonBeamLimitingDeviceSequence no 300A,03A2 IonBeamSequence no 300A,03A3 IonOcontrolPointSequence no 300A,03A4 IonWedgeSequence no 300A,03A6 IonWedgeSequence no 300A,03A7 ReferencedSetupImageSequence no 300A,0401 ReferencedSetupImageSequence no
300A,034C BeamCurrentModulationID no 300A,0350 PatientSupportType no 300A,0352 PatientSupportID no 300A,0354 PatientSupportAccessoryCode no 300A,0355 FixationLightAzimuthalAngle no 300A,0356 FixationLightPolarAngle no 300A,0358 MetersetRate no 300A,0360 RangeShifterSettingsSequence no 300A,0361 RangeShifterSetting no 300A,0362 RangeShifterSetting no 300A,0364 IsocenterToRangeShifterDistance no 300A,0366 RangeShifterWaterEquivThickness no 300A,0370 LateralSpreadingDeviceSetting no 300A,0371 LateralSpreadingDeviceSetting no 300A,0372 LateralSpreadingDeviceSetting no 300A,0374 IsocenterToLateralSpreadingDevDist no 300A,0380 RangeModulatorSettingSsequence no 300A,0381 RangeModulatorGatingStartValue no 300A,0382 RangeModulatorGatingStartValue no 300A,0384 RangeModulatorGatingStopValue no 300A,0380 ScanSpotTuneID no 300A,0390 ScanSpotTuneID no 300A,0391 ScanSpotPositions no 300A,0392 ScanSpotPositionMap no 300A,0393 ScanSpotMetersetWeights no 300A,0394 ScanSpotPositionMap no 300A,0395 ScanSpotMetersetWeights no 300A,0396 ScanSpotMetersetWeights no 300A,0397 NumberOfPaintings no 300A,0398 ScanningSpotSize no 300A,0390 IonToleranceTableSequence no 300A,0340 IonBeamSequence no 300A,0341 IonBeamLimitingDeviceSequence no 300A,0342 IonBeamSequence no 300A,0343 IonWedgeSequence no 300A,0344 IonWedgeSequence no 300A,0340 ReferencedSetupImageSequence no 300A,0401 ReferencedSetupImageSequence no 300A,0402 SetupImageComment no
300A,0350 PatientSupportType no 300A,0352 PatientSupportID no 300A,0354 PatientSupportAccessoryCode no 300A,0356 FixationLightAzimuthalAngle no 300A,0358 FixationLightPolarAngle no 300A,035A MetersetRate no 300A,0360 RangeShifterSettingsSequence no 300A,0361 IsocenterToRangeShifterDistance no 300A,0362 RangeShifterWaterEquivThickness no 300A,0366 RangeShifterWaterEquivThickness no 300A,0370 LateralSpreadingDeviceSetting no 300A,0371 LateralSpreadingDeviceSetting no 300A,0372 LateralSpreadingDeviceSetting no 300A,0374 IsocenterToLateralSpreadingDevDist no 300A,0380 RangeModulatorSettingsSequence no 300A,0381 RangeModulatorGatingStartValue no 300A,0382 RangeModulatorGatingStartValue no 300A,0384 RangeModulatorGatingStopValue no 300A,0385 IsocenterToRangeModulatorDistance no 300A,0390 ScanSpotTuneID no 300A,0391 ScanSpotPositions no 300A,0392 RangeModulatorGatingStartValue no 300A,0393 ScanSpotPositionMap no 300A,0394 ScanSpotPositionMap no 300A,0395 ScanSpotMetersetWeights no 300A,0396 ScanSpotMetersetWeights no 300A,0397 NumberOfPaintings no 300A,0398 ScanningSpotSize no 300A,0390 IonToleranceTableSequence no 300A,030 IonBeamLimitingDeviceSequence no 300A,030 IonWedgeSequence no 300A,030 IonWedgeSequence no 300A,030 IonWedgeSequence no 300A,0401 ReferencedSetupImageSequence no 300A,0402 SetupImageComment no
300A,0352 PatientSupportID no 300A,0354 PatientSupportAccessoryCode no 300A,0356 FixationLightAzimuthalAngle no 300A,0358 FixationLightPolarAngle no 300A,035A MetersetRate no 300A,0360 RangeShifterSettingsSequence no 300A,0362 RangeShifterSetting no 300A,0364 IsocenterToRangeShifterDistance no 300A,0366 RangeShifterWaterEquivThickness no 300A,0370 LateralSpreadingDeviceSettingsSeq no 300A,0371 LateralSpreadingDeviceSetting no 300A,0372 LateralSpreadingDeviceSetting no 300A,0374 IsocenterToLateralSpreadingDevDist no 300A,0380 RangeModulatorSettingsSequence no 300A,0381 RangeModulatorGatingStartValue no 300A,0382 RangeModulatorGatingStartValue no 300A,0384 RangeModulatorGatingStopValue no 300A,0380 ScanSpotTuneID no 300A,0390 ScanSpotTuneID no 300A,0391 ScanSpotPositions no 300A,0392 NumberOfScanSpotPositions no 300A,0393 ScanSpotMetersetWeights no 300A,0394 ScanSpotMetersetWeights no 300A,0398 ScanningSpotSize no 300A,0390 IonToleranceTableSequence no 300A,03A0 IonBeamLimitingDeviceSequence no 300A,03A1 IonBeamLimitingDeviceSequence no 300A,03A2 IonBeamLimitingDeviceSequence no 300A,03A3 IonBockSequence no 300A,03A4 IonBeamLimitingDeviceSequence no 300A,03A5 IonWedgePositionSequence no 300A,03A6 IonWedgePositionSequence no 300A,03A7 ReferencedSetupImageSequence no 300A,03A0 SetupImageComment no
300A,0354 PatientSupportAccessoryCode no 300A,0356 FixationLightAzimuthalAngle no 300A,0358 FixationLightPolarAngle no 300A,035A MetersetRate no 300A,0360 RangeShifterSettingsSequence no 300A,0364 IsocenterToRangeShifterDistance no 300A,0364 RangeShifterWaterEquivThickness no 300A,0366 RangeShifterWaterEquivThickness no 300A,0367 LateralSpreadingDeviceSetting no 300A,0370 LateralSpreadingDeviceSetting no 300A,0372 LateralSpreadingDeviceSetting no 300A,0374 IsocenterToLateralSpreadingDevDist no 300A,0380 RangeModulatorSettingsSequence no 300A,0382 RangeModulatorGatingStartValue no 300A,0384 RangeModulatorGatingStartValue no 300A,0384 RangeModulatorGatingStopValue no 300A,0390 ScanSpotTuneID no 300A,0390 ScanSpotTuneID no 300A,0394 ScanSpotPositions no 300A,0394 ScanSpotPositionMap no 300A,0396 ScanSpotMetersetWeights no 300A,0398 ScanningSpotSize no 300A,039A IonToleranceTableSequence no 300A,03A0 IonToleranceTableSequence no 300A,03A1 IonBeamLimitingDeviceSequence no 300A,03A2 IonBeamSequence no 300A,03A3 IonBlockSequence no 300A,03A6 IonBlockSequence no 300A,03A7 IonWedgeSequence no 300A,03AC IonWedgePositionSequence no 300A,03AC IonWedgePositionSequence no 300A,0402 SetupImageComment no
300A,0356FixationLightAzimuthalAngleno300A,0358FixationLightPolarAngleno300A,035AMetersetRateno300A,0360RangeShifterSettingSequenceno300A,0362RangeShifterSettingno300A,0364IsocenterToRangeShifterDistanceno300A,0366RangeShifterWaterEquivThicknessno300A,0370LateralSpreadingDeviceSettingno300A,0372LateralSpreadingDeviceSettingno300A,0374IsocenterToLateralSpreadingDevDistno300A,0380RangeModulatorSettingSSequenceno300A,0381RangeModulatorGatingStartValueno300A,0384RangeModulatorGatingStopValueno300A,0384RangeModulatorGatingStopValueno300A,0390ScanSpotTuneIDno300A,0391NumberOfScanSpotPositionsno300A,0392NumberOfScanSpotPositionsno300A,0393ScanSpotMetersetWeightsno300A,0394ScanSpotMetersetWeightsno300A,0395ScanningSpotSizeno300A,0396NumberOfPaintingsno300A,0304IonToleranceTableSequenceno300A,0304IonBeamSequenceno300A,0304IonBeamSequenceno300A,0308IonControlPointSequenceno300A,030AIonWedgeSequenceno300A,030AIonWedgePositionSequenceno300A,0401ReferencedSetupImageSequenceno300A,0402SetupImageCommentn
300A,0358FixationLightPolarAngleno300A,035AMetersetRateno300A,0360RangeShifterSettingSSequenceno300A,0362RangeShifterSettingno300A,0364IsocenterToRangeShifterDistanceno300A,0366RangeShifterWaterEquivThicknessno300A,0370LateralSpreadingDeviceSettingsSeqno300A,0372LateralSpreadingDeviceSettingno300A,0374IsocenterToLateralSpreadingDevDistno300A,0380RangeModulatorSettingsSequenceno300A,0381RangeModulatorGatingStartValueno300A,0382RangeModulatorGatingStopValueno300A,0384RangeModulatorGatingStopValueno300A,0390ScanSpotTuneIDno300A,0391ScanSpotToneIDno300A,0392NumberOfScanSpotPositionsno300A,0393ScanSpotMetersetWeightsno300A,0394ScanSpotMetersetWeightsno300A,0398ScanningSpotSizeno300A,039AIonToleranceTableSequenceno300A,030AIonBeamSequenceno300A,030AIonBeamSequenceno300A,030AIonBlockSequenceno300A,030AIonWedgeSequenceno300A,030AIonWedgePositionSequenceno300A,0401ReferencedSetupImageSequenceno300A,0402SetupImageCommentno
300A,035AMetersetRateno300A,0360RangeShifterSettingsSequenceno300A,0362RangeShifterSettingno300A,0364IsocenterToRangeShifterDistanceno300A,0366RangeShifterWaterEquivThicknessno300A,0370LateralSpreadingDeviceSettingsSeqno300A,0372LateralSpreadingDeviceSettingno300A,0374IsocenterToLateralSpreadingDevDistno300A,0380RangeModulatorSettingsSequenceno300A,0381RangeModulatorGatingStartValueno300A,0382RangeModulatorGatingStopValueno300A,0384RangeModulatorGatingStopValueno300A,0390ScanSpotTuneIDno300A,0391ScanSpotTuneIDno300A,0392NumberOfScanSpotPositionsno300A,0393ScanSpotMetersetWeightsno300A,0394ScanSpotMetersetWeightsno300A,0398ScanningSpotSizeno300A,039AIonToleranceTableSequenceno300A,03A0IonBeamSequenceno300A,03A1IonBeamLimitingDeviceSequenceno300A,03A2IonBlockSequenceno300A,03A3IonControlPointSequenceno300A,03A4IonWedgeSequenceno300A,03ACIonWedgePositionSequenceno300A,0401ReferencedSetupImageSequenceno300A,0402SetupImageCommentno
300A,0360RangeShifterSettingsSequenceno300A,0362RangeShifterSettingno300A,0364IsocenterToRangeShifterDistanceno300A,0366RangeShifterWaterEquivThicknessno300A,0370LateralSpreadingDeviceSettingsSeqno300A,0372LateralSpreadingDeviceSettingno300A,0374IsocenterToLateralSpreadingDevDistno300A,0380RangeModulatorSettingsSequenceno300A,0381RangeModulatorGatingStartValueno300A,0384RangeModulatorGatingStopValueno300A,0390ScanSpotTuneIDno300A,0391ScanSpotTuneIDno300A,0392NumberOfScanSpotPositionsno300A,0393ScanSpotMetersetWeightsno300A,0394ScanSpotMetersetWeightsno300A,0398ScanningSpotSizeno300A,0399NumberOfPaintingsno300A,0340IonToleranceTableSequenceno300A,03A1IonBeamSequenceno300A,03A2IonBeamLimitingDeviceSequenceno300A,03A3IonControlPointSequenceno300A,03A4IonWedgeSequenceno300A,03ACIonWedgePositionSequenceno300A,0401ReferencedSetupImageSequenceno300A,0402SetupImageCommentno
300A,0362 RangeShifterSetting no 300A,0364 IsocenterToRangeShifterDistance no 300A,0366 RangeShifterWaterEquivThickness no 300A,0370 LateralSpreadingDeviceSettingSeq no 300A,0372 LateralSpreadingDeviceSetting no 300A,0374 IsocenterToLateralSpreadingDevDist no 300A,0380 RangeModulatorSettingsSequence no 300A,0382 RangeModulatorGatingStartValue no 300A,0384 RangeModulatorGatingStartValue no 300A,038A IsocenterToRangeModulatorDistance no 300A,0390 ScanSpotTuneID no 300A,0390 ScanSpotTuneID no 300A,0391 ScanSpotPositions no 300A,0392 NumberOfScanSpotPositions no 300A,0394 ScanSpotMetersetWeights no 300A,0396 ScanSpotMetersetWeights no 300A,0398 ScanningSpotSize no 300A,039A NumberOfPaintings no 300A,03A0 IonToleranceTableSequence no 300A,03A1 IonBeamLimitingDeviceSequence no 300A,03A2 IonBeamSequence no 300A,03A3 IonControlPointSequence no 300A,03A4 IonWedgeSequence no 300A,03AC IonWedgePositionSequence no 300A,0401 ReferencedSetupImageSequence no 300A,0402 SetupImageComment no
300A,0364 IsocenterToRangeShifterDistance no 300A,0366 RangeShifterWaterEquivThickness no 300A,0370 LateralSpreadingDeviceSettingSSeq no 300A,0372 LateralSpreadingDeviceSetting no 300A,0374 IsocenterToLateralSpreadingDevDist no 300A,0380 RangeModulatorSettingsSequence no 300A,0382 RangeModulatorGatingStartValue no 300A,0384 RangeModulatorGatingStopValue no 300A,038A IsocenterToRangeModulatorDistance no 300A,0390 ScanSpotTuneID no 300A,0391 NumberOfScanSpotPositions no 300A,0392 NumberOfScanSpotPositions no 300A,0394 ScanSpotMetersetWeights no 300A,0396 ScanSpotMetersetWeights no 300A,0398 ScanningSpotSize no 300A,0390 NumberOfPaintings no 300A,0304 IonToleranceTableSequence no 300A,0304 IonBeamLimitingDeviceSequence no 300A,0304 IonBeamLimitingDeviceSequence no 300A,0305 IonBlockSequence no 300A,0306 IonBlockSequence no 300A,0307 IonWedgeSequence no 300A,0308 IonWedgeSequence no 300A,0309 ReferencedSetupImageSequence no 300A,0401 ReferencedSetupImageSequence no
300A,0366 RangeShifterWaterEquivThickness no 300A,0370 LateralSpreadingDeviceSettingsSeq no 300A,0372 LateralSpreadingDeviceSetting no 300A,0374 IsocenterToLateralSpreadingDevDist no 300A,0380 RangeModulatorSettingsSequence no 300A,0382 RangeModulatorGatingStartValue no 300A,0384 RangeModulatorGatingStopValue no 300A,038A IsocenterToRangeModulatorDistance no 300A,0390 ScanSpotTuneID no 300A,0391 NumberOfScanSpotPositions no 300A,0392 NumberOfScanSpotPositions no 300A,0394 ScanSpotMetersetWeights no 300A,0398 ScanningSpotSize no 300A,0398 ScanningSpotSize no 300A,0304 IonToleranceTableSequence no 300A,03A1 IonBeamLimitingDeviceSequence no 300A,03A2 IonBeamSequence no 300A,03A3 IonControlPointSequence no 300A,03A6 IonWedgeSequence no 300A,03AC IonWedgePositionSequence no 300A,0401 ReferencedSetupImageSequence no 300A,0402 SetupImageComment no
300A,0370 LateralSpreadingDeviceSettingsSeq no 300A,0372 LateralSpreadingDeviceSetting no 300A,0374 IsocenterToLateralSpreadingDevDist no 300A,0380 RangeModulatorSettingsSequence no 300A,0382 RangeModulatorGatingStartValue no 300A,0384 RangeModulatorGatingStopValue no 300A,038A IsocenterToRangeModulatorDistance no 300A,0390 ScanSpotTuneID no 300A,0392 NumberOfScanSpotPositions no 300A,0394 ScanSpotPositionMap no 300A,0396 ScanSpotMetersetWeights no 300A,0398 ScanningSpotSize no 300A,039A NumberOfPaintings no 300A,03A0 IonToleranceTableSequence no 300A,03A1 IonBeamLimitingDeviceSequence no 300A,03A2 IonBeamSequence no 300A,03A6 IonControlPointSequence no 300A,03AA IonWedgeSequence no 300A,03AC IonWedgePositionSequence no 300A,0401 ReferencedSetupImageSequence no 300A,0402 SetupImageComment no
300A,0372 LateralSpreadingDeviceSetting no 300A,0374 IsocenterToLateralSpreadingDevDist no 300A,0380 RangeModulatorSettingsSequence no 300A,0382 RangeModulatorGatingStartValue no 300A,0384 RangeModulatorGatingStopValue no 300A,038A IsocenterToRangeModulatorDistance no 300A,0390 ScanSpotTuneID no 300A,0392 NumberOfScanSpotPositions no 300A,0394 ScanSpotPositionMap no 300A,0396 ScanSpotMetersetWeights no 300A,0398 ScanningSpotSize no 300A,039A NumberOfPaintings no 300A,03A0 IonToleranceTableSequence no 300A,03A1 IonBeamLimitingDeviceSequence no 300A,03A6 IonBlockSequence no 300A,03A6 IonControlPointSequence no 300A,03A6 IonWedgeSequence no 300A,03AC IonWedgePositionSequence no 300A,0401 ReferencedSetupImageSequence no 300A,0402 SetupImageComment no
300A,0374 IsocenterToLateralSpreadingDevDist no 300A,0380 RangeModulatorSettingsSequence no 300A,0382 RangeModulatorGatingStartValue no 300A,0384 RangeModulatorGatingStopValue no 300A,038A IsocenterToRangeModulatorDistance no 300A,0390 ScanSpotTuneID no 300A,0392 NumberOfScanSpotPositions no 300A,0394 ScanSpotPositionMap no 300A,0396 ScanSpotMetersetWeights no 300A,0398 ScanningSpotSize no 300A,039A NumberOfPaintings no 300A,03A0 IonToleranceTableSequence no 300A,03A2 IonBeamSequence no 300A,03A4 IonBeamLimitingDeviceSequence no 300A,03A6 IonControlPointSequence no 300A,03AA IonWedgeSequence no 300A,03AC IonWedgePositionSequence no 300A,0401 ReferencedSetupImageSequence no 300A,0402 SetupImageComment no
300A,0380 RangeModulatorSettingsSequence no 300A,0382 RangeModulatorGatingStartValue no 300A,0384 RangeModulatorGatingStopValue no 300A,038A IsocenterToRangeModulatorDistance no 300A,0390 ScanSpotTuneID no 300A,0392 NumberOfScanSpotPositions no 300A,0394 ScanSpotPositionMap no 300A,0396 ScanSpotMetersetWeights no 300A,0398 ScanningSpotSize no 300A,039A NumberOfPaintings no 300A,03A0 IonToleranceTableSequence no 300A,03A2 IonBeamSequence no 300A,03A4 IonBeamLimitingDeviceSequence no 300A,03A6 IonControlPointSequence no 300A,03AA IonWedgeSequence no 300A,03AC IonWedgePositionSequence no 300A,0401 ReferencedSetupImageSequence no 300A,0402 SetupImageComment no
300A,0382RangeModulatorGatingStartValueno300A,0384RangeModulatorGatingStopValueno300A,038AIsocenterToRangeModulatorDistanceno300A,0390ScanSpotTuneIDno300A,0392NumberOfScanSpotPositionsno300A,0394ScanSpotPositionMapno300A,0396ScanSpotMetersetWeightsno300A,0398ScanningSpotSizeno300A,039ANumberOfPaintingsno300A,03A0IonToleranceTableSequenceno300A,03A2IonBeamSequenceno300A,03A4IonBeamLimitingDeviceSequenceno300A,03A6IonBlockSequenceno300A,03A8IonControlPointSequenceno300A,03AAIonWedgeSequenceno300A,03ACIonWedgePositionSequenceno300A,0401ReferencedSetupImageSequenceno300A,0402SetupImageCommentno
300A,0384 RangeModulatorGatingStopValue no 300A,038A IsocenterToRangeModulatorDistance no 300A,0390 ScanSpotTuneID no 300A,0392 NumberOfScanSpotPositions no 300A,0394 ScanSpotPositionMap no 300A,0396 ScanSpotMetersetWeights no 300A,0398 ScanningSpotSize no 300A,039A NumberOfPaintings no 300A,039A IonToleranceTableSequence no 300A,03A2 IonBeamSequence no 300A,03A4 IonBeamLimitingDeviceSequence no 300A,03A6 IonControlPointSequence no 300A,03A8 IonControlPointSequence no 300A,03AC IonWedgeSequence no 300A,03AC SetupImageSequence no 300A,0401 ReferencedSetupImageSequence no
300A,038A IsocenterToRangeModulatorDistance no 300A,0390 ScanSpotTuneID no 300A,0392 NumberOfScanSpotPositions no 300A,0394 ScanSpotPositionMap no 300A,0396 ScanSpotMetersetWeights no 300A,0398 ScanningSpotSize no 300A,039A NumberOfPaintings no 300A,039A IonToleranceTableSequence no 300A,03A2 IonBeamSequence no 300A,03A4 IonBeamLimitingDeviceSequence no 300A,03A6 IonControlPointSequence no 300A,03A8 IonControlPointSequence no 300A,03AC IonWedgeSequence no 300A,03AC IonWedgePositionSequence no 300A,0401 ReferencedSetupImageSequence no 300A,0402 SetupImageComment no
300A,0390 ScanSpotTuneID no 300A,0392 NumberOfScanSpotPositions no 300A,0394 ScanSpotPositionMap no 300A,0396 ScanSpotMetersetWeights no 300A,0398 ScanningSpotSize no 300A,039A NumberOfPaintings no 300A,03AO IonToleranceTableSequence no 300A,03A2 IonBeamSequence no 300A,03A4 IonBeamLimitingDeviceSequence no 300A,03A6 IonBlockSequence no 300A,03A8 IonControlPointSequence no 300A,03AA IonWedgeSequence no 300A,03AC IonWedgePositionSequence no 300A,0401 ReferencedSetupImageSequence no 300A,0402 SetupImageComment no
300A,0394 ScanSpotPositionMap no 300A,0396 ScanSpotMetersetWeights no 300A,0398 ScanningSpotSize no 300A,039A NumberOfPaintings no 300A,03A0 IonToleranceTableSequence no 300A,03A2 IonBeamSequence no 300A,03A4 IonBeamLimitingDeviceSequence no 300A,03A6 IonBlockSequence no 300A,03A8 IonControlPointSequence no 300A,03AA IonWedgeSequence no 300A,03AC IonWedgePositionSequence no 300A,0401 ReferencedSetupImageSequence no 300A,0402 SetupImageComment no
300A,0396 ScanSpotMetersetWeights no 300A,0398 ScanningSpotSize no 300A,039A NumberOfPaintings no 300A,03A0 IonToleranceTableSequence no 300A,03A2 IonBeamSequence no 300A,03A4 IonBeamLimitingDeviceSequence no 300A,03A6 IonBlockSequence no 300A,03A8 IonControlPointSequence no 300A,03AA IonWedgeSequence no 300A,03AC IonWedgePositionSequence no 300A,0401 ReferencedSetupImageSequence no 300A,0402 SetupImageComment no
300A,0398 ScanningSpotSize no 300A,039A NumberOfPaintings no 300A,03A0 IonToleranceTableSequence no 300A,03A2 IonBeamSequence no 300A,03A4 IonBeamLimitingDeviceSequence no 300A,03A6 IonBlockSequence no 300A,03A8 IonControlPointSequence no 300A,03AA IonWedgeSequence no 300A,03AC IonWedgePositionSequence no 300A,0401 ReferencedSetupImageSequence no 300A,0402 SetupImageComment no
300A,039A NumberOfPaintings no 300A,03A0 IonToleranceTableSequence no 300A,03A2 IonBeamSequence no 300A,03A4 IonBeamLimitingDeviceSequence no 300A,03A6 IonBlockSequence no 300A,03A8 IonControlPointSequence no 300A,03AA IonWedgeSequence no 300A,03AC IonWedgePositionSequence no 300A,0401 ReferencedSetupImageSequence no 300A,0402 SetupImageComment no
300A,03A0 IonToleranceTableSequence no 300A,03A2 IonBeamSequence no 300A,03A4 IonBeamLimitingDeviceSequence no 300A,03A6 IonBlockSequence no 300A,03A8 IonControlPointSequence no 300A,03AA IonWedgeSequence no 300A,03AC IonWedgePositionSequence no 300A,0401 ReferencedSetupImageSequence no 300A,0402 SetupImageComment no
300A,03A2 IonBeamSequence no 300A,03A4 IonBeamLimitingDeviceSequence no 300A,03A6 IonBlockSequence no 300A,03A8 IonControlPointSequence no 300A,03AA IonWedgeSequence no 300A,03AC IonWedgePositionSequence no 300A,0401 ReferencedSetupImageSequence no 300A,0402 SetupImageComment no
300A,03A4 IonBeamLimitingDeviceSequence no 300A,03A6 IonBlockSequence no 300A,03A8 IonControlPointSequence no 300A,03AA IonWedgeSequence no 300A,03AC IonWedgePositionSequence no 300A,0401 ReferencedSetupImageSequence no 300A,0402 SetupImageComment no
300A,03A6 IonBlockSequence no 300A,03A8 IonControlPointSequence no 300A,03AA IonWedgeSequence no 300A,03AC IonWedgePositionSequence no 300A,0401 ReferencedSetupImageSequence no 300A,0402 SetupImageComment no
300A,03A8 IonControlPointSequence no 300A,03AA IonWedgeSequence no 300A,03AC IonWedgePositionSequence no 300A,0401 ReferencedSetupImageSequence no 300A,0402 SetupImageComment no
300A,03AA IonWedgeSequence no 300A,03AC IonWedgePositionSequence no 300A,0401 ReferencedSetupImageSequence no 300A,0402 SetupImageComment no
300A,03AC IonWedgePositionSequence no 300A,0401 ReferencedSetupImageSequence no 300A,0402 SetupImageComment no
300A,0401 ReferencedSetupImageSequence no 300A,0402 SetupImageComment no
300A,0402 SetupImageComment no
300A,0410 MotionSynchronizationSequence no
300A,0412 ControlPointOrientation no
300A,0420 GeneralAccessorySequence no
300A,0421 GeneralAccessoryID no
300A,0422 GeneralAccessoryDescription no
300A,0423 GeneralAccessoryType no
300A,0424 GeneralAccessoryNumber no
300C,0002 ReferencedRTPlanSequence no

300C,0007	ReferencedReferenceImageNumber	no
300C,0008	StartCumulativeMetersetWeight	no
300C,0009	EndCumulativeMetersetWeight	no
300C,000A	ReferencedBrachyAppSetupSeq	no
300C,000C	ReferencedBrachyAppSetupNumber	no
300C,000E	ReferencedSourceNumber	no
300C,0020	ReferencedFractionGroupSequence	no
300C,0022	ReferencedFractionGroupNumber	no
300C,0040	ReferencedVerificationImageSeq	no
300C,0042	ReferencedReferenceImageSequence	no
300C,0050	ReferencedDoseReferenceSequence	no
300C,0051	ReferencedDoseReferenceNumber	no
300C,0055	BrachyReferencedDoseReferenceSeq	no
300C,0060	ReferencedStructureSetSequence	no
300C,006A	ReferencedPatientSetupNumber	no
300C,0080	ReferencedDoseSequence	no
300C,00A0	ReferencedToleranceTableNumber	no
300C,00B0	ReferencedBolusSequence	no
300C,00C0	ReferencedWedgeNumber	no
300C,00D0	ReferencedCompensatorNumber	no
300C,00E0	ReferencedBlockNumber	no
300C,00F0	ReferencedControlPointIndex	no
300C,00F2	ReferencedControlPointSequence	no
300C,00F2	ReferencedStartControlPointIndex	no
300C,00F4	ReferencedStopControlPointIndex	no
300C,00F0	ReferencedRangeShifterNumber	no
300C,0100	ReferencedLateralSpreadingDevNum	
300C,0102	ReferencedRangeModulatorNumber	no
		no
300E,0002	ApprovalStatus	no
300E,0004	ReviewDate	no
300E,0005	ReviewTime ReviewerName	no
300E,0008		no
4000,0000	TextGroupLength	no
4000,0010	Arbitrary	no
4000,4000	TextComments	no
4008,0040	ResultsID	no
4008,0042	ResultsIDIssuer	no
4008,0050	ReferencedInterpretationSequence	no
	INFARNCESFIANDACARGANSEA	
4008,0100	InterpretationRecordedDate	no
4008,0101	InterpretationRecordedTime	no
4008,0101 4008,0102	InterpretationRecordedTime InterpretationRecorder	no no
4008,0101 4008,0102 4008,0103	InterpretationRecordedTime InterpretationRecorder ReferenceToRecordedSound	no no no
4008,0101 4008,0102 4008,0103 4008,0108	InterpretationRecordedTime InterpretationRecorder ReferenceToRecordedSound InterpretationTranscriptionDate	no no no no
4008,0101 4008,0102 4008,0103 4008,0108 4008,0109	InterpretationRecordedTime InterpretationRecorder ReferenceToRecordedSound InterpretationTranscriptionDate InterpretationTranscriptionTime	no no no
4008,0101 4008,0102 4008,0103 4008,0108 4008,0109 4008,010A	InterpretationRecordedTime InterpretationRecorder ReferenceToRecordedSound InterpretationTranscriptionDate InterpretationTranscriptionTime InterpretationTranscriber	no no no no
4008,0101 4008,0102 4008,0103 4008,0108 4008,0109 4008,010A 4008,010B	InterpretationRecordedTime InterpretationRecorder ReferenceToRecordedSound InterpretationTranscriptionDate InterpretationTranscriptionTime InterpretationTranscriber InterpretationText	no no no no
4008,0101 4008,0102 4008,0103 4008,0108 4008,0109 4008,010A 4008,010B 4008,010C	InterpretationRecordedTime InterpretationRecorder ReferenceToRecordedSound InterpretationTranscriptionDate InterpretationTranscriptionTime InterpretationTranscriber InterpretationText InterpretationAuthor	no no no no no
4008,0101 4008,0102 4008,0103 4008,0108 4008,0109 4008,010A 4008,010B 4008,010C 4008,0111	InterpretationRecordedTime InterpretationRecorder ReferenceToRecordedSound InterpretationTranscriptionDate InterpretationTranscriptionTime InterpretationTranscriber InterpretationText InterpretationAuthor InterpretationApproverSequence	no no no no no no
4008,0101 4008,0102 4008,0103 4008,0108 4008,0109 4008,010A 4008,010B 4008,010C 4008,0111 4008,0112	InterpretationRecordedTime InterpretationRecorder ReferenceToRecordedSound InterpretationTranscriptionDate InterpretationTranscriptionTime InterpretationTranscriber InterpretationText InterpretationAuthor InterpretationApproverSequence InterpretationApprovalDate	no
4008,0101 4008,0102 4008,0103 4008,0108 4008,0109 4008,010A 4008,010B 4008,010C 4008,0111 4008,0112 4008,0113	InterpretationRecordedTime InterpretationRecorder ReferenceToRecordedSound InterpretationTranscriptionDate InterpretationTranscriptionTime InterpretationTranscriber InterpretationText InterpretationAuthor InterpretationApproverSequence InterpretationApprovalDate InterpretationApprovalTime	no no no no no no no no
4008,0101 4008,0102 4008,0103 4008,0108 4008,0109 4008,010A 4008,010B 4008,010C 4008,0111 4008,0112 4008,0113 4008,0114	InterpretationRecordedTime InterpretationRecorder ReferenceToRecordedSound InterpretationTranscriptionDate InterpretationTranscriptionTime InterpretationTranscriber InterpretationText InterpretationAuthor InterpretationApproverSequence InterpretationApprovalDate InterpretationApprovalTime PhysicianApprovingInterpretation	no
4008,0101 4008,0102 4008,0103 4008,0108 4008,0109 4008,010A 4008,010B 4008,010C 4008,0111 4008,0112 4008,0113 4008,0114 4008,0115	InterpretationRecordedTime InterpretationRecorder ReferenceToRecordedSound InterpretationTranscriptionDate InterpretationTranscriptionTime InterpretationTranscriber InterpretationText InterpretationAuthor InterpretationApproverSequence InterpretationApprovalDate InterpretationApprovalTime PhysicianApprovingInterpretation InterpretationDiagnosisDescription	no n
4008,0101 4008,0102 4008,0103 4008,0108 4008,0109 4008,010A 4008,010B 4008,010C 4008,0111 4008,0112 4008,0113 4008,0114 4008,0115 4008,0117	InterpretationRecordedTime InterpretationRecorder ReferenceToRecordedSound InterpretationTranscriptionDate InterpretationTranscriptionTime InterpretationTranscriber InterpretationText InterpretationAuthor InterpretationApproverSequence InterpretationApprovalDate InterpretationApprovalTime PhysicianApprovingInterpretation	no n
4008,0101 4008,0102 4008,0103 4008,0108 4008,0109 4008,010A 4008,010B 4008,010C 4008,0111 4008,0112 4008,0113 4008,0114 4008,0115	InterpretationRecordedTime InterpretationRecorder ReferenceToRecordedSound InterpretationTranscriptionDate InterpretationTranscriptionTime InterpretationTranscriber InterpretationText InterpretationAuthor InterpretationApproverSequence InterpretationApprovalDate InterpretationApprovalTime PhysicianApprovingInterpretation InterpretationDiagnosisDescription	no n
4008,0101 4008,0102 4008,0103 4008,0108 4008,0109 4008,010A 4008,010B 4008,010C 4008,0111 4008,0112 4008,0113 4008,0114 4008,0115 4008,0117	InterpretationRecordedTime InterpretationRecorder ReferenceToRecordedSound InterpretationTranscriptionDate InterpretationTranscriptionTime InterpretationTranscriber InterpretationText InterpretationAuthor InterpretationApproverSequence InterpretationApprovalDate InterpretationApprovalTime PhysicianApprovingInterpretation InterpretationDiagnosisDescription InterpretationDiagnosisCodeSeq	no n
4008,0101 4008,0102 4008,0103 4008,0108 4008,010A 4008,010B 4008,010C 4008,0111 4008,0112 4008,0113 4008,0114 4008,0115 4008,0117 4008,0118	InterpretationRecordedTime InterpretationRecorder ReferenceToRecordedSound InterpretationTranscriptionDate InterpretationTranscriptionTime InterpretationTranscriber InterpretationText InterpretationAuthor InterpretationApproverSequence InterpretationApprovalDate InterpretationApprovalTime PhysicianApprovingInterpretation InterpretationDiagnosisDescription InterpretationDiagnosisCodeSeq ResultsDistributionListSequence	no n
4008,0101 4008,0102 4008,0103 4008,0108 4008,0109 4008,010A 4008,010B 4008,0111 4008,0111 4008,0113 4008,0114 4008,0115 4008,0117 4008,0118 4008,0119	InterpretationRecordedTime InterpretationRecorder ReferenceToRecordedSound InterpretationTranscriptionDate InterpretationTranscriptionTime InterpretationTranscriber InterpretationText InterpretationAuthor InterpretationApproverSequence InterpretationApprovalDate InterpretationApprovalTime PhysicianApprovingInterpretation InterpretationDiagnosisDescription InterpretationDiagnosisCodeSeq ResultsDistributionListSequence DistributionName	no n
4008,0101 4008,0102 4008,0103 4008,0108 4008,0109 4008,010A 4008,010B 4008,0111 4008,0111 4008,0113 4008,0114 4008,0115 4008,0117 4008,0118 4008,0118 4008,0119 4008,011A	InterpretationRecordedTime InterpretationRecorder ReferenceToRecordedSound InterpretationTranscriptionDate InterpretationTranscriptionTime InterpretationTranscriber InterpretationText InterpretationAuthor InterpretationApproverSequence InterpretationApprovalDate InterpretationApprovalTime PhysicianApprovingInterpretation InterpretationDiagnosisDescription InterpretationDiagnosisCodeSeq ResultsDistributionListSequence DistributionName DistributionAddress InterpretationID	no n
4008,0101 4008,0102 4008,0103 4008,0108 4008,0109 4008,010A 4008,010B 4008,0111 4008,0111 4008,0113 4008,0115 4008,0115 4008,0117 4008,0118 4008,0118 4008,0119 4008,011A 4008,011A	InterpretationRecordedTime InterpretationRecorder ReferenceToRecordedSound InterpretationTranscriptionDate InterpretationTranscriptionTime InterpretationTranscriber InterpretationText InterpretationAuthor InterpretationApproverSequence InterpretationApprovalDate InterpretationApprovalTime PhysicianApprovingInterpretation InterpretationDiagnosisDescription InterpretationDiagnosisCodeSeq ResultsDistributionListSequence DistributionName DistributionAddress	no n
4008,0101 4008,0102 4008,0103 4008,0108 4008,0109 4008,010A 4008,010B 4008,0111 4008,0111 4008,0112 4008,0113 4008,0114 4008,0115 4008,0117 4008,0118 4008,0118 4008,011A 4008,011A 4008,011A	InterpretationRecordedTime InterpretationRecorder ReferenceToRecordedSound InterpretationTranscriptionDate InterpretationTranscriptionTime InterpretationTranscriber InterpretationText InterpretationAuthor InterpretationApproverSequence InterpretationApprovalDate InterpretationApprovalTime PhysicianApprovingInterpretation InterpretationDiagnosisDescription InterpretationDiagnosisCodeSeq ResultsDistributionListSequence DistributionName DistributionAddress InterpretationID InterpretationIDIssuer InterpretationTypeID	no n
4008,0101 4008,0102 4008,0108 4008,0109 4008,010A 4008,010B 4008,010C 4008,0111 4008,0112 4008,0113 4008,0114 4008,0115 4008,0115 4008,0117 4008,0118 4008,0118 4008,011A 4008,011A 4008,011A 4008,0200 4008,0202 4008,0210	InterpretationRecordedTime InterpretationRecorder ReferenceToRecordedSound InterpretationTranscriptionDate InterpretationTranscriptionTime InterpretationTranscriber InterpretationText InterpretationAuthor InterpretationApproverSequence InterpretationApprovalDate InterpretationApprovalTime PhysicianApprovingInterpretation InterpretationDiagnosisDescription InterpretationDiagnosisCodeSeq ResultsDistributionListSequence DistributionName DistributionAddress InterpretationID InterpretationIDIssuer	no n
4008,0101 4008,0102 4008,0108 4008,0109 4008,010A 4008,010B 4008,010C 4008,0111 4008,0112 4008,0113 4008,0114 4008,0115 4008,0117 4008,0118 4008,0118 4008,011A 4008,011A 4008,011A 4008,011A 4008,0200 4008,0210 4008,0212	InterpretationRecordedTime InterpretationRecorder ReferenceToRecordedSound InterpretationTranscriptionDate InterpretationTranscriptionTime InterpretationTranscriber InterpretationText InterpretationAuthor InterpretationApproverSequence InterpretationApprovalDate InterpretationApprovalTime PhysicianApprovingInterpretation InterpretationDiagnosisDescription InterpretationDiagnosisCodeSeq ResultsDistributionListSequence DistributionName DistributionAddress InterpretationID InterpretationIDIssuer InterpretationTypeID InterpretationStatusID	no n
4008,0101 4008,0102 4008,0108 4008,0109 4008,010A 4008,010B 4008,010C 4008,0111 4008,0112 4008,0113 4008,0114 4008,0115 4008,0117 4008,0118 4008,0118 4008,011A 4008,011A 4008,011A 4008,011A 4008,0200 4008,0202 4008,0210 4008,0300	InterpretationRecordedTime InterpretationRecorder ReferenceToRecordedSound InterpretationTranscriptionDate InterpretationTranscriptionTime InterpretationTranscriber InterpretationText InterpretationAuthor InterpretationApproverSequence InterpretationApprovalDate InterpretationApprovalTime PhysicianApprovingInterpretation InterpretationDiagnosisDescription InterpretationDiagnosisCodeSeq ResultsDistributionListSequence DistributionName DistributionAddress InterpretationID InterpretationIDIssuer InterpretationTypeID InterpretationStatusID Impressions	no n
4008,0101 4008,0102 4008,0103 4008,0109 4008,010A 4008,010C 4008,0111 4008,0112 4008,0113 4008,0114 4008,0115 4008,0117 4008,0118 4008,0118 4008,011A 4008,011A 4008,0200 4008,0202 4008,0210 4008,0210 4008,0300 4008,0300 4008,0300 4008,0300 4008,0001	InterpretationRecordedTime InterpretationRecorder ReferenceToRecordedSound InterpretationTranscriptionDate InterpretationTranscriptionTime InterpretationTranscriber InterpretationText InterpretationAuthor InterpretationApproverSequence InterpretationApprovalDate InterpretationApprovalTime PhysicianApprovingInterpretation InterpretationDiagnosisDescription InterpretationDiagnosisCodeSeq ResultsDistributionListSequence DistributionName DistributionAddress InterpretationID InterpretationIDIssuer InterpretationTypeID InterpretationStatusID Impressions ResultsComments	no n
4008,0101 4008,0102 4008,0103 4008,0109 4008,010A 4008,010C 4008,0111 4008,0112 4008,0113 4008,0114 4008,0115 4008,0115 4008,0117 4008,0118 4008,0119 4008,011A 4008,0202 4008,0202 4008,0212 4008,0300 4008,4000 4FFE,0001 50xx,0005	InterpretationRecordedTime InterpretationRecorder ReferenceToRecordedSound InterpretationTranscriptionDate InterpretationTranscriptionTime InterpretationTranscriber InterpretationText InterpretationAuthor InterpretationApproverSequence InterpretationApprovalDate InterpretationApprovalTime PhysicianApprovingInterpretation InterpretationDiagnosisDescription InterpretationDiagnosisCodeSeq ResultsDistributionListSequence DistributionName DistributionAddress InterpretationID InterpretationIDIssuer InterpretationTypeID InterpretationStatusID Impressions ResultsComments MACParametersSequence	no n
4008,0101 4008,0102 4008,0103 4008,0109 4008,010A 4008,010C 4008,0111 4008,0112 4008,0113 4008,0115 4008,0115 4008,0117 4008,0118 4008,0118 4008,0119 4008,011A 4008,0202 4008,0202 4008,0212 4008,0300 4008,4000 4FFE,0001 50xx,0005 50xx,0010	InterpretationRecordedTime InterpretationRecorder ReferenceToRecordedSound InterpretationTranscriptionDate InterpretationTranscriptionTime InterpretationTranscriber InterpretationText InterpretationAuthor InterpretationApproverSequence InterpretationApprovalDate InterpretationApprovalTime PhysicianApprovingInterpretation InterpretationDiagnosisDescription InterpretationDiagnosisCodeSeq ResultsDistributionListSequence DistributionName DistributionAddress InterpretationID InterpretationIDIssuer InterpretationTypeID InterpretationStatusID Impressions ResultsComments MACParametersSequence CurveDimensions NumberOfPoints	no n
4008,0101 4008,0102 4008,0103 4008,0109 4008,010A 4008,010C 4008,0111 4008,0112 4008,0113 4008,0115 4008,0115 4008,0117 4008,0118 4008,0119 4008,011A 4008,011A 4008,0202 4008,0210 4008,0212 4008,0300 4008,4000 4FFE,0001 50xx,0005 50xx,0010 50xx,0020	InterpretationRecordedTime InterpretationRecorder ReferenceToRecordedSound InterpretationTranscriptionDate InterpretationTranscriptionTime InterpretationTranscriber InterpretationText InterpretationAuthor InterpretationApproverSequence InterpretationApprovalDate InterpretationApprovalTime PhysicianApprovingInterpretation InterpretationDiagnosisDescription InterpretationDiagnosisCodeSeq ResultsDistributionListSequence DistributionName DistributionAddress InterpretationID InterpretationIDIssuer InterpretationTypeID InterpretationStatusID Impressions ResultsComments MACParametersSequence CurveDimensions NumberOfPoints TypeOfData	no n
4008,0101 4008,0102 4008,0103 4008,0109 4008,010A 4008,010B 4008,010C 4008,0111 4008,0112 4008,0113 4008,0115 4008,0115 4008,0117 4008,0118 4008,0118 4008,011A 4008,011A 4008,011A 4008,0200 4008,0212 4008,0300 4008,0300 4008,0300 4008,0300 50xx,0005 50xx,0020 50xx,0022	InterpretationRecordedTime InterpretationRecorder ReferenceToRecordedSound InterpretationTranscriptionDate InterpretationTranscriptionTime InterpretationTranscriber InterpretationText InterpretationAuthor InterpretationApproverSequence InterpretationApprovalDate InterpretationApprovalTime PhysicianApprovingInterpretation InterpretationDiagnosisDescription InterpretationDiagnosisCodeSeq ResultsDistributionListSequence DistributionName DistributionAddress InterpretationID InterpretationIDIssuer InterpretationStatusID Impressions ResultsComments MACParametersSequence CurveDimensions NumberOfPoints TypeOfData CurveDescription	no n
4008,0101 4008,0102 4008,0103 4008,0109 4008,010A 4008,010B 4008,010C 4008,0111 4008,0112 4008,0113 4008,0115 4008,0115 4008,0117 4008,0118 4008,0118 4008,0119 4008,011A 4008,0200 4008,0202 4008,0200 4008,0200 5000000000000000000000000000000000	InterpretationRecordedTime InterpretationRecorder ReferenceToRecordedSound InterpretationTranscriptionDate InterpretationTranscriptionTime InterpretationTranscriber InterpretationText InterpretationAuthor InterpretationApproverSequence InterpretationApprovalDate InterpretationApprovalTime PhysicianApprovingInterpretation InterpretationDiagnosisDescription InterpretationDiagnosisCodeSeq ResultsDistributionListSequence DistributionName DistributionAddress InterpretationID InterpretationIDIssuer InterpretationTypeID InterpretationStatusID Impressions ResultsComments MACParametersSequence CurveDimensions NumberOfPoints TypeOfData CurveDescription AxisUnits	no n
4008,0101 4008,0102 4008,0103 4008,0109 4008,010A 4008,010B 4008,010C 4008,0111 4008,0112 4008,0113 4008,0115 4008,0115 4008,0117 4008,0118 4008,0118 4008,011A 4008,011A 4008,011A 4008,0200 4008,0212 4008,0300 4008,0300 4008,0300 4008,0300 50xx,0005 50xx,0020 50xx,0022	InterpretationRecordedTime InterpretationRecorder ReferenceToRecordedSound InterpretationTranscriptionDate InterpretationTranscriptionTime InterpretationTranscriber InterpretationText InterpretationAuthor InterpretationApproverSequence InterpretationApprovalDate InterpretationApprovalTime PhysicianApprovingInterpretation InterpretationDiagnosisDescription InterpretationDiagnosisCodeSeq ResultsDistributionListSequence DistributionName DistributionAddress InterpretationID InterpretationIDIssuer InterpretationStatusID Impressions ResultsComments MACParametersSequence CurveDimensions NumberOfPoints TypeOfData CurveDescription	no n

	ExifTool 13.24 Tag Names	
50xx,0104	MinimumCoordinateValue	no
50xx,0105	MaximumCoordinateValue	no
50xx,0106	CurveRange	no
50xx,0110	CurveDataDescriptor	no
50xx,0112	CoordinateStartValue	no
50xx,0114 50xx,1001	CoordinateStepValue CurveActivationLayer	no
50xx,1001 50xx,2000	AudioType	no no
50xx,2000	AudioSampleFormat	no
50xx,2004	NumberOfChannels	no
50xx,2006	NumberOfSamples	no
50xx,2008	SampleRate	no
50xx,200A	TotalTime	no
50xx,200C	AudioSampleData	no
50xx,200E	AudioComments	no
50xx,2500 50xx,2600	CurveLabel ReferencedOverlaySequence	no
50xx,2610	ReferencedOverlaySequence ReferencedOverlayGroup	no no
50xx,2010	CurveData	no
5200,9229	SharedFunctionalGroupsSequence	no
5200,9230	PerFrameFunctionalGroupsSequence	no
5400,0100	WaveformSequence	no
5400,0110	ChannelMinimumValue	no
5400,0112	ChannelMaximumValue	no
5400,1004	WaveformBitsAllocated	no
5400,1006 5400,100A	WaveformSampleInterpretation WaveformPaddingValue	no
5400,100A 5400,1010	WaveformData	no no
5600,0010	FirstOrderPhaseCorrectionAngle	no
5600,0020	SpectroscopyData	no
6000,0000	OverlayGroupLength	no
60xx,0010	OverlayRows	no
60xx,0011	OverlayColumns	no
60xx,0012	OverlayPlanes	no
60xx,0015	NumberOfFramesInOverlay	no
60xx,0022 60xx,0040	OverlayDescription OverlayType	no no
60xx,0045	OverlaySubtype	no
60xx,0050	OverlayOrigin	no
60xx,0051	ImageFrameOrigin	no
60xx,0052	OverlayPlaneOrigin	no
60xx,0060	OverlayCompressionCode	no
60xx,0061	OverlayCompressionOriginator	no
60xx,0062	OverlayCompressionLabel	no
60xx,0063 60xx,0066	OverlayCompressionDescription	no
60xx,0068	OverlayCompressionStepPointers OverlayRepeatInterval	no no
60xx,0069	OverlayBitsGrouped	no
60xx,0100	OverlayBitsAllocated	no
60xx,0102	OverlayBitPosition	no
60xx,0110	OverlayFormat	no
60xx,0200	OverlayLocation	no
60xx,0800	OverlayCodeLabel	no
60xx,0802	OverlayNumberOfTables	no
60xx,0803 60xx,0804	OverlayCodeTableLocation OverlayBitsForCodeWord	no no
60xx,1001	OverlayActivationLayer	no
60xx,1100	OverlayDescriptorGray	no
60xx,1101	OverlayDescriptorRed	no
60xx,1102	OverlayDescriptorGreen	no
60xx,1103	OverlayDescriptorBlue	no
60xx,1200	OverlaysGray	no
60xx,1201	OverlaysRed	no
60xx,1202 60xx,1203	OverlaysGreen OverlaysBlue	no
60xx,1203	ROIArea	no no
60xx,1301	ROIMean	no
60xx,1303	ROIStandardDeviation	no
60xx,1500	OverlayLabel	no
60xx,3000	OverlayData	no

60xx,4000	OverlayComments	no
7Fxx,0000	PixelDataGroupLength	no
7Fxx,0010	PixelData	no
7Fxx,0011	VariableNextDataGroup	no
7Fxx,0020	VariableCoefficientsSDVN	no
7Fxx,0030	VariableCoefficientsSDHN	no
7Fxx,0040	VariableCoefficientsSDDN	no
FFFA,FFFA	DigitalSignaturesSequence	no
FFFC,FFFC	DataSetTrailingPadding	no
FFFE,E000	StartOfItem	no
FFFE,E00D	EndOfItems	no
FFFE,EODD	EndOfSequence	no

# FITS Tags

This table lists some standard Flexible Image Transport System (FITS) tags, but ExifTool will extract any other tags found. See <a href="https://fits.gsfc.nasa.gov/fits\_standard.html">https://fits.gsfc.nasa.gov/fits\_standard.html</a> for the specification.

Tag ID	Tag Name	Writable
'AUTHOR'	Author	no
'BACKGRND'	Background	no
'COMMENT'	Comment	no
'DATE'	CreateDate	no
'DATE-END'	ObservationDateEnd	no
'DATE-OBS'	ObservationDate	no
'HISTORY'	History	no
'INSTRUME'	Instrument	no
'OBJECT'	Object	no
'OBSERVER'	Observer	no
'REFERENC'	Reference	no
'TELESCOP'	Telescope	no
'TIME-END'	ObservationTimeEnd	no
'TIME-OBS'	ObservationTime	no

## XISF Tags

This table lists some standard Extensible Image Serialization Format (XISF) tags, but ExifTool will extract any other tags found. See <a href="https://pixinsight.com/xisf/">https://pixinsight.com/xisf/</a> for the specification.

Tag ID	Tag Name	Writable
'Abstract'	Abstract	no
'AccessRights'	AccessRights	no
'Authors'	Authors	no
'BibliographicReference	ces'	
	BibliographicReferences	no
'BriefDescription'	BriefDescription	no
'CompressionCodecs'	CompressionCodecs	no
'CompressionLevel'	CompressionLevel	no
'Contributors'	Contributors	no
'Copyright'	Copyright	no
'CreationTime'	CreateDate	no
'CreatorApplication'	CreatorApplication	no
'CreatorModule'	CreatorModule	no
'CreatorOS'	CreatorOS	no
'Description'	Description	no
'ImageBounds'	ImageBounds	no
'ImageColorSpace'	ColorSpace	no
'ImageData'	ImageData	no
'ImageGeometry'	ImageGeometry	no
'ImageICCProfile'	ICC_Profile	no
'ImageICCProfileLocat:	ion' ICCProfileLocation	no
'ImageId'	ImageID	no
'ImageImageType'	ImageType	no
'ImageLocation'	ImageLocation	no
'ImageOffset'	ImagePixelOffset	no
'ImageOrientation'	Orientation	no
'ImagePixelStorage'		no
'ImageResolutionHorizo	ontal' XResolution	no

'ImageResolutionUnit'	ResolutionUnit	no
'ImageResolutionVertic	cal' YResolution	no
'ImageSampleFormat'	ImageSampleFormat	no
'ImageUuid'	UUID	no
'Keywords'	Keywords	no
'Languages'	Languages	no
'License'	License	no
'OriginalCreationTime	' DateTimeOriginal	no
'RelatedResources'	RelatedResources	no
'Title'	Title	no

## HTML Tags

Meta information extracted from the header of HTML and XHTML files. This is a mix of information found in the "META" elements, "XML" element, and the "TITLE" element.

Tag ID	Tag Name	Writable
'abstract'	 Abstract	no
'author'	Author	no
'classification'	Classification	no
'content-language'	ContentLanguage	no
'copyright'	Copyright	no
'dc'	DC	HTML dc
'description'	Description	no
'distribution'	Distribution	no
'doc-class'	DocClass	no
'doc-rights'	DocRights	no
'doc-type'	DocType	no
'formatter'	Formatter	no
'generator'	Generator	no
'generatorversion'	GeneratorVersion	no
'googlebot'	GoogleBot	no
'http-equiv'	HTTP-equiv	HTML equiv
'keywords'	Keywords	no+
'mssmarttagspreventparsing'	NoMSSmartTags	no
'ncc'	NCC	HTML ncc
' O '	Office	HTML Office
'originator'	Originator	no
'owner'	Owner	no
'prod'	Prod	HTML prod
'progid'	ProgID	no
'rating'	Rating	no
'refresh'	Refresh	no
'resource-type'	ResourceType	no
'revisit-after'	RevisitAfter	no
'robots'	Robots	no+
'title'	Title	no
'vw96'	VW96	HTML vw96

## HTML dc Tags

Dublin Core schema tags (also used in XMP).

Tag ID	Tag Name	Writable
'contributor'	Contributor	no+
'coverage'	Coverage	no
'creator'	Creator	no+
'date'	Date	no+
'description'	Description	no
'format'	Format	no
'identifier'	Identifier	no
'language'	Language	no+
'publisher'	Publisher	no+
'relation'	Relation	no+
'rights'	Rights	no
'source'	Source	no
'subject'	Subject	no+
'title'	Title	no

'type' Type no+

# HTML equiv Tags

These tags have a family 1 group name of "HTTP-equiv".

Tag ID	Tag Name	Writable
'cache-control'	CacheControl	no
'content-disposition'	ContentDisposition	no
'content-language'	ContentLanguage	no
<pre>'content-script-type'</pre>	ContentScriptType	no
'content-style-type'	ContentStyleType	no
'content-type'	ContentType	no
'default-style'	DefaultStyle	no
'expires'	Expires	no
'ext-cache'	ExtCache	no
'imagetoolbar'	ImageToolbar	no
'lotus'	Lotus	no
'page-enter'	PageEnter	no
'page-exit'	PageExit	no
'pics-label'	PicsLabel	no
'pragma'	Pragma	no
'refresh'	Refresh	no
'reply-to'	ReplyTo	no
'set-cookie'	SetCookie	no
'site-enter'	SiteEnter	no
'site-exit'	SiteExit	no
'vary'	Vary	no
'window-target'	WindowTarget	no

## <u>HTML</u> ncc Tags

Tag ID	Tag Name	Writable
 'charset'	 CharacterSet	no
'depth'	Depth	no
'files'	Files	no
'footnotes'	Footnotes	no
'generator'	Generator	no
'kbytesize'	KByteSize	no
'maxpagenormal'	MaxPageNormal	no
'multimediatype'	MultimediaType	no
'narrator'	Narrator	no
'pagefront'	PageFront	no
'pagenormal'	PageNormal	no
'pagespecial'	PageSpecial	no
'prodnotes'	ProdNotes	no
'produceddate'	ProducedDate	no
'producer'	Producer	no
'revision'	Revision	no
'revisiondate'	RevisionDate	no
'setinfo'	SetInfo	no
'sidebars'	Sidebars	no
'sourcedate'	SourceDate	no
'sourceedition'	SourceEdition	no
'sourcepublisher'	SourcePublisher	no
'sourcerights'	SourceRights	no
'sourcetitle'	SourceTitle	no
'tocitems'	TOCItems	no
'totaltime'	Duration	no

# HTML Office Tags

Tags written by Microsoft Office applications.

Tag ID	Tag Name	Writable
'Author'	Author	no
'Category'	Category	no

'Characters'	Characters	no
'CharactersWithSpaces'	CharactersWithSpaces	no
'Company'	Company	no
'Created'	CreateDate	no
'Description'	Description	no
'Keywords'	Keywords	no
'LastAuthor'	LastAuthor	no
'LastPrinted'	LastPrinted	no
'LastSaved'	ModifyDate	no
'Lines'	Lines	no
'Manager'	Manager	no
'Pages'	Pages	no
'Paragraphs'	Paragraphs	no
'Revision'	RevisionNumber	no
'Subject'	Subject	no
'Template'	Template	no
'TotalTime'	TotalEditTime	no
'Version'	RevisionNumber	no
'Words'	Words	no

### HTML prod Tags

Tag ID	Tag Name	Writable
'recengineer'	RecEngineer	no
'reclocation'	RecLocation	no

## HTML vw96 Tags

Tag ID	Tag Name	Writable
'objecttype'	ObjectType	no

#### Palm Tags

Information extracted from Palm database files (PDB and PRC extensions), Mobipocket electronic books (MOBI), and Amazon Kindle KF7 and KF8 books (AZW and AZW3).

Index4	Tag Name	Writable
0	DatabaseName	no
9	CreateDate	no
10	ModifyDate	no
11	LastBackupDate	no
12	ModificationNumber	no
15	PalmFileType	no

## Palm MOBI Tags

Information extracted from the MOBI header of Mobipocket and Amazon Kindle KF7 and KF8 files.

Index4	Tag Name	Writable
0	Compression	no
1	UncompressedTextLength	no
3	Encryption	no
6	MobiType	no
7	CodePage	no
9	MobiVersion	no
21	BookName	no
26	MinimumVersion	no

### Palm EXTH Tags

Information extracted from the MOBI extended header.

Tag ID	Tag Name	Writable
0x0001	DRMServerID	no

00000	DDMGammaraaa		
$0 \times 0002$ $0 \times 0003$	DRMCommerceID		10
0x0003 $0x0064$	DRM_E-BookBaseID Author		10
0x0064	Publisher		10
0x0065	Imprint		10
0x0066	Description		10
0x0067	ISBN		10
0x0069	Subject		.10 10+
0x0069	PublishDate		10+
0x006b	Review		10
0x006c	Contributor		10
0x006d	Rights		10
0x006e	SubjectCode		10
0x006f	BookType		10
0x0001	Source		10
0x0070 0x0071	ASIN		10
0x0071 0x0072	BookVersion		10
0x0072	SampleFlag		10
0x0073	StartReading		10
0x0071	Adult		10
0x0075	RetailPrice		10
0x0070	RetailPriceCurrency		10
0x007d	ResourceCount		10
0x0081	KF8CoverURI		10
0x00c8	DictionaryShortName		10
0x00cc	CreatorSoftware		10
0x00cd	CreatorMajorVersion		10
0x00ce	CreatorMinorVersion		10
0x00cf	CreatorBuildNumber		10
0x00d0	Watermark		10
0x00d1	Tamper-proofKeys		10
0x0191	ClippingLimit		10
0x0192	PublisherLimit		10
0x0194	TextToSpeech		10
0x0195	RentalFlag		10
0x0196	RentalExpirationDate		10
0x01f5	CDEType		10
0x01f6	LastUpdateTime		10
0x01f7	UpdatedTitle		10
0x01f8	ASIN2		10
0x020c	Language		10
0x020d	Alignment		10
0x0217	CreatorBuildNumber2		10
		-	

#### Torrent Tags

Below are tags commonly found in BitTorrent files. As well as these tags, any other existing tags will be extracted. For convenience, list items are expanded into individual tags with an index in the tag name, but only the tags with index "1" are listed in the tables below. See <a href="https://wiki.theory.org/BitTorrentSpecification">https://wiki.theory.org/BitTorrentSpecification</a>> for the BitTorrent specification.

Tag ID	Tag Name	Writable
'announce'	Announce	no
'announce-list'	AnnounceList1	no
'comment'	Comment	no
'created by'	Creator	no
'creation date'	CreateDate	no
'encoding'	Encoding	no
'info'	Info	Torrent Info
'url-list'	URLList1	no

# Torrent Info Tags

Tag ID	Tag Name	Writable
'file-duration'	File1Duration	no
'file-media'	File1Media	no
'files'	Files	Torrent Files

#### -- ExifTool 13.24 Tag Names --

'md5sum'MD5Sumno'name'Nameno'name.utf-8'NameUTF-8no'piece length'PieceLengthno'pieces'Piecesno'private'Privateno	'length'	Length	no
'name.utf-8' NameUTF-8 no 'piece length' PieceLength no 'pieces' Pieces no	'md5sum'	MD5Sum	no
'piece length' PieceLength no 'pieces' Pieces no	'name'	Name	no
'pieces' Pieces no	'name.utf-8'	NameUTF-8	no
1	'piece length'	PieceLength	no
'private' Private no	'pieces'	Pieces	no
	'private'	Private	no

'profiles' Profiles Torrent Profiles

#### Torrent Files Tags

Tag ID	Tag Name	Writable
'length'	File1Length	no
'md5sum'	File1MD5Sum	no
'path'	File1Path	no
'path.utf-8'	File1PathUTF-8	no

#### Torrent Profiles Tags

Tag Name	Writable
Profile1AudioCodec	no
ProfilelHeight	no
Profile1VideoCodec	no
ProfilelWidth	no
	Tag Name Profile1AudioCodec Profile1Height Profile1VideoCodec Profile1Width

### EXE Tags

This module extracts information from various types of Windows, MacOS and Unix executable and library files. The first table below lists information extracted from the header of Windows PE (Portable Executable) EXE files and DLL libraries.

Index2	Tag Name	Writable
0	MachineType	no
2	TimeStamp	no
9	ImageFileCharacteristics	no
10	PEType	no
11	LinkerVersion	no
12	CodeSize	no
14	InitializedDataSize	no
16	UninitializedDataSize	no
18	EntryPoint	no
30	OSVersion	no
32	ImageVersion	no
34	SubsystemVersion	no
44	Subsystem	no

## EXE PEVersion Tags

Information extracted from the VS\_VERSION\_INFO structure of Windows PE files.

Index4	Tag Name	Writable
2	FileVersionNumber	no
4	ProductVersionNumber	no
6	FileFlagsMask	no
7	FileFlags	no
8	FileOS	no
9	ObjectFileType	no
10	FileSubtype	no

### EXE PEString Tags

Resource strings found in Windows PE files. The TagID's are not shown because they are the same as the Tag Name. ExifTool will extract any existing StringFileInfo tags even if not listed in this table.

Tag Name	Writable
BuildDate	no
BuildVersion	no
CharacterSet	no
Comments	no
CompanyName	no
Copyright	no
FileDescription	no
FileVersion	no
InternalName	no
LanguageCode	no
LegalCopyright	no
LegalTrademarks	no
OriginalFileName	no
PrivateBuild	no
ProductName	no
ProductVersion	no
SpecialBuild	no

#### EXE DebugRSDS Tags

CodeView RSDS debug information found in some Windows EXE files.

Index1	Tag Name	Writable
0	PDBModifyDate	no
20	PDBAge	no
24	PDBFileName	no

### EXE DebugNB10 Tags

CodeView NB10 debug information found in some Windows EXE files.

Index1	Tag Name	Writable
0	PDBModifyDate	no
8	PDBCreateDate	no
12	PDBAge	no
16	PDBFileName	no

## EXE Misc Tags

Miscellaneous CodeView debug information in Windows EXE files.

Index1	Tag Name	Writable
12	EXEFileName	no

## EXE MachO Tags

Information extracted from Mach-O (Mac OS X) executable files and DYLIB libraries.

Index	Tag Name	Writable
0	CPUArchitecture	no
1	CPUByteOrder	no
2	CPUCount	no
3	CPUType	no+
4	CPUSubtype	no+
5	ObjectFileType	no
6	ObjectFlags	no

### EXE PEF Tags

Information extracted from PEF (Classic MacOS) executable files and libraries.

Index4 Tag Name

Writable

2	CPUArchitecture	no
3	PEFVersion	no
4	TimeStamp	no

### EXE ELF Tags

Information extracted from  ${\tt ELF}$  (Unix) executable files and  ${\tt SO}$  libraries.

## EXE AR Tags

Information extracted from static libraries.

Index1	Tag Name	Writable
16	CreateDate	no

## EXE CHM Tags

Index1 Tag Name

Tags extracted from Microsoft Compiled HTML files.

Index4	Tag Name	Writable
1	CHMVersion	no
5	LanguageCode	no

# LNK Tags

Information extracted from MS Shell Link (Windows shortcut) files.

Writable

$0 \times 0014$	Flags	no	
0x0018	FileAttributes	no	
0x001c	CreateDate	no	
$0 \times 0024$	AccessDate	no	
0x002c	ModifyDate	no	
$0 \times 0034$	TargetFileSize	no	
0x0038	IconIndex	no	
0x003c	RunWindow	no	
$0 \times 0040$	HotKey	no	
0x10000	ItemID	LNK	ItemID
0x20000	LinkInfo	LNK	LinkInfo
0x30004	Description	no	
0x30008	RelativePath	no	
0x30010	WorkingDirectory	no	
0x30020	CommandLineArguments	no	
$0 \times 30040$	IconFileName	no	
0xa0000000	UnknownData	LNK	UnknownData
0xa0000001	EnvVarData	LNK	UnknownData
0xa0000002	ConsoleData	LNK	ConsoleData
0xa0000003	TrackerData	LNK	TrackerData
0xa0000004	ConsoleFEData	LNK	ConsoleFEData
0xa0000005	SpecialFolderData	LNK	UnknownData
0xa0000006	DarwinData	LNK	UnknownData
0xa0000007	IconEnvData	LNK	UnknownData
0xa0000008	ShimData		UnknownData
0xa0000009	PropertyStoreData		UnknownData
0xa000000b	KnownFolderData	LNK	UnknownData
0xa000000c	VistaIDListData	LNK	UnknownData

Tag ID	Tag Name	Writable
$0 \times 0032$	Item0032	LNK Item0032

## LNK Item0032 Tags

Index1	Tag Name	Writable
14	TargetFileDOSName	no

### LNK LinkInfo Tags

Tag Name	Writable
CommonNetworkRelLink	no
CommonPathSuffix	no
DeviceName	no
DriveSerialNumber	no
DriveType	no
LocalBasePath	no
NetName	no
NetProviderType	no
VolumeID	no
VolumeLabel	no

## LNK UnknownData Tags

Index1	Tag Name	Writable
[no tags	known]	

## LNK ConsoleData Tags

Index1	Tag Name	Writable
8	FillAttributes	no
10	PopupFillAttributes	no
12	ScreenBufferSize	no
16	WindowSize	no
20	WindowOrigin	no
32	FontSize	no
36	FontFamily	no
40	FontWeight	no
44	FontName	no
108	CursorSize	no
112	FullScreen	no
116	QuickEdit	no
120	InsertMode	no
124	WindowOriginAuto	no
128	HistoryBufferSize	no
132	NumHistoryBuffers	no
136	RemoveHistoryDuplicates	no

## LNK TrackerData Tags

Index1	Tag Name	Writable
16	MachineID	no

## LNK ConsoleFEData Tags

Index1	Tag Name	Writable
8	CodePage	no

## PCAP Tags

Tags extracted from CAP, PCAP and PCAPNG Packet Capture files.

### -- ExifTool 13.24 Tag Names --

Comment	no
CustomOption1	no
CustomOption2	no
CustomOption3	no
CustomOption3	no
ByteOrder	no
DeviceName	no
Description	no
IPv4Addr	no
IPv6Addr	no
MACAddr	no
EUIAddr	no
Speed	no
TimeStampResolution	no
TimeZone	no
Filter	no
OperatingSytem	no
FCSLen	no
TimeStampOffset	no
Hardware	no
TXSpeed	no
RXSpeed	no
TimezoneName	no
LinkType	no
PCAPVersion	no
Hardware	no
OperatingSytem	no
UserApplication	no
TimeStamp	no
	CustomOption1 CustomOption2 CustomOption3 CustomOption3 ByteOrder DeviceName Description IPv4Addr IPv6Addr MACAddr EUIAddr Speed TimeStampResolution TimeZone Filter OperatingSytem FCSLen TimeStampOffset Hardware TXSpeed RXSpeed RXSpeed TimezoneName LinkType PCAPVersion Hardware UserApplication

#### Font Tags

This table contains a collection of tags found in font files of various formats. ExifTool current recognizes OTF, TTF, TTC, DFONT, PFA, PFB, PFM, AFM, ACFM and AMFM font files.

Tag ID	Tag Name	Writable
'AFM'	AFM	Font AFM
'C2PA'	C2PA	Jpeg2000
'PFM'	PFMHeader	Font PFM
'PSInfo'	PSFontInfo	Font PSInfo
'fontname'	FontName	no
'name'	Name	Font Name
'numfonts'	NumFonts	no
'postfont'	PostScriptFontName	no

### Font AFM Tags

Tags extracted from Adobe Font Metrics files (AFM, ACFM and AMFM).

Tag ID	Tag Name	Writable
'Ascender'	Ascender	no
'CapHeight'	CapHeight	no
'CharacterSet'	CharacterSet	no
'Characters'	Characters	no
'Creation Date'	CreateDate	no
'Descender'	Descender	no
'EncodingScheme'	EncodingScheme	no
'EscChar'	EscChar	no
'FamilyName'	FontFamily	no
'FontName'	FontName	no
'FullName'	FullName	no
'IsBaseFont'	IsBaseFont	no
'IsFixedV'	IsFixedV	no
'MappingScheme'	MappingScheme	no
'Notice'	Notice	no
'Version'	Version	no
'Weight'	Weight	no
'XHeight'	XHeight	no

## Font PFM Tags

Tags extracted from the PFM file header.

Index1	Tag Name	Writable
0	PFMVersion	no
6	Copyright	no
66	FontType	no
68	PointSize	no
70	YResolution	no
72	XResolution	no
74	Ascent	no
76	InternalLeading	no
78	ExternalLeading	no
80	Italic	no
81	Underline	no
82	Strikeout	no
83	Weight	no
85	CharacterSet	no
86	PixWidth	no
88	PixHeight	no
90	PitchAndFamily	no
91	AvgWidth	no
93	MaxWidth	no
95	FirstChar	no
96	LastChar	no
97	DefaultChar	no
98	BreakChar	no
99	WidthBytes	no

### Font PSInfo Tags

Tags extracted from PostScript font files (PFA and PFB).

Tag ID	Tag Name	Writable
'Copyright'	Copyright	no
'FSType'	FSType	no
'FamilyName'	FontFamily	no
'FontName'	FontName	no
'FontType'	FontType	no
'FullName'	FullName	no
'ItalicAngle'	ItalicAngle	no
'Notice'	Notice	no
'UnderlinePosition'	UnderlinePosition	no
'UnderlineThickness'	UnderlineThickness	no
'Weight'	Weight	no
'isFixedPitch'	IsFixedPitch	no
'version'	Version	no

### Font Name Tags

The following tags are extracted from the TrueType font "name" table found in OTF, TTF, TTC and DFONT files. These tags support localized languages by adding a hyphen followed by a language code to the end of the tag name (eg. "Copyright-fr" or "License-en-US"). Tags with no language code use the default language of "en".

Tag ID	Tag Name	Writable
0x0000	Copyright	no
$0 \times 0001$	FontFamily	no
0x0002	FontSubfamily	no
0x0003	FontSubfamilyID	no
$0 \times 0004$	FontName	no
$0 \times 0005$	NameTableVersion	no
0x0006	PostScriptFontName	no
0x0007	Trademark	no

0x0008	Manufacturer	no
0x0009	Designer	no
0x000a	Description	no
0x000b	VendorURL	no
0x000c	DesignerURL	no
0x000d	License	no
0x000e	LicenseInfoURL	no
$0 \times 0010$	PreferredFamily	no
$0 \times 0011$	PreferredSubfamily	no
$0 \times 0012$	CompatibleFontName	no
$0 \times 0013$	SampleText	no
$0 \times 0014$	PostScriptFontName	no
0x0015	WWSFamilyName	no
$0 \times 0016$	WWSSubfamilyName	no

#### VCard Tags

This table lists common vCard tags, but ExifTool will also extract any other vCard tags found. Tag names may have "Pref" added to indicate the preferred instance of a vCard property, and other "TYPE" parameters may also added to the tag name. VCF files may contain multiple vCard entries which are distinguished by the ExifTool family 3 group name (document number). See <a href="http://tools.ietf.org/html/rfc6350">http://tools.ietf.org/html/rfc6350</a> for the vCard 4.0 specification.

Tag ID	Tag Name	Writable
'Adr'	Address	no
'Anniversary'	Anniversary	no
'Bday'	Birthday	no
'Email'	Email	no
'Fn'	FormattedName	no
'Gender'	Gender	no
'Geo'	Geolocation	no
'Impp'	IMPP	no
'Lang'	Language	no
'Logo'	Logo	no
'N'	Name	no
'Nickname'	Nickname	no
'Note'	Note	no
'Org'	Organization	no
'Photo'	Photo	no
'Prodid'	Software	no
'Rev'	Revision	no
'Sound'	Sound	no
'Tel'	Telephone	no
'Title'	JobTitle	no
'Tz'	TimeZone	no
'Uid'	UID	no
'Url'	URL	no
'Version'	VCardVersion	no
'X-abdate'	ABDate	no
'X-ablabel'	ABLabel	no
'X-abrelatednames'	ABRelatedNames	no
'X-abuid'	AB_UID	no
'X-aim'	AIM	no
'X-icq'	ICQ	no
'X-socialprofile'	SocialProfile	no

#### <u>VCard</u> <u>VCalendar</u> <u>Tags</u>

The VCard module is also used to process iCalendar ICS files since they use a format similar to vCard. The following table lists standard iCalendar tags, but any existing tags will be extracted. Top-level iCalendar components (eg. Event, Todo, Timezone, etc.) are used for the family 1 group names, and embedded components (eg. Alarm) are added as a prefix to the tag name. See <a href="http://tools.ietf.org/html/rfc5545">http://tools.ietf.org/html/rfc5545</a> for the official iCalendar 2.0 specification.

Tag ID	Tag Name	Writable

	ExifTool 13.24 Tag Names -	-
'Acknowledged'	Acknowledged	no
'Action'	Action	no
'Attach'	Attachment	no
'Attendee'	Attendee	no
'Calscale'	CalendarScale	no
'Categories'	Categories	no
'Class'	Classification	no
'Comment'	Comment	no
'Completed'	DateTimeCompleted	no
'Contact' 'Created'	Contact DateCreated	no
'Description'	Description	no no
'Dtend'	DateTimeEnd	no
'Dtstamp'	DateTimeStamp	no
'Dtstart'	DateTimeStart	no
'Due'	DateTimeDue	no
'Duration'	Duration	no
'Exdate'	ExceptionDateTimes	no
'Freebusy'	FreeBusyTime	no
'Geo'	Geolocation	no
'Last-modified'	ModifyDate	no
'Location'	Location	no
'Method'	Method	no
'Organizer'	Organizer	no
'Percent-complete'	PercentComplete	no
'Priority'	Priority	no
'Prodid' 'Rdate'	Software RecurrenceDateTimes	no
'Recurrence-id'	RecurrenceID	no no
'Related-to'	RelatedTo	no
'Repeat'	Repeat	no
'Request-status'	RequestStatus	no
'Resources'	Resources	no
'Rrule'	RecurrenceRule	no
'Sequence'	SequenceNumber	no
'Status'	Status	no
'Summary'	Summary	no
'Transp'	TimeTransparency	no
'Trigger'	Trigger	no
'Tzid'	TimezoneID	no
'Tzname'	TimezoneName	no
'Tzoffsetfrom' 'Tzoffsetto'	TimezoneOffsetFrom TimezoneOffsetTo	no
'Tzurl'	TimeZoneURL	no no
'Uid'	UID	no
'Url'	URL	no
'Version'	VCalendarVersion	no
	color' CalendarColor	no
'X-apple-default-al		no
'X-apple-local-defa	ault-alarm'	
	LocalDefaultAlarm	no
	lldayevent' AllDayEvent	no
'X-microsoft-cdo-ap		
	AppointmentSequence	no
	usystatus' BusyStatus	no
	mportance' Importance	no
'X-microsoft-cdo-in	nsttype' InstanceType	no
X-IIIICIOSOI L-CUO-III	IntendedBusyStatus	no
'X-microsoft-cdo-ow		110
n microsoft edo ow	OwnerAppointmentID	no
'X-microsoft-disall		
1_1.010 010011	DisallowCounterProposal	no
'X-microsoft-donotf		-
	DoNotForwardMeeting	no
'X-microsoft-locati	ions' MeetingLocations	no
'X-wr-alarmuid'	AlarmUID	no
'X-wr-caldesc'	CalendarDescription	no
'X-wr-calname'	CalendarName	no
'X-wr-relcalid'	CalendarID	no

'X-wr-timezone' TimeZone2 no

## <u>VCard</u> <u>VNote</u> <u>Tags</u>

Tags extracted from V-Note VNT files.

Tag ID	Tag Name	Writable
'Body'	Body	no
'Dcreated'	CreateDate	no
'Last-modified'	ModifyDate	no
'Version'	Version	no

## Text Tags

Although basic text files contain no metadata, the following tags are determined from a simple analysis of the data in TXT and CSV files. Statistics are generated only for 8-bit encodings, but the FastScan (-fast) option may be used to limit processing to the first 64 KiB in which case some tags are not produced. To avoid long processing delays, ExifTool will issue a minor warning and process only the first 64 KiB of any file larger than 20 MiB unless the IgnoreMinorErrors (-m) option is used.

Tag Name	Writable
ByteOrderMark	no
ColumnCount	no
Delimiter	no
LineCount	no
MIMEEncoding	no
Newlines	no
Quoting	no
RowCount	no
WordCount	no

## RSRC Tags

Tags extracted from Mac OS resource files, DFONT files and ".\_" sidecar files. These tags may also be extracted from the resource fork of any file in OS X, either by adding "/..namedfork/rsrc" to the filename to process the resource fork alone, or by using the ExtractEmbedded (-ee) option to process the resource fork as a sub-document of the main file. When writing, ExifTool preserves the Mac OS resource fork by default, but it may deleted with "-rsrc:all=" on the command line.

Tag ID	Tag Name	Writable
'8BIM'	PhotoshopInfo	Photoshop
'POST_0x01f5'	PostscriptFont	PostScript
'STR _0xbff3'	ApplicationMissingMsg	no
'STR _0xbff4'	CreatorApplication	no
'STR#_0x0080'	Keywords	no
'TEXT_0x0080'	Description	no
'sfnt'	Font	Font Name
'usro_0x0000'	OpenWithApplication	no
'vers_0x0001'	ApplicationVersion	no

#### Rawzor Tags

Rawzor files store compressed images of other formats. As well as the information listed below, exiftool uncompresses and extracts the meta information from the original image.

Tag Name	Writable
CompressionFactor	no
OriginalFileSize	no
OriginalFileType	no
RawzorCreatorVersion	no
RawzorRequiredVersion	no

The following tags are extracted from ZIP archives. ExifTool also extracts additional meta information from compressed documents inside some ZIP-based files such Office Open XML (DOCX, PPTX and XLSX), Open Document (ODB, ODC, ODF, ODG, ODI, ODP, ODS and ODT), iWork (KEY, PAGES, NUMBERS), Capture One Enhanced Image Package (EIP), Adobe InDesign Markup Language (IDML), Electronic Publication (EPUB), and Sketch design files (SKETCH). The ExifTool family 3 groups may be used to organize ZIP tags by embedded document number (ie. the exiftool "-g3" option).

Index2	Tag Name	Writable
2	ZipRequiredVersion	no
3	ZipBitFlag	no
4	ZipCompression	no
5	ZipModifyDate	no
7	ZipCRC	no
9	ZipCompressedSize	no
11	ZipUncompressedSize	no
15	ZipFileName	no
'_com'	ZipFileComment	no

#### ZIP GZIP Tags

These tags are extracted from GZIP (GNU ZIP) archives, but currently only for the first file in the archive.

Index1	Tag Name	Writable
2	Compression	no
3	Flags	no
4	ModifyDate	no
8	ExtraFlags	no
9	OperatingSystem	no
10	ArchivedFileName	no
11	Comment	no

## ZIP RAR Tags

These tags are extracted from RAR archive files.

Index1	Tag Name	Writable
0	CompressedSize	no
4	UncompressedSize	no
8	OperatingSystem	no
13	ModifyDate	no
18	PackingMethod	no
25	ArchivedFileName	no

#### ZIP RAR5 Tags

These tags are extracted from RAR v5 and 7z archive files.

Tag Name	Writable
ArchivedFileName	no
CompressedSize	no
FileVersion	no
ModifyDate	no
OperatingSystem	no
UncompressedSize	no

## RTF Tags

This table lists standard tags of the RTF information group, but ExifTool will also extract any non-standard tags found in this group. As well, ExifTool will extract any custom properties that are found. See <a href="http://www.microsoft.com/en-ca/download/details.aspx?id=10725">http://www.microsoft.com/en-ca/download/details.aspx?id=10725</a> for the specification.

Tag ID	Tag Name	Writable
'author'	Author	no
'buptim'	BackupTime	no
'category'	Category	no
'comment'	Comment	no
'company'	Company	no
'copyright'	Copyright	no
'creatim'	CreateDate	no
'doccomm'	Comments	no
'edmins'	TotalEditTime	no
'hlinkbase'	HyperlinkBase	no
'id'	InternalIDNumber	no
'keywords'	Keywords	no
'manager'	Manager	no
'nofchars'	Characters	no
'nofcharsws'	CharactersWithSpaces	no
'nofpages'	Pages	no
'nofwords'	Words	no
'operator'	LastModifiedBy	no
'printim'	LastPrinted	no
'revtim'	ModifyDate	no
'subject'	Subject	no
'title'	Title	no
'vern'	InternalVersionNumber	no
'version'	RevisionNumber	no

## OOXML Tags

The Office Open XML (OOXML) format was introduced with Microsoft Office 2007 and is used by file types such as DOCX, PPTX and XLSX. These are essentially ZIP archives containing XML files. The table below lists some tags which have been observed in OOXML documents, but ExifTool will extract any tags found from XML files of the OOXML document properties ("docProps") directory.

## Tips:

- 1) Structural ZIP tags may be ignored (if desired) with "--ZIP:all" on the command line.
- 2) Tags may be grouped by their document number in the ZIP archive with the "-g3" or "-G3" option.

Tag Name	Writable
AppVersion	no
Application	no
Category	no
Characters	no
CharactersWithSpaces	no
CheckedBy	no
Client	no
Company	no
CreateDate	no
DateCompleted	no
Department	no
Destination	no
Disposition	no
Division	no
DocSecurity	no
DocumentNumber	no
Editor	no
ForwardTo	no
Group	no
HeadingPairs	no
HiddenSlides	no
HyperlinkBase	no
HyperlinksChanged	no
Keywords	no
Language	no

LastModifiedBy	no
LastPrinted	no
Lines	no
LinksUpToDate	no
MMClips	no
Mailstop	no
Manager	no
Matter	no
ModifyDate	no
Notes	no
Office	no
Owner	no
Pages	no
Paragraphs	no
PresentationFormat	no
Project	no
Publisher	no
Purpose	no
ReceivedFrom	no
RecordedBy	no
RecordedDate	no
Reference	no
RevisionNumber	no
ScaleCrop	no
SharedDoc	no
Slides	no
Source	no
Status	no
TelephoneNumber	no
Template	no
TitlesOfParts	no
TotalEditTime	no
Typist	no
Words	no

## iWork Tags

The Apple iWork '09 file format is a ZIP archive containing XML files similar to the Office Open XML (OOXML) format. Metadata tags in iWork files are extracted even if they don't appear below.

Tag Name	Writable
Author	no
Comment	no
Copyright	no
Keywords	no
Projects	no+
Title	no

# ISO Tags

Tags extracted from ISO 9660 disk images.

Tag ID	Tag Name	Writable
0x0000	BootRecord	ISO BootRecord
$0 \times 0001$	PrimaryVolume	ISO PrimaryVolume

# ISO BootRecord Tags

Index1	Tag Name	Writable
7	BootSystem	no
39	BootIdentifier	no

## ISO PrimaryVolume Tags

Writable
no
e no

80	VolumeBlockCount	no
120	VolumeSetDiskCount?	no
124	VolumeSetDiskNumber?	no
128	VolumeBlockSize	no
132	PathTableSize?	no
140	PathTableLocation?	no
174	RootDirectoryCreateDate	no
190	VolumeSetName	no
318	Publisher	no
446	DataPreparer	no
574	Software	no
702	CopyrightFileName	no
740	AbstractFileName	no
776	BibligraphicFileName	no
813	VolumeCreateDate	no
830	VolumeModifyDate	no
847	VolumeExpirationDate	no
864	VolumeEffectiveDate	no

## MacOS Tags

On MacOS systems, the there are additional MDItem and XAttr Finder tags that may be extracted. These tags are not extracted by default -- they must be specifically requested or enabled via an API option. (Except when reading MacOS ".\_" files directly, see below.)

The tables below list some of the tags that may be extracted, but ExifTool will extract all available information even for tags not listed.

Tags in these tables are referred to as "pseudo" tags because their information is not stored in the file itself. As such, Writable tags in these tables may be changed without having to rewrite the file.

Note that on some filesystems, MacOS creates sidecar files with names that begin with ".\_". ExifTool will read these files if specified, and extract the information listed in the following table without the need for extra options, but these files are not writable directly.

Tag ID	Tag Name	Writable
$0 \times 0002$	RSRC	RSRC
$0 \times 0009$	ATTR	MacOS XAttr

## MacOS XAttr Tags

XAttr tags are extracted using the "xattr" utility. They are extracted if any "XAttr\*" tag or the MacOS group is specifically requested, or by setting the API XAttrTags option to 1 or the API RequestAll option to 2 or higher. And they are extracted by default from MacOS ".\_" files when reading these files directly.

Tag Name	Writable
XAttrAppleMailDateReceived	no
XAttrAppleMailDateSent	no
XAttrAppleMailIsRemoteAttachment	no
XAttrFinderInfo	no
XAttrLastUsedDate	no
XAttrMDItemDownloadedDate	no
XAttrMDItemFinderComment	no
XAttrMDItemWhereFroms	yes!
XAttrMDLabel	no
XAttrQuarantine	yes!
XAttrResourceFork	no

## MacOS MDItem Tags

MDItem tags are extracted using the "mdls" utility. They are extracted if any "MDItem\*" tag or the MacOS group is specifically requested, or by setting the API MDItemTags option to 1 or the API RequestAll option

to 2 or higher. Note that these tags do not necessarily reflect the current metadata of a file -- it may take some time for the MacOS mdworker daemon to index the file after a metadata change.

Tag Name	Writable
AppleMailDateReceived	no
AppleMailDateSent	no
AppleMailFlagged AppleMailIsRemoteAttachment	no
AppleMailMessageID	no no
AppleMailPriority	no
AppleMailRead	no
AppleMailRepliedTo	no
MDItemAccountHandles	no
MDItemAccountIdentifier	no
MDItemAcquisitionMake	no
MDItemAcquisitionModel MDItemAltitude	no
MDItemAperture	no no
MDItemAudioBitRate	no
MDItemAudioChannelCount	no
MDItemAuthorEmailAddresses	no
MDItemAuthors	no
MDItemBitsPerSample	no
MDItemBundleIdentifier	no
MDItemCity MDItemCodecs	no no
MDItemColorSpace	no
MDItemComment	no
MDItemContentCreationDate	no
MDItemContentCreationDateRanking	no
MDItemContentCreationDate_Ranking	no
MDItemContentModificationDate	no
MDItemContentType	no
MDItemContentTypeTree MDItemContributors	no
MDItemCopyright	no no
MDItemCountry	no
MDItemCreator	no
MDItemDateAdded	no
MDItemDateAdded_Ranking	no
MDItemDescription	no
MDItemDisplayName	no
MDItemDownloadedDate MDItemDurationSeconds	no
MDItemEXIFGPSVersion	no no
MDItemEXIFVersion	no
MDItemEmailConversationID	no
MDItemEncodingApplications	no
MDItemExposureMode	no
MDItemExposureProgram	no
MDItemExposureTimeSeconds	no
MDItemFNumber MDItemFSContentChangeDate	no
MDItemFSCreationDate	no yes!
MDItemFSCreatorCode	no
MDItemFSFinderFlags	no
MDItemFSHasCustomIcon	no
MDItemFSInvisible	no
MDItemFSIsExtensionHidden	no
MDItemFSIsStationery	no .
MDItemFSLabel MDItemFSName	yes!
MDItemFSNodeCount	no no
MDItemFSOwnerGroupID	no
MDItemFSOwnerUserID	no
MDItemFSSize	no
MDItemFSTypeCode	no
MDItemFinderComment	yes!

MDItemFlashOnOff	no
MDItemFocalLength	no
MDItemGPSDateStamp	no
MDItemGPSStatus	no
MDItemGPSTrack	no
MDItemHasAlphaChannel	no
MDItemISOSpeed	no
MDItemIdentifier	no
MDItemImageDirection	no
MDItemInterestingDateRanking	no
MDItemInterestingDate_Ranking	no
MDItemIsApplicationManaged	no
MDItemIsExistingThread	no
MDItemIsLikelyJunk	no
MDItemKeywords	no
MDItemKind	no
MDItemLastUsedDate	no
MDItemLastUsedDate_Ranking	no
MDItemLatitude	no
MDItemLensModel	no
MDItemLogicalSize	no
MDItemLongitude	no
MDItemMailDateReceived_Ranking	no
MDItemMailboxes	no
MDItemMediaTypes	no
MDItemNumberOfPages	no
MDItemOrientation	no
MDItemOriginApplicationIdentifier	no
MDItemOriginMessageID	no
MDItemOriginSenderDisplayName	no
MDItemOriginSenderHandle	no
MDItemOriginSubject	no
MDItemPageHeight	no
MDItemPageWidth	no
MDItemPhysicalSize	no
MDItemPixelCount	no
MDItemPixelHeight	no
MDItemPixelWidth	no
MDItemPrimaryRecipientEmailAddresses	no
MDItemProfileName	no
MDItemRecipients	no
MDItemRedEyeOnOff	no
MDItemResolutionHeightDPI	no
MDItemResolutionWidthDPI	no
MDItemSecurityMethod	no
MDItemSpeed	no
MDItemStateOrProvince	no
MDItemStreamable	no
MDItemSubject	no
MDItemTimestamp	no
MDItemTitle	no
MDItemTotalBitRate	no
MDItemUseCount	no
MDItemUsedDates	no
MDItemUserDownloadedDate	no
MDItemUserDownloadedUserHandle	no
MDItemUserSharedReceivedDate	no
MDItemUserSharedReceivedRecipient	no
MDItemUserSharedReceivedRecipientHandle	no
MDItemUserSharedReceivedSender	no
MDItemUserSharedReceivedSenderHandle	no
MDItemUserSharedReceivedTransport	no
MDItemUserTags	yes!+
MDItemVersion	no
MDItemVideoBitRate	no
MDItemWhereFroms MDItemWhiteBalance	no
MIDITEHHMITTERATATICE	no

# Extra Tags

The  $\operatorname{\bar{e}xtra}$  tags provide extra features or extra information extracted or

generated by ExifTool that is not directly associated with another tag group. The Group column lists the family 1 group name when reading. Tags with a "-" in this column are write-only.

Tags in the family 1 "System" group are referred to as "pseudo" tags because they don't represent real metadata in the file. Instead, this information is stored in the directory structure of the filesystem. The Writable System "pseudo" tags in this table may be written without modifying the file itself. The TestName tag is used for dry-run testing before writing FileName.

Tag Name	Group	Writable
Adobe	Adobe	yes!
BaseName	System	no
CanonDR4	CanonVRD	yes!^
CanonVRD	CanonVRD	yes!^
Comment	File	yes
CurrentIPTCDigest	File	no
Directory	System	yes!
EXIF	EXIF	yes!
EmbeddedVideo	File	no
Error	ExifTool	no
ExifByteOrder	File	yes
ExifToolVersion	ExifTool	no
ExifUnicodeByteOrder	_	yes
FileAccessDate	System	no
FileAttributes	System	no
FileBlockCount	System	no
FileBlockSize	System	no
FileCreateDate	System	yes!
FileDeviceID	System	no
FileDeviceNumber	System	no .
FileGroupID	System	yes!
FileHardLinks	System	no
FileInodeChangeDate	System	no
FileInodeNumber	System	no .
FileModifyDate	System	yes!
FileName	System	yes!
FilePath	System	no .
FilePermissions	System	yes!
FileSequence	ExifTool	no
FileSize	System File	no
FileType		no
FileTypeExtension FileUserID	File	no
ForceWrite	System	yes!
Geolocate	_	yes
GeolocationBearing	ExifTool	yes no
GeolocationCity	ExifTool	no
GeolocationCountry	ExifTool	no
GeolocationCountryCode	ExifTool	no
GeolocationDistance	ExifTool	no
GeolocationFeatureCode	ExifTool	no
GeolocationFeatureType	ExifTool	no
GeolocationPopulation	ExifTool	no
GeolocationPosition	ExifTool	no
GeolocationRegion	ExifTool	no
GeolocationSubregion	ExifTool	no
GeolocationTimeZone	ExifTool	no
GeolocationWarning	ExifTool	no
Geosync	_	yes
Geotag	_	yes
Geotime	_	yes
HardLink	_	yes!
ICC_Profile	ICC_Profile	yes!
ID3Size	File	no
IPTC	IPTC	yes!
ImageDataHash	File	no
ImageHeight	File	no

ImageWidth	File	no
JPEGDigest	File	no
JPEGImageLength	File	no
JPEGQualityEstimate	File	no
JUMBF	JUMBF	no
MIMEType	File	no
MaxVal	File	no
NewGUID	ExifTool	no
Now	ExifTool	no
NumPlanes	File	no
OtherImage	File	no
PageCount	File	no
PreviewImage	File	yes
PreviewJXL	File	no
PreviewPDF	File	no
PreviewPNG	File	no
PreviewTIFF	File	no
PreviewWMF	File	no
ProcessingTime	ExifTool	no
RAFCompression	File	no
RAFVersion	File	no
ResourceForkSize	System	no
SphericalVideoXML	GSpherical	yes!
SymLink	_	yes!
TestName	_	yes!
ThumbnailImage	File	no
Trailer	File	yes!
Validate	ExifTool	no
Warning	ExifTool	no
XML	XML	no
XMP	XMP	yes!
XResolution	File	no
YResolution	File	no
ZoneIdentifier	System	yes!

## Composite Tags

The values of the composite tags are Derived From the values of other tags. These are convenience tags which are calculated after all other information is extracted. Only a few of these tags are writable directly, the others are changed by writing the corresponding Derived From tags. User-defined Composite tags, also useful for custom-formatting of tag values, may created via the ExifTool configuration file.

Tag Name	Derived From	Writable
AdvancedSceneMode	Model SceneMode AdvancedSceneType	no
Aperture	FNumber ApertureValue	no
AudioBitrate	MPEG:MPEGAudioVersion MPEG:SampleRate MPEG:VBRBytes MPEG:VBRFrames	no
AutoFocus	Nikon:FocusMode	no
AvgBitrate	QuickTime::MediaDataSize QuickTime::Duration	no
BlueBalance	WB_RGGBLevels WB_RGBGLevels WB_RBGGLevels WB_GRBGLevels WB_GRGBLevels WB_GBRGLevels WB_RGBLevels WB_RBLevels WB_RBLevels WB_RBLevels WB_RBLevels WBRBLevels	no
CDDBDiscPlayTime	CDDB1Info	no

# -- ExifTool 13.24 Tag Names --

E:	xifTool 13.24 Tag Names -	-
CDDBDiscTracks	CDDB1Info	no
CFAPattern	CFARepeatPatternDim	no
	CFAPattern2	
CircleOfConfusion	ScaleFactor35ef1	no
ConditionalFEC	FlashExposureComp	no
0011011011011011120	FlashBits	
ContrastDetectAF	Nikon:FocusMode	no
ConcrabeDecedear	Nikon: AFDetectionMethod	110
DOF	FocalLength	no
DOF	Aperture	110
	CircleOfConfusion	
	FocusDistance	
	SubjectDistance	
	ObjectDistance	
	ApproximateFocusDistance	
	FocusDistanceLower	
	FocusDistanceUpper	
DateCreated	Kodak: YearCreated	no
	Kodak:MonthDayCreated	
DateTimeCreated	IPTC:DateCreated	no
	IPTC:TimeCreated	
DateTimeOriginal	DateTimeCreated	no
	DateCreated	
	TimeCreated	
DateTimeOriginal	ID3:RecordingTime	no
	ID3:Year	
	ID3:Date	
	ID3:Time	
DepthMapTiff	DepthMapData	no
	DepthMapWidth	
	DepthMapHeight	
DigitalCreationDateT	ime IPTC:DigitalCreationDa	ate no
	IPTC:DigitalCreationTime	
DigitalZoom	Canon:ZoomSourceWidth	no
	Canon:ZoomTargetWidth	
	Canon:DigitalZoom	
DriveMode	ContinuousDrive	no
	SelfTimer	
Duration	AIFF:SampleRate	no
	AIFF:NumSampleFrames	
Duration	APE:SampleRate	no
	APE:TotalFrames	
	APE:BlocksPerFrame	
	APE:FinalFrameBlocks	
Duration	FLAC:SampleRate	no
	FLAC:TotalSamples	
Duration	FileSize	no
	ID3Size	
	MPEG:AudioBitrate	
	MPEG:VideoBitrate	
	MPEG:VBRFrames	
	MPEG:SampleRate	
	MPEG:MPEGAudioVersion	
Duration	RIFF:FrameRate	no
	RIFF:FrameCount	
	VideoFrameRate	
	VideoFrameCount	
Duration	RIFF: AvgBytesPerSec	no
	FileSize	
	FrameCount	
	VideoFrameCount	
Duration	Vorbis:NominalBitrate	no
	FileSize	
ExtenderStatus	Olympus:Extender	no
	Olympus:LensType	
	MaxApertureValue	
FOV	FocalLength	no
	ScaleFactor35efl	•
	FocusDistance	
FileNumber	DirectoryIndex	yes
	-	_

E	xifTool 13.24 Tag Names	-	
Flash	FileIndex XMP:FlashFired XMP:FlashReturn XMP:FlashMode XMP:FlashFunction XMP:FlashRedEyeMode	yes	
FlashType FocalLength35efl	XMP:Flash FlashBits FocalLength ScaleFactor35ef1	no no	
FocusDistance	Sony: FocusPosition FocalLength	no	
FocusDistance2	Sony:FocusPosition2 FocalLengthIn35mmFormat	no	
GPSAltitude	GPS:GPSAltitude GPS:GPSAltitudeRef XMP:GPSAltitude XMP:GPSAltitudeRef	no	
GPSAltitude GPSAltitude GPSAltitudeRef	QuickTime:GPSCoordinates QuickTime:LocationInforma QuickTime:GPSCoordinates	ation n no	
GPSAltitudeRef GPSDateTime	QuickTime:LocationInforma GPS:GPSDateStamp	ation i no	10
GPSDateTime	GPS:GPSTimeStamp Parrot:GPSLatitude Main:CreateDate SampleTime	no	
GPSDateTime	Sony:GPSDateStamp Sony:GPSTimeStamp	no	
GPSDestLatitude	GPS:GPSDestLatitude GPS:GPSDestLatitudeRef	no	
GPSDestLatitudeRef GPSDestLongitude	XMP-exif:GPSDestLatitude GPS:GPSDestLongitude GPS:GPSDestLongitudeRef	no no	
GPSDestLongitudeRef GPSLatitude	XMP-exif:GPSDestLongitude GPS:GPSLatitude GPS:GPSLatitudeRef	e no yes/	
GPSLatitude	QuickTime:GPSCoordinates		
GPSLatitude GPSLatitude	QuickTime:LocationInforma Sony:GPSLatitude Sony:GPSLatitudeRef	no no	10
GPSLatitudeRef GPSLongitude	XMP-exif:GPSLatitude GPS:GPSLongitude GPS:GPSLongitudeRef	no yes/	
GPSLongitude GPSLongitude	QuickTime:GPSCoordinates QuickTime:LocationInforma		no
GPSLongitude	Sony:GPSLongitude Sony:GPSLongitudeRef	no	
GPSLongitudeRef GPSPosition	XMP-exif:GPSLongitude GPSLatitude GPSLongitude	no yes!	
HiddenData	Sony:HiddenDataOffset Sony:HiddenDataLength	no	
HyperfocalDistance	FocalLength Aperture	no	
IDCPreviewImage	CircleOfConfusion IDCPreviewStart IDCPreviewLength	no	
ISO	Canon:CameraISO Canon:BaseISO	no	
ImageHeight	Canon:AutoISO IFD0:SensorTopBorder IFD0:SensorBottomBorder	no	
ImageHeight	Main:PostScript:ImageData PostScript:BoundingBox	a no	
ImageSize	ImageWidth	no	

ImageHeight

ExifImageWidth
ExifImageHeight
RawImageCroppedSize

# -- ExifTool 13.24 Tag Names --

ImageWidth	IFD0:SensorLeftBorder	no
	IFD0:SensorRightBorder	
ImageWidth	Main:PostScript:ImageData	no
	PostScript:BoundingBox	
JpgFromRaw	JpgFromRawStart	yes
	JpgFromRawLength	
Lens	Canon:MinFocalLength	no
	Canon:MaxFocalLength	
Lens35efl	Canon:MinFocalLength	no
	Canon:MaxFocalLength	
	Lens	
	ScaleFactor35efl	
LensID	LensType	no
	FocalLength	
	MaxAperture -	
	MaxApertureValue	
	MinFocalLength	
	MaxFocalLength	
	LensModel	
	LensFocalRange	
	LensSpec	
	LensType2	
	LensType3	
	LensFocalLength	
T TD	RFLensType	
LensID	LensModel	no
	Lens	
	XMP-aux:LensID	
	Make	
LensID	Nikon:LensIDNumber	no
	LensFStops	
	MinFocalLength	
	MaxFocalLength	
	MaxApertureAtMinFocal	
	MaxApertureAtMaxFocal	
	MCUVersion	
LensID	Nikon:LensType Ricoh:LensFirmware	no
LensID	XMP-aux:LensID	no
Lensid	Make	no
	LensInfo	
	FocalLength	
	LensModel	
	MaxApertureValue	
LensSpec	Nikon:Lens	no
пенаврес	Nikon:LensType	110
LensType	LensTypeMake	no
пспвтурс	LensTypeModel	110
LightValue	Aperture	no
Highe value	ShutterSpeed	110
	ISO	
MPImage	MPImageStart	no
	MPImageLength	
	MPImageType	
Megapixels	ImageSize	no
	OriginalDecisionDataOffse	t yes!
OtherImage	OtherImageStart	yes
	OtherImageLength	-
	OtherImageStart (1)	
	OtherImageLength (1)	
PeakSpectralSensitiv		no
PhaseDetectAF	Nikon:FocusPointSchema	no
	Nikon:AFDetectionMethod	
PreviewImage	PreviewImageStart	yes
	PreviewImageLength	
	PreviewImageValid	
	PreviewImageStart (1)	
	PreviewImageLength (1)	
PreviewImage	ScreenNail	no
PreviewImageSize	PreviewImageWidth	no

PreviewImageHeight PreviewJXL PreviewJXLStart no PreviewJXLLength PreviewJXLStart (1) PreviewJXLLength (1) RedBalance WB\_RGGBLevels no WB\_RGBGLevels WB\_RBGGLevels WB\_GRBGLevels WB\_GRGBLevels WB\_GBRGLevels WB\_RGBLevels WB\_GRBLevels WB\_RBLevels WBRedLevel WBGreenLevel RedEyeReduction CanonFlashMode no FlashBits RicohPitch Ricoh: Accelerometer no RicohRoll Ricoh: Accelerometer Rotation QuickTime: MatrixStructure yes! QuickTime: HandlerType RunTimeSincePowerUp Apple:RunTimeValue Apple:RunTimeScale ScaleFactor35efl FocalLength no FocalLengthIn35mmFormat Composite:DigitalZoom FocalPlaneDiagonal SensorSize FocalPlaneXSize FocalPlaneYSize FocalPlaneResolutionUnit FocalPlaneXResolution FocalPlaneYResolution ExifImageWidth ExifImageHeight CanonImageWidth CanonImageHeight ImageWidth ImageHeight ShootingMode CanonExposureMode no EasyMode BulbDuration ShutterCurtainHack FlashBits no ShutterCurtainSync ShutterSpeed ExposureTime ShutterSpeedValue BulbDuration SingleShotDepthMapTiff SingleShotDepthMap no SegWidth SegHeight EXIF:CreateDate SubSecCreateDate yes SubSecTimeDigitized OffsetTimeDigitized SubSecDateTimeOriginal EXIF:DateTimeOriginal yes SubSecTimeOriginal OffsetTimeOriginal SubSecModifyDate EXIF: ModifyDate yes SubSecTime OffsetTime ThumbnailImage ThumbnailOffset yes ThumbnailLength ThumbnailTIFF SubfileType no Compression ImageWidth ImageHeight BitsPerSample

PhotometricInterpretation

StripOffsets SamplesPerPixel RowsPerStrip StripByteCounts PlanarConfiguration

Orientation

VolumeSize ISO:VolumeBlockCount no

ISO:VolumeBlockSize

WB\_RGBLevels KDC\_IFD:WhiteBalance no

WB\_RGBLevelsAuto

WB\_RGBLevelsFluorescent
WB\_RGBLevelsTungsten
WB\_RGBLevelsDaylight

WB\_RGBLevels4
WB\_RGBLevels5
WB\_RGBLevelsShade

WB\_RGBLevels KodakIFD:WhiteBalance no

WB\_RGBMul0
WB\_RGBMul1
WB\_RGBMul2
WB\_RGBMul3
WB\_RGBCoeffs0
WB\_RGBCoeffs1
WB\_RGBCoeffs2
WB\_RGBCoeffs2

KodakIFD:ColorTemperature

Kodak:WB\_RGBLevels

WB\_RGGBLevels Canon:WhiteBalance no

WB\_RGGBLevelsAsShot
WB\_RGGBLevelsAuto
WB\_RGGBLevelsDaylight
WB\_RGGBLevelsCloudy
WB\_RGGBLevelsTungsten
WB\_RGGBLevelsFluorescent
WB\_RGGBLevelsFlash
WB\_RGGBLevelsCustom
WB\_RGGBLevelsShade

WB\_RGGBLevelsKelvin

WB\_RGGBLevels WB\_RGGBLevelsUncorrected no

WB\_RGGBLevelsBlack

ZoomedPreviewImage ZoomedPreviewStart no

ZoomedPreviewLength

#### Shortcuts Tags

Shortcut tags are convenience tags that represent one or more other tag names. They are used like regular tags to read and write the information for a specified set of tags.

The shortcut tags below have been pre-defined, but user-defined shortcuts may be added via the %Image::ExifTool::UserDefined::Shortcuts lookup in the =/.ExifTool\_config file. See the

Image::ExifTool::Shortcuts documentation for more details.

Tag Name Refers To Writable
----AllDates DateTimeOriginal yes

CreateDate

ModifyDate

Canon FileName yes

Model

DateTimeOriginal ShootingMode ShutterSpeed Aperture MeteringMode

ExposureCompensation

ISO Lens

FocalLength ImageSize Quality Flash FlashType ConditionalFEC RedEyeReduction ShutterCurtainHack

WhiteBalance FocusMode Contrast Sharpness Saturation ColorTone ColorSpace

LongExposureNoiseReduction

FileSize
FileNumber
DriveMode
OwnerName
SerialNumber

ColorSpaceTags ExifIFD:ColorSpace yes

ExifIFD:Gamma

InteropIFD:InteropIndex

ICC\_Profile

Common FileName yes

FileSize Model

DateTimeOriginal

ImageSize Quality FocalLength ShutterSpeed Aperture ISO

WhiteBalance

Flash

CommonIFD0 IFD0: ImageDescription yes

IFD0:Make
IFD0:Model
IFD0:Software
IFD0:ModifyDate
IFD0:Artist
IFD0:Copyright
IFD0:Rating

IFD0:RatingPercent IFD0:DNGLensInfo IFD0:PanasonicTitle IFD0:PanasonicTitle2

IFD0:XPTitle
IFD0:XPComment
IFD0:XPAuthor
IFD0:XPKeywords
IFD0:XPSubject

ImageDataMD5ImageDataHashyesLargeTagsCanonVRDyes

DLOData EXIF

ICC\_Profile
IDCPreviewImage
ImageData

IPTC
JpgFromRaw

OriginalRawImage

OtherImage PreviewImage ThumbnailImage TIFFPreview

XML XMP

ZoomedPreviewImage

MakerNotes MakerNotes yes

MakerNoteApple MakerNoteCanon MakerNoteCasio

MakerNoteCasio2

MakerNoteDJI

MakerNoteDJIInfo

MakerNoteFLIR

MakerNoteFujiFilm

MakerNoteGE

MakerNoteGE2

MakerNoteHasselblad

MakerNoteHP

MakerNoteHP2

MakerNoteHP4

MakerNoteHP6

MakerNoteISL

MakerNoteJVC

MakerNoteJVCText

MakerNoteKodak1a

MakerNoteKodak1b

MakerNoteKodak2

MakerNoteKodak3

MakerNoteKodak4 MakerNoteKodak5

MakerNoteKodak6a

MakerNoteKodak6b

MakerNoteKodak7

MakerNoteKodak8a

MakerNoteKodak8b MakerNoteKodak8c

MakerNoteKodak9

MakerNoteKodak10

MakerNoteKodak11

MakerNoteKodak12

MakerNoteKodakUnknown

MakerNoteKyocera

MakerNoteMinolta

MakerNoteMinolta2

MakerNoteMinolta3

MakerNoteMotorola

MakerNoteNikon

MakerNoteNikon2

MakerNoteNikon3 MakerNoteNintendo

MakerNoteOlympus

MakerNoteOlympus2

MakerNoteOlympus3

MakerNoteLeica

MakerNoteLeica2

MakerNoteLeica3

MakerNoteLeica4

MakerNoteLeica5 MakerNoteLeica6

MakerNoteLeica7

MakerNoteLeica8

MakerNoteLeica9

MakerNoteLeica10

MakerNotePanasonic

MakerNotePanasonic2

MakerNotePanasonic3

MakerNotePentax

MakerNotePentax2

MakerNotePentax3

MakerNotePentax4

MakerNotePentax5

MakerNotePentax6

MakerNotePhaseOne

MakerNoteReconyx

MakerNoteReconyx2

MakerNoteReconyx3

MakerNoteRicoh

MakerNoteRicoh2

MakerNoteRicohPentax MakerNoteRicohText MakerNoteSamsung1a MakerNoteSamsung1b MakerNoteSamsung2 MakerNoteSanyo MakerNoteSanyoC4 MakerNoteSanyoPatch MakerNoteSigma MakerNoteSony MakerNoteSony2 MakerNoteSony3 MakerNoteSony4 MakerNoteSony5

MakerNoteSonyEricsson MakerNoteSonySRF MakerNoteUnknownText MakerNoteUnknownBinary MakerNoteUnknown

Nikon Model yes SubSecDateTimeOriginal

> ShutterCount LensSpec FocalLength ImageSize ShutterSpeed Aperture

ISO NoiseReduction ExposureProgram ExposureCompensation

WhiteBalance

WhiteBalanceFineTune

ShootingMode Quality MeteringMode FocusMode

ImageOptimization

ToneComp ColorHue ColorSpace HueAdjustment Saturation Sharpness Flash FlashMode

FlashExposureComp

Unsafe IFD0:YCbCrPositioning yes

> IFD0:YCbCrCoefficients IFD0:TransferFunction

ExifIFD:ComponentsConfiguration ExifIFD:CompressedBitsPerPixel

InteropIFD:InteropIndex InteropIFD:InteropVersion InteropIFD: RelatedImageWidth InteropIFD:RelatedImageHeight

ls-l FilePermissions

> FileHardLinks FileUserID FileGroupID FileSize# FileModifyDate FileName

## MWG Tags

The Metadata Working Group (MWG) recommends techniques to allow certain overlapping EXIF, IPTC and XMP tags to be reconciled when reading, and synchronized when writing. The MWG Composite tags below are designed to aid in the implementation of these recommendations. As well, the MWG defines new XMP tags which are listed in the subsequent tables

below. See

<https://web.archive.org/web/20180919181934/http://www.metadataworkinggroup.org/pd
f/mwq quidance.pdf>

for the official MWG specification.

## MWG Composite Tags

The table below lists special Composite tags which are used to access other tags based on the MWG 2.0 recommendations. These tags are only accessible when explicitly loaded, but this is done automatically by the exiftool application if MWG is specified as a group for any tag on the command line, or manually with the "-use MWG" option. Via the API, the MWG Composite tags are loaded by calling ""Image::ExifTool::MWG::Load()"".

When reading, the value of each MWG tag is Derived From the specified tags based on the MWG guidelines. When writing, the appropriate associated tags are written. The value of the IPTCDigest tag is updated automatically when the IPTC is changed if either the IPTCDigest tag didn't exist beforehand or its value agreed with the original IPTC digest (indicating that the XMP is synchronized with the IPTC). IPTC information is written only if the original file contained IPTC.

Loading the MWG module activates "strict MWG conformance mode", which has the effect of causing EXIF, IPTC and XMP in non-standard locations to be ignored when reading, as per the MWG recommendations. Instead, a "Warning" tag is generated when non-standard metadata is encountered. This feature may be disabled by setting "\$Image::ExifTool::MWG::strict = 0" in the ExifTool config file (or from your Perl script when using the API). Note that the behaviour when writing is not changed: ExifTool always creates new records only in the standard location, but writes new tags to any EXIF/IPTC/XMP records that exist.

Contrary to the EXIF specification, the MWG recommends that EXIF "ASCII" string values be stored as UTF-8. To honour this, the exiftool application sets the default internal EXIF string encoding to "UTF8" when the MWG module is loaded, but via the API this must be done manually by setting the CharsetEXIF option.

A complication of the MWG specification is that although the MWG:Creator property may consist of multiple values, the associated EXIF tag (EXIF:Artist) is only a simple string. To resolve this discrepancy the MWG recommends a technique which allows a list of values to be stored in a string by using a semicolon-space separator (with quotes around values if necessary). When the MWG module is loaded, ExifTool automatically implements this policy and changes EXIF:Artist to a list-type tag.

City IPTC:City yes  XMP-photoshop:City  XMP-iptcExt:LocationShownCity  CurrentIPTCDigest  IPTCDigest  Copyright EXIF:Copyright yes  IPTC:CopyrightNotice  XMP-dc:Rights  CurrentIPTCDigest  IPTCDigest  CurrentIPTCDigest  IPTCDigest  IPTCCOuntry-PrimaryLocationName yes  XMP-photoshop:Country	Tag Name	Derived From	Writable
XMP-iptcExt:LocationShownCity CurrentIPTCDigest IPTCDigest Copyright EXIF:Copyright yes IPTC:CopyrightNotice XMP-dc:Rights CurrentIPTCDigest IPTCDigest IPTCDigest Country IPTC:Country-PrimaryLocationName yes	City	2	yes
Copyright EXIF:Copyright yes IPTC:CopyrightNotice XMP-dc:Rights CurrentIPTCDigest IPTCDigest IPTCDigest Country IPTC:Country-PrimaryLocationName yes		1 1	nCity
Copyright EXIF:Copyright yes  IPTC:CopyrightNotice  XMP-dc:Rights  CurrentIPTCDigest  IPTCDigest  Country IPTC:Country-PrimaryLocationName yes		<del>-</del>	
IPTC:CopyrightNotice XMP-dc:Rights CurrentIPTCDigest IPTCDigest Country IPTC:Country-PrimaryLocationName yes		_	
XMP-dc:Rights CurrentIPTCDigest IPTCDigest Country IPTC:Country-PrimaryLocationName yes	Copyright	EXIF:Copyright	yes
CurrentIPTCDigest IPTCDigest Country IPTC:Country-PrimaryLocationName yes		IPTC:CopyrightNotice	
Country IPTCDigest IPTC:Country-PrimaryLocationName yes		XMP-dc:Rights	
Country IPTCDigest IPTC:Country-PrimaryLocationName yes		CurrentIPTCDigest	
Country IPTC: Country-PrimaryLocationName yes		IPTCDigest	
XMP-photoshop:Country	Country	_	tionName yes
	-	XMP-photoshop:Country	_
		XMP-iptcExt:LocationShownCountryName	
CurrentIPTCDigest			
IPTCDigest		IPTCDigest	
CreateDate Composite:SubSecCreateDate yes	CreateDate	_	te yes
EXIF:CreateDate		EXIF:CreateDate	-
IPTC:DigitalCreationDate		IPTC:DigitalCreationDate	
IPTC:DigitalCreationTime		_	

XMP-xmp:CreateDate

CurrentIPTCDigest

IPTCDigest

Creator EXIF: Artist yes+

IPTC:By-line XMP-dc:Creator CurrentIPTCDigest

IPTCDigest

DateTimeOriginal Composite:SubSecDateTimeOriginal yes

EXIF:DateTimeOriginal IPTC:DateCreated IPTC:TimeCreated

XMP-photoshop:DateCreated

CurrentIPTCDigest

IPTCDigest

Description EXIF: ImageDescription yes

IPTC:Caption-Abstract XMP-dc:Description CurrentIPTCDigest

IPTCDigest

Keywords IPTC: Keywords yes+

XMP-dc:Subject CurrentIPTCDigest

IPTCDigest

Location IPTC: Sub-location yes

XMP-iptcCore:Location

 ${\tt XMP-iptcExt:} Location Shown Sublocation$ 

CurrentIPTCDigest

IPTCDigest

ModifyDate Composite:SubSecModifyDate yes

EXIF:ModifyDate XMP-xmp:ModifyDate CurrentIPTCDigest

IPTCDigest

Orientation EXIF:Orientation yes
Rating XMP-xmp:Rating yes
State IPTC:Province-State yes

XMP-photoshop:State

XMP-iptcExt:LocationShownProvinceState

CurrentIPTCDigest

IPTCDigest

## MWG Collections Tags

Collections metadata defined by the MWG 2.0 specification. See <a href="https://web.archive.org/web/20180919181934/http://www.metadataworkinggroup.org/pdf/mwg\_guidance.pdf">https://www.metadataworkinggroup.org/pdf/mwg\_guidance.pdf</a>

for the official specification.

These tags belong to the ExifTool XMP-mwg-coll family 1 group.

Tag Name Writable

Collections MWG CollectionInfo Struct+

CollectionName string\_+ CollectionURI string\_+

## MWG CollectionInfo Struct

Field Name Writable
----CollectionName string
CollectionURI string

## MWG Keywords Tags

Hierarchical keywords metadata defined by the MWG 2.0 specification. ExifTool unrolls keyword structures to an arbitrary depth of 6 to allow individual levels to be accessed with different tag names, and to avoid infinite recursion. See

<https://web.archive.org/web/20180919181934/http://www.metadataworkinggroup.org/pd</pre>

f/mwg\_guidance.pdf>

for the official specification.

These tags belong to the ExifTool XMP-mwg-kw family 1 group.

KeywordInfo MWG KeywordInfo Struct HierarchicalKeywords MWG KeywordStruct Struct\_+ HierarchicalKeywords1Applied HierarchicalKeywords1Children MWG KeywordStruct Struct\_+ HierarchicalKeywords2Applied boolean\_+ HierarchicalKeywords2Children MWG KeywordStruct Struct\_+ HierarchicalKeywords3Applied boolean\_+ HierarchicalKeywords3Children MWG KeywordStruct Struct\_+ HierarchicalKeywords4Applied boolean\_+ HierarchicalKeywords4Children MWG KeywordStruct Struct\_+ HierarchicalKeywords5Applied boolean\_+ HierarchicalKeywords5Children MWG KeywordStruct Struct\_+ HierarchicalKeywords6Applied boolean\_+ Hierarchical Keywords 6 string + HierarchicalKeywords5 string\_+ HierarchicalKeywords4 string + HierarchicalKeywords3 string + HierarchicalKeywords2 string\_+ HierarchicalKeywords1 string + MWG KeywordInfo Struct Field Name Writable Hierarchy MWG KeywordStruct Struct+ MWG KeywordStruct Struct Field Name Writable \_\_\_\_\_ \_\_\_\_\_ Applied boolean Children MWG KeywordStruct Struct+ Keyword string

## MWG Regions Tags

Image region metadata defined by the MWG 2.0 specification. These tags may be accessed without the need to load the MWG Composite tags above. See

<https://web.archive.org/web/20180919181934/http://www.metadataworkinggroup.org/pd</pre> f/mwq quidance.pdf>

for the official specification.

These tags belong to the ExifTool XMP-mwg-rs family 1 group.

Tag Name Writable RegionInfo MWG RegionInfo Struct RegionAppliedToDimensions Dimensions Struct\_ RegionAppliedToDimensionsH real RegionAppliedToDimensionsUnit string\_ RegionAppliedToDimensionsW MWG RegionStruct Struct\_+ RegionList RegionArea Area Struct\_+ RegionAreaD real\_+ real\_+ RegionAreaH string\_+ RegionAreaUnit RegionAreaW real\_+ real\_+ RegionAreaX RegionAreaY real\_+ string\_+ RegionBarCodeValue RegionDescription string + RegionExtensions MWG Extensions Struct\_+

RegionFocusUsage string\_+ RegionName string\_+ RegionRotation real\_+ RegionSeeAlso string\_+ RegionType string\_+

## MWG RegionInfo Struct

Field Name Writable

AppliedToDimensions Dimensions Struct

RegionList MWG RegionStruct Struct+

#### MWG RegionStruct Struct

Writable Field Name Area Struct Area BarCodeValue string Description string Extensions MWG Extensions Struct

FocusUsage string Name string Rotation real Type

string SeeAlso string

## MWG Extensions Struct

This structure may contain any top-level XMP tags, but none have been pre-defined in ExifTool. Since no flattened tags have been predefined, RegionExtensions is writable only as a structure (eq. "{xmp-dc:creator=me,rating=5}"). Fields for this structure are identified using the standard ExifTool tag name (with optional leading group name, and/or trailing language code, and/or trailing "#" symbol to disable print conversion).

Field Name Writable [no tags known]

## NOTES

This document generated automatically by Image::ExifTool::BuildTagLookup.

#### **AUTHOR**

Copyright 2003-2025, Phil Harvey (philharvey66 at gmail.com)

This library is free software; you can redistribute it and/or modify it under the same terms as Perl itself.

#### SEE ALSO

Image::ExifTool(3pm)

perl v5.18.4 2025-03-07 TAGNAMES (1)